



PP 1: Display Stock/Requirements List

Exercise Use the SAP Fiori Launchpad to display the Stock/Requirements List.

Time 5 min

Task Review the material status of your Deluxe Touring bike (finished good) in the Dallas plant using the Stock/Requirements list.

Name (Position) Lars Iseler (Shop Floor Worker 2)

The Stock/Requirements list contains up-to-date information on the current status of inventory on hand, requirements, and receipts. It is a dynamic list that allows you to view changes made to material status.

Stock/Requirements List


To review the material status, in the space *Production Planning and Execution* space and the role of *Shop Floor Worker*, use the app *Monitor Stock / Requirements List*.

Fiori App



Firstly, you need to find the material number(s) for your Deluxe Touring bikes. For this, click the *Material* field and press **F4** (or click on the search icon \square next to the field). This will open the *Material Number* (1) search screen.

F4



Go to the T: *Material by Material Type* tab. Use the \checkmark icon to display a list of all search tabs available.

In the *Material Type* field, select **Finished Product** (**FERT**). In order to display your Deluxe Touring bikes only, you need to define two more search criteria. First, in the *Material Description* field type **Deluxe Touring***. Second, in the *Material* field (which is the field for the unique material

Material by Material Type

Finished Product


Deluxe Touring*

© SAP UCC Magdeburg

*###


number) type *###. Remember to replace ### with your three-digit number, e.g., *014 if your number is 014.

Compare your entries with the screen below before pressing Enter or clicking on ^{Go} to start the search.




The result of this search should give you a list of all:

- a) finished goods,
- b) names (with a short description) that start with Deluxe Touring,
- c) material numbers that end with your number (###).



You should get a list of three different Deluxe Touring bikes – black, red and silver (please note that the material numbers in your screen will be different). Double-click on your black Touring bike which will copy its unique material number (**DXTR1**###) into the *Material* field.


In addition to the material number, in the *Plant* field select Global Bike's manufacturing facility in Dallas (**DL00**).



DXTR1###

DL00

Then, click on Continue. You should be displayed a screen similar to the one





PP 2: Display Bill of Material

Exercise Use the SAP Fiori Launchpad to display a bill of material.

Time 10 min

Task Review the components of your black Deluxe Touring bike and the components of the Touring Aluminum Wheel Assembly within the finished bike bill of material.

Name (Position) Jun Lee (Production Manager)

A bill of material (BOM) is a list of the components that are needed to create a given product. The list contains the description, the quantity, and unit of measure. The BOM can contain items of different item categories such as stock items, non-stock items, document items, and text items.

Bill of Material (BOM)


To review a bill of material, in the space Production Planning and Execution space and the role of *Production Manager*, use the app *Maintain Bill Of Material – Create, change & display.*

Fiori App



DL00

Enter for *material number* **DXTR1**### and **DL00** for the *plant* in **Dallas**.



© SAP UCC Magdeburg Page 4


DXTR1###

Production

Press Enter or Go to run the search. You will be shown the parts list of your black Deluxe Touring Bike.




Click somewhere in the row you found to open the Bill of Material. (Please note that the material numbers in your screen will be different).



Scroll to the right to view more information about each component. The column *Assembly Indicator* highlights components that have their own BOMs. In this case, the component *Touring Aluminum Wheel* serves as an example.



Click View in the Assembly Indicator column to open the parts list of the Touring Aluminum Wheel.



Repeat the procedure for your red and the silver Deluxe Touring bike to identify the differences in their bills of materials. You can also use multiple windows or tabs of your browser to better compare the BOMs.

Click SAP Fiori Launchpad.



PP 3: Display Multi-Level Bill of Materials

Exercise Use the SAP Fiori Launchpad to display a multi-level BOM.

Time 5 min

Task Review the BOM for your black Deluxe Touring bike from a multi-level hierarchy level.

Name (Position) Jun Lee (Production Manager)

To display a multi-level BOM, in the space *Production Planning and Execution* space and the role of *Production Manager*, use the app *Multilevel BOM*.


Fiori App



In the following screen, enter (or find) *Material* **DXTR1**### (replace ### with your number), *Plant* **DL00**, and *BOM Application* **PP01** (Production-General). Under *Selection* enter **1** for Required quantity.

DXTR1### DL00 PP01 1

Then, click on to display the BOM structure for your bike valid today. If a pop-up opens, click Continue.



You will now see a summarized list of all materials required for both the Deluxe Touring Bike (DXTR1##) and the Touring Aluminum Bike (TRWA1##). In contrast to the previous task, in which individual parts lists were considered, all materials for the touring aluminum bike are now also multiplied by the corresponding quantity required. This means that the total consumption of all materials can be examined across all stages.


Click on to go back to the initial screen. There, you click on . On the following screen, in the *Display* field group select **Variable list**.

Variable list




Keep the fields that were filled in by the system and click on to display the list in the newly selected representation.

You will get an overview of all used items.



In addition to a different display format, the interaction options have also changed compared to the previous display. Select the *TRWA1##* component and click





PP 4: Display Routing

Exercise Use SAP Fiori Launchpad to display a routing.

Time 10 min

Task Review the routing for your black Deluxe Touring bike.

Name (Position) Jun Lee (Production Manager)

A routing is a series of sequential operations that are carried out to produce an end product. Routings contain information about where work needs to be performed, steps that need to be completed, and timelines assigned for each operation.

Routing

To review a routing, in the space *Production Planning and Execution* space and the role of *Production Manager*, use the app *Display Routing*.


Fiori App

Display Routing

Enter Material **DXTR1**### and Plant **DL00**.

DXTR1### DL00

Then, click on operations to display the following list of operations.



Select Allocation to display the list of components. If you don't see the button Allocation follow the path Menu ▶ Goto ▶ Allocation.


Note None of the components is specifically assigned to an operation. The corresponding *Activity* column is empty for each component.




Select operation to go back to the operation overview. Then find the following system menu item:

Menu ► Extras ► Scheduling ► Schedule

A popup for setting the scheduling appears. Enter **1** as the scheduling type and **10** as the lot size.




Press . In the following popup, select as *overview var.* **00000000001** (operation segments). You can also use the value help for this.



Press again. An overview of all operations, the latest start times and the respective setup, machining and teardown times is displayed.

1 10

00000000001





PP 5: Display Work Center

Exercise Use the SAP Fiori Launchpad to display a work center.

Time 15 min

Task Review a work center in Global Bike's plant in Dallas.

Name (Position) Jun Lee (Production Manager)

A work center is a location where operations are carried out for a production order. Capacities (setup, machine, and labor) are assigned to work centers so that they can be allocated and consumed within an order in a controlled and predictable manner. The work center capacity is created in and assigned to a single work center.

Work center


To review a work center and the capacity assigned to it, in the space *Production Planning and Execution* space and the role of *Production Manager*, use the app *Display Work Center*.

Fiori App




Enter *Plant* **DL00**. In the *Work center* field, use the **F4** help and choose Enter to display all work centers in Dallas. Then click in the *Work center* field and select the value help icon \Box .

DL00 F4



Accept the default settings and press to display all workstations in Dallas.



In the search results, click on the **DL Assembly** work center to select it and press ok to copy its number (**ASSY1000**).




Back in the Display Work Center: Initial Screen press Basic Data

On the Basic Data tab, find out who is the person responsible.

On the *Default Values* tab, click in the *Control key* field (**ASSY**) and select the value help icon . In the following popup, the entry Routing/Ref. op. set – internal proc. (**ASSY**) is already selected.

ASSY1000

ASSY



**Operation Quartity: 1 ** Base Quartity: 1 ** No. of Spites: 2 ** Standard values	Test Formula	×
Standard values Values for internal processing Setup: 7 MEN Normal duration: Work: MEN Number of employees: 1.00 Number of employees: 1.00 Number: 1 Then, select: The total duration for the specified operation quantity is now determined on the basis of the standard values. Test Formula Setup: Durat: 7.000 MIN Process. Durat: 3.500 MIN Teardown Dur.: 0.000 MIN Tot. Duratn: 10.500 MIN Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select: End Formula Test to go back.	General values	
Standard values Values for internal processing Setup: 7 MEN Normal duration: Work: MEN Number of employees: 1.00 Number of employees: 1.00 Number: 1 Then, select: The total duration for the specified operation quantity is now determined on the basis of the standard values. Test Formula Setup: Durat: 7.000 MIN Process. Durat: 3.500 MIN Teardown Dur.: 0.000 MIN Tot. Duratn: 10.500 MIN Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select: End Formula Test to go back.	* Operation Quantity: 1	EA
Standard values Values for internal processing		
Standard values Values for internal processing Normal duration Normal duratio		
Setup: 7 MIN Normal duration: Work: Number of employees: 1.00 Number: 1 Then, select	" No. of Spitts. Z	
Then, select	Standard values	Values for internal processing
Then, select. The total duration for the specified operation quantity is now determined on the basis of the standard values. Test Formula Duration with Operation Segments Setup Durat: [7.000 MIN Process. Durat: [3.500 MIN Teardown Dur.: [0.000 MIN Tot. Duration of Internal Processing Duration of Internal Processing Duration Int. Process.: [0.000 MIN MIN Tot. Duration of Internal Processing Duration of Internal Processing Duration of Internal Processing Duration of Internal Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Setup: 7 MIN	Normal duration:
Then, select . The total duration for the specified operation quantity is now determined on the basis of the standard values. Test Formula Duration with Operation Segments Setup Durat: 7.000 MIN Process. Durat: 3.500 MIN Teardown Dur.: 0.000 MIN Tot. Duratn: 10.500 MIN Duration of Internal Processing Duration Int. Process: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Machine: MIN	Work:
Then, select. The total duration for the specified operation quantity is now determined on the basis of the standard values. Test Formula Duration with Operation Segments Setup Durat: [7.000 MIN Process. Durat: [3.500 MIN Teardown Dur.: [0.000 MIN Tot. Duratri: 10.500 MIN MIN Tot. Duratri: 10.500 MIN MIN Tot. Duration Int. Process: [0.000 MIN	Labor: 7 MIN	Number of employees: 1.00
Duration with Operation Segments Setup Durat: 7.000 MIN Process. Durat: 3.500 MIN Teardown Dur: 0.000 MIN Duration of Internal Processing Duration Int. Process: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.		Number: 1
Setup Durat:: 7.000 MIN Process. Durat:: 3.500 MIN Teardown Dur.: 0.000 MIN Tot. Duratn: 10.500 MIN Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	determined on the basis of the standard values.	
Process. Durat.: 3.500 MIN Teardown Dur.: 0.000 MIN Tot. Duratn: 10.500 MIN Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on ✓ to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Duration with Operation Segments	
Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Setup Durat.:	7.000 MIN
Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Process. Durat.:	3.500 MIN
Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on ✓ to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Teardown Dur.:	0.000 MIN
Duration of Internal Processing Duration Int. Process.: 0.000 MIN Click on ✓ to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.		
Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Tot. Duratn:	10.500 MIN
Click on to continue. The formula for process duration is: Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Duration of Internal Processing	
Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	Duration Int. Process.:	0.000 MIN
	Process Duration = (((Labor * Operation quantity) / Base quantity) / Operation splits) Did the Processing formula work correctly? Select End Formula Test to go back.	