# 16.15. errno — Standard errno system symbols

This module makes available standard errno system symbols. The value of each symbol is the corresponding integer value. The names and descriptions are borrowed from linux/include/errno.h, which should be pretty all-inclusive.

## errno.errorcode

Dictionary providing a mapping from the errno value to the string name in the underlying system. For instance, errno.errorcode[errno.EPERM] maps to 'EPERM'.

To translate a numeric error code to an error message, use os.strerror().

Of the following list, symbols that are not used on the current platform are not defined by the module. The specific list of defined symbols is available as errno.errorcode.keys(). Symbols available can include:

#### errno. EPERM

Operation not permitted

#### errno. ENOENT

No such file or directory

# errno. ESRCH

No such process

#### errno. EINTR

Interrupted system call.

**See also:** This error is mapped to the exception InterruptedError.

errno. EIO

I/O error

#### errno. ENXIO

No such device or address

errno. E2BIG

Arg list too long

errno. ENOEXEC

#### Exec format error

#### errno. EBADF

Bad file number

# errno. ECHILD

No child processes

#### errno. EAGAIN

Try again

# errno. ENOMEM

Out of memory

#### errno. EACCES

Permission denied

#### errno. EFAULT

Bad address

# errno. ENOTBLK

Block device required

#### errno. EBUSY

Device or resource busy

# errno. EEXIST

File exists

# errno. EXDEV

Cross-device link

#### errno. ENODEV

No such device

# errno. ENOTDIR

Not a directory

# errno. EISDIR

Is a directory

# errno. EINVAL

Invalid argument

errno. ENFILE

#### File table overflow

#### errno. EMFILE

Too many open files

# errno. **ENOTTY**

Not a typewriter

#### errno. ETXTBSY

Text file busy

# errno. EFBIG

File too large

## errno. ENOSPC

No space left on device

# errno. ESPIPE

Illegal seek

# errno. EROFS

Read-only file system

#### errno. EMLINK

Too many links

# errno. EPIPE

Broken pipe

# errno. EDOM

Math argument out of domain of func

# errno. ERANGE

Math result not representable

#### errno. EDEADLK

Resource deadlock would occur

# errno. ENAMETOOLONG

File name too long

# errno. ENOLCK

No record locks available

# errno. ENOSYS

# Function not implemented

#### errno. **ENOTEMPTY**

Directory not empty

#### errno. ELOOP

Too many symbolic links encountered

# errno. EWOULDBLOCK

Operation would block

# errno. ENOMSG

No message of desired type

#### errno. **EIDRM**

Identifier removed

#### errno. ECHRNG

Channel number out of range

#### errno. EL2NSYNC

Level 2 not synchronized

# errno. EL3HLT

Level 3 halted

# errno. EL3RST

Level 3 reset

# errno. ELNRNG

Link number out of range

#### errno. EUNATCH

Protocol driver not attached

#### errno. ENOCSI

No CSI structure available

#### errno. EL2HLT

Level 2 halted

# errno. EBADE

Invalid exchange

errno. EBADR

# Invalid request descriptor

#### errno. EXFULL

Exchange full

# errno. ENOANO

No anode

# errno. EBADRQC

Invalid request code

#### errno. EBADSLT

Invalid slot

# errno. EDEADLOCK

File locking deadlock error

# errno. EBFONT

Bad font file format

# errno. ENOSTR

Device not a stream

# errno. ENODATA

No data available

# errno. ETIME

Timer expired

# errno. ENOSR

Out of streams resources

#### errno. ENONET

Machine is not on the network

#### errno. ENOPKG

Package not installed

# errno. EREMOTE

Object is remote

# errno. ENOLINK

Link has been severed

errno. EADV

#### Advertise error

#### errno. ESRMNT

Srmount error

#### errno. ECOMM

Communication error on send

#### errno. EPROTO

Protocol error

#### errno. EMULTIHOP

Multihop attempted

# errno. EDOTDOT

RFS specific error

#### errno. EBADMSG

Not a data message

#### errno. EOVERFLOW

Value too large for defined data type

# errno. ENOTUNIQ

Name not unique on network

#### errno. EBADFD

File descriptor in bad state

# errno. EREMCHG

Remote address changed

#### errno. ELIBACC

Can not access a needed shared library

#### errno. ELIBBAD

Accessing a corrupted shared library

#### errno. ELIBSCN

.lib section in a.out corrupted

#### errno. ELIBMAX

Attempting to link in too many shared libraries

# errno. ELIBEXEC

# Cannot exec a shared library directly

# errno. EILSEQ

Illegal byte sequence

#### errno. ERESTART

Interrupted system call should be restarted

#### errno. ESTRPIPE

Streams pipe error

#### errno. EUSERS

Too many users

#### errno. ENOTSOCK

Socket operation on non-socket

# errno. EDESTADDRREQ

Destination address required

#### errno. EMSGSIZE

Message too long

#### errno. EPROTOTYPE

Protocol wrong type for socket

#### errno. ENOPROTOOPT

Protocol not available

# errno. EPROTONOSUPPORT

Protocol not supported

#### errno. ESOCKTNOSUPPORT

Socket type not supported

# errno. EOPNOTSUPP

Operation not supported on transport endpoint

#### errno. EPFNOSUPPORT

Protocol family not supported

#### errno. EAFNOSUPPORT

Address family not supported by protocol

# errno. EADDRINUSE

# Address already in use

#### errno. EADDRNOTAVAIL

Cannot assign requested address

#### errno. ENETDOWN

Network is down

#### errno. ENETUNREACH

Network is unreachable

#### errno. ENETRESET

Network dropped connection because of reset

#### errno. ECONNABORTED

Software caused connection abort

#### errno. ECONNRESET

Connection reset by peer

#### errno. ENOBUFS

No buffer space available

#### errno. EISCONN

Transport endpoint is already connected

#### errno. ENOTCONN

Transport endpoint is not connected

# errno. ESHUTDOWN

Cannot send after transport endpoint shutdown

#### errno. ETOOMANYREFS

Too many references: cannot splice

#### errno. ETIMEDOUT

Connection timed out

#### errno. ECONNREFUSED

Connection refused

# errno. EHOSTDOWN

Host is down

# errno. EHOSTUNREACH

#### No route to host

# errno. EALREADY

Operation already in progress

# errno. EINPROGRESS

Operation now in progress

# errno. ESTALE

Stale NFS file handle

# errno. EUCLEAN

Structure needs cleaning

# errno. **ENOTNAM**

Not a XENIX named type file

# errno. **ENAVAIL**

No XENIX semaphores available

# errno. EISNAM

Is a named type file

# errno. EREMOTEIO

Remote I/O error

# errno. EDQUOT

Quota exceeded