



1. VM Creation and Networking

1. In the Azure Portal, create a new Virtual Machine selecting **Ubuntu Server** as the image.
2. Under the *Networking* tab, ensure a **Public IP** is created and assigned.
3. Enable **SSH (22)** in the inbound port rules to allow remote access.



Microsoft Azure

Search resources, services, and docs (G+/I)

Copilot

koltehar@outlook.com

Home > Create a resource

Create a virtual machine

Help me choose the right VM size for my workload Help me create a VM optimized for high availability Help me create a low cost VM

Hibernate does not currently support Trusted launch and Confidential virtual machines for Linux images. [Learn more](#)

Administrator account

Authentication type

☒ SSH public key
 ☐ Password

Azure now automatically generates an SSH key pair for you and allows you to store it for future use. It is a fast, simple, and secure way to connect to your virtual machine.

Username *

SSH public key source

SSH Key Type

☒ RSA SSH Format
 ☐ Ed25519 SSH Format

Ed25519 provides a fixed security level of no more than 128 bits for 256-bit key, while RSA could offer better security with keys longer than 3072 bits.

Key pair name *

Inbound port rules

Select which virtual machine network ports are accessible from the public internet. You can specify more limited or granular network access on the Networking tab.

Public inbound ports *

☐ None
 ☒ Allow selected ports

Select inbound ports *

This will allow all IP addresses to access your virtual machine. This is only recommended for testing. Use the Advanced controls in the Networking tab to create rules to limit inbound traffic to known IP addresses.

< Previous Next: Disks > Review + create

Give feedback

Microsoft Azure

Search resources, services, and docs (G+/I)

Copilot

koltehar@outlook.com

Home > Create a resource > Create a virtual machine

Create a new disk

Create a new disk to store applications and data on your VM. Disk pricing varies based on factors including disk size, storage type, and number of transactions. [Learn more](#)

Name *

Source type *

Size *

4 GiB (P1 performance tier)
 Premium SSD LRS
 [Change size](#)

Key management

Enable shared disk ☐ Yes ☒ No

Delete disk with VM ☒

OK

Give feedback

2. Storage: Premium SSD

- Go to the *Disks* tab and select **Create and attach a new disk**.
- Choose **Premium SSD** for the storage type, then finish the VM deployment.
- Once the VM is running, SSH into it and use *fdisk* and *mount* commands to initialize and mount the SSD to a local directory.

Microsoft Azure

Search resources, services, and docs (G+/I)

Copilot

kolteetushar@outlook.com
DEFAULT DIRECTORY (COLTEETUS...)

Home > Create a resource

Create a virtual machine

Help me choose the right VM size for my workloadHelp me create a VM optimized for high availabilityHelp me create a low cost VM

VM disk encryption

Azure disk storage encryption automatically encrypts your data stored on Azure managed disks (OS and data disks) at rest by default when persisting it to the cloud.

Encryption at host

Encryption at host is not registered for the selected subscription. [Learn more](#)

OS disk

OS disk size

Image default (30 GiB)

OS disk type *

Standard HDD (locally-redundant storage)

The selected VM size supports premium disks. We recommend Premium SSD for high IOPS workloads. Virtual machines with Premium SSD disks qualify for the 99.9% connectivity SLA.

Delete with VM

Key management

Platform-managed key

Enable Ultra Disk compatibility

Data disks for Ims-prac-vm

You can add and configure additional data disks for your virtual machine or attach existing disks. This VM also comes with a temporary disk.

LUN	Name	Size (GiB)	Disk type	Host caching	Delete with VM
0	Ims-prac-vm_DataDis...	4	Premium SSD LRS	None	

Create and attach a new diskAttach an existing disk

Advanced

< PreviousNext : Networking >Review + create

Give feedback

Microsoft Azure

Search resources, services, and docs (G+/I)

Copilot

kolteetushar@outlook.com
DEFAULT DIRECTORY (COLTEETUS...)

Home > Create a resource

Create a virtual machine

Help me choose the right VM size for my workloadHelp me create a VM optimized for high availabilityHelp me create a low cost VM

Network interface

When creating a virtual machine, a network interface will be created for you.

Virtual network *

(new) Ims-prac-vm-vnet

Create new

Subnet *

(new) default (10.0.0.0/24)

Public IP

(new) Ims-prac-vm-ip

Create new

Public IP addresses have a nominal charge. [Estimate price](#)

NIC network security group

None

Basic

Advanced

Public inbound ports *

None

Allow selected ports

Select inbound ports *

SSH (22)

This will allow all IP addresses to access your virtual machine. This is only recommended for testing. Use the Advanced controls in the Networking tab to create rules to limit inbound traffic to known IP addresses.

Delete public IP and NIC when VM is deleted

Enable accelerated networking

The resource provider 'Microsoft.Network' should be registered in order to enable accelerated networking. [Learn more](#)

Load balancing

< PreviousNext : Management >Review + create

Give feedback

Microsoft Azure

Search resources, services, and docs (G+)

Copilot

kolteharshar@outlook.com

Home > Create a resource

Create a virtual machine

Help me choose the right VM size for my workload Help me create a VM optimized for high availability Help me create a low cost VM

Validation passed

Basics Disks Networking Management Monitoring Advanced Tags Review + create

Price

1 X Standard B1s
by Microsoft
[Terms of use](#) [Privacy policy](#)

Subscription credits apply ⓘ
0.0112 USD/hr
[Pricing for other VM sizes](#)

TERMS

By clicking "Create", I (a) agree to the legal terms and privacy statement(s) associated with the Marketplace offering(s) listed above; (b) authorize Microsoft to bill my current payment method for the fees associated with the offering(s), with the same billing frequency as my Azure subscription; and (c) agree that Microsoft may share my contact, usage and transactional information with the provider(s) of the offering(s) for support, billing and other transactional activities. Microsoft does not provide rights for third-party offerings. See the Azure Marketplace [Terms](#) for additional details.

Name

Preferred e-mail address

Preferred phone number

⚠ You have set SSH port(s) open to the internet. This is only recommended for testing. If you want to change this setting, go back to Basics tab.

Basics

Subscription Azure for Students

Resource group (new) lms-vm

< Previous Next > Create

[Download a template for automation](#) [Give feedback](#)

3. Remote Access

7. Locate your **Public IP address** on the VM Overview page.
8. Connect via terminal using: `ssh -i <private-key-path> azureuser@<VM-Public-IP>.`

```

azureuser@lms-prac-vm: ~
PS C:\Windows\system32> ssh -i "C:\Users\tushar.kolte\Downloads\lms-prac-vm_key.pem" azureuser@135.235.178.186
The authenticity of host '135.235.178.186 (135.235.178.186)' can't be established.
ED25519 key fingerprint is SHA256:ipIP+F310LaXL0YHc4FApyzPYzUbfdWIyKglQe8LCmk.
This key is not known by any other names.
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
Warning: Permanently added '135.235.178.186' (ED25519) to the list of known hosts.
Welcome to Ubuntu 24.04.4 LTS (GNU/Linux 6.17.0-1008-azure x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

System information as of Wed Apr  1 05:48:36 UTC 2026

System load:  0.02          Processes:      115
Usage of /:   5.7% of 28.0GB Users logged in: 0
Memory usage: 29%          IPv4 address for eth0: 10.0.0.4
Swap usage:   0%

Expanded Security Maintenance for Applications is not enabled.

0 updates can be applied immediately.

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

The list of available updates is more than a week old.
To check for new updates run: sudo apt update
  
```

```
azureuser@lms-prac-vm: ~  
System information as of Wed Apr 1 05:48:36 UTC 2026  
  
System load: 0.02      Processes:      115  
Usage of /: 5.7% of 28.02GB Users logged in: 0  
Memory usage: 29%     IPv4 address for eth0: 10.0.0.4  
Swap usage: 0%  
  
Expanded Security Maintenance for Applications is not enabled.  
  
0 updates can be applied immediately.  
  
Enable ESM Apps to receive additional future security updates.  
See https://ubuntu.com/esm or run: sudo pro status  
  
The list of available updates is more than a week old.  
To check for new updates run: sudo apt update  
  
The programs included with the Ubuntu system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by  
applicable law.  
  
To run a command as administrator (user "root"), use "sudo <command>".  
See "man sudo_root" for details.  
  
azureuser@lms-prac-vm:~$ |
```

```
Enable ESM Apps to receive additional future security updates.  
See https://ubuntu.com/esm or run: sudo pro status  
  
The list of available updates is more than a week old.  
To check for new updates run: sudo apt update  
  
The programs included with the Ubuntu system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by  
applicable law.  
  
To run a command as administrator (user "root"), use "sudo <command>".  
See "man sudo_root" for details.  
  
azureuser@lms-prac-vm:~$ lsblk  
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS  
sda          8:0    0   4G  0 disk  
sdb          8:16   0   4G  0 disk  
└─sdb1       8:17   0   4G  0 part /mnt  
sdc          8:32   0  30G  0 disk  
├─sdc1       8:33   0  29G  0 part /  
├─sdc14      8:46   0   4M  0 part  
├─sdc15      8:47   0  106M  0 part /boot/efi  
└─sdc16     259:0   0  913M  0 part /boot  
sr0         11:0    1 630K  0 rom  
  
azureuser@lms-prac-vm:~$ |
```

Microsoft Azure

Search resources, services, and docs (G+J)

Copilot

kolhehshar@outlook.com
CURRENT DIRECTORY: AWS/STUD...

Home

Ims-prac-vm

Virtual machine

Help me copy this VM in any region

Manage this VM with Azure CLI

Search

Standard HDD OS disks will be retired on September 8, 2028. →

Help me copy this VM in any region

Connect

Start

Restart

Stop

Hibernate

Capture

Delete

Refresh

Scale

Open in mobile

Feedback

CU / PS

Essentials

Resource group (mova) : [Ims-prac-vm](#)

Status : Running

Location : Central India (Zone 1)

Subscription (mova) : [Azure for Students](#)

Subscription ID : 347950b0-bcad-4cc0-bfaa-78093bcbfe66

Availability zone : 1

Operating system : Linux (ubuntu 24.04)

Size : Standard B1s (1 vcpu, 1 GiB memory)

Primary NIC public IP : [135.235.178.186](#)
[1 associated public IPs](#)

Virtual network/subnet : [Ims-prac-vm-vnet/default](#)

DNS name : [Not configured](#)

Health state : -

Time created : 4/1/2026, 5:42 AM UTC

Tags (edit) : [Add tags](#)

Properties

Monitoring

Capabilities (7)

Recommendations

Tutorials

Virtual machine

Computer name : Ims-prac-vm

Operating system : Linux (ubuntu 24.04)

VM generation : V2

VM architecture : x64

Agent status : Ready

Agent version : 2.15.1.3

Hibernation : Disabled

Host group : -

Host : -

Proximity placement group : -

Networking

Public IP address : [135.235.178.186](#) (Network interface Ims-prac-vm/781_21)
[1 associated public IPs](#)

Public IP address (IPv6) : -

Private IP address : 10.0.0.4

Private IP address (IPv6) : -

Virtual network/subnet : [Ims-prac-vm-vnet/default](#)

DNS name : [Configure](#)

Size

Size : Standard B1s

Overview

Activity log

Access control (IAM)

Tags

Diagnose and solve problems

Monitor

Resource visualizer

Connect

Networking

Settings

Availability + scale

Security

Backup + disaster recovery

Operations

Monitoring

Automation

Help

Add or remove favorites by pressing Ctrl+V+35 (Ft+V)