Server Cheatsheet

Phil

September 12, 2026

1 Adresses et liens

Adresses ip

adresse ip local : http://192.168.1.238

adresse ip tailscale : http://100.79.190.77/

Ports

homepage : 8082 / http://192.168.1.238:8082 / https://tysufa.com immich : 2283 / http://192.168.1.238:2283

2 Tunnel cloudflare

gerer les tunnels sur cloudflare

Connecter un tunnel sur nixos

copier le token (format : eyJhIjoi**********eCJ9) puis executer cette commande pour obtenir 3 secrets : `echo "eyJhIjoi**********eCJ9" | base64 -d`

placer ensuite les 3 secrets dans les champs suivants :

- “AccountTag” (“a”)
- “TunnelID” (“t”)
- “TunnelSecret” (“s”)

que l’on peut modifier avec la commande `nix-shell -p sops --run "sops secrets/secrets.yaml"`

3 Sops

Les secrets sont ecris dans le dossier accessible uniquement pour root /run/secrets

4 Backups

exporting local backups

to backup a restic directory from a local machine to a distant one : `restic -r sftp:tysufa@192.168.1.238:/mnt/storage/Backups/restic copy --from-repo /local/restic/repo`

Automaticaly backing up server to external drives

This code adds a udev rule to automatically call our systemd service when the specified hard drive (ID_FS_LABEL=“offline-backup”) is connected to the server

```
services.udev.extraRules =
''
  ACTION=="add", SUBSYSTEM=="block", ENV{ID_FS_LABEL}=="offline-backup", TAG+="systemd", ENV{SYSTEMD_WANTS}+="restic-external-backup.service"
'';
```

The job of our systemd service is to :

1. Mount the hdd on the server
2. Execute the restic backup commands on all the folders we want to backup `${pkgs.restic}/bin/restic -r $RESTIC_REPOSITORY backup /mnt/storage/zotero/ /mnt/storage/shared-files/ /mnt/storage/audiobookshelf/`
3. Unmount the hdd and warn the user that everything is over and so the hdd can be unplugged

restic service

there is a restic service that saves daily :

- zotero
- immich