```
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
!
hostname Switch/Equipos1-5
!
enable secret 5 $1$mERr$hx5rVt7rPNoS4wqbXKX7m0
!
!
!
ip ssh version 2
ip domain-name reto.mx
!
username Switch/Equipos1-5 privilege 1 password 7 0822455D0A16
!
!
!
spanning-tree mode pvst
spanning-tree extend system-id
!
interface FastEthernet0/1
 description conectado a Switch-Medio
 switchport mode trunk
!
interface FastEthernet0/2
 description interfaces vlan 10
 switchport access vlan 10
 switchport mode access
!
interface FastEthernet0/3
 description interfaces vlan 10
 switchport access vlan 10
 switchport mode access
!
interface FastEthernet0/4
 description interfaces vlan 10
 switchport access vlan 10
 switchport mode access
!
interface FastEthernet0/5
 description interfaces vlan 20
 switchport access vlan 20
 switchport mode access
!
interface FastEthernet0/6
 description interfaces vlan 20
 switchport access vlan 20
 switchport mode access
!
interface FastEthernet0/7
 description interfaces vlan 20
 switchport access vlan 20
 switchport mode access
!
interface FastEthernet0/8
 description interfaces vlan 30
 switchport access vlan 30
```

```
 switchport mode access
!
interface FastEthernet0/9
 description interfaces vlan 30
 switchport access vlan 30
 switchport mode access
!
interface FastEthernet0/10
 description interfaces vlan 30
 switchport access vlan 30
 switchport mode access
!
interface FastEthernet0/11
 description interfaces vlan 40
 switchport access vlan 40
 switchport mode access
!
interface FastEthernet0/12
 description interfaces vlan 40
 switchport access vlan 40
 switchport mode access
!
interface FastEthernet0/13
 description interfaces vlan 40
 switchport access vlan 40
 switchport mode access
!
interface FastEthernet0/14
 description interfaces vlan 50
 switchport access vlan 50
 switchport mode access
!
interface FastEthernet0/15
 description interfaces vlan 50
 switchport access vlan 50
 switchport mode access
!
interface FastEthernet0/16
 description interfaces vlan 50
 switchport access vlan 50
 switchport mode access
!
interface FastEthernet0/17
!
interface FastEthernet0/18
!
interface FastEthernet0/19
!
interface FastEthernet0/20
!
interface FastEthernet0/21
!
interface FastEthernet0/22
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface GigabitEthernet0/1
```

```
!
interface GigabitEthernet0/2
!
interface Vlan1
 no ip address
 shutdown
!
interface Vlan200
 ip address 192.168.5.4 255.255.255.240
!
ip default-gateway 192.168.5.1
!
banner motd $
MMMMMMMMMMMMMMMMMMMMMMWWWNNNNNNNNNNNNNNNNNNNNNNNNNNNNWWWMMMMMMMMMMMMMMMMMMMMMMMM

MMMMMMMMMMMMMMMMWWNNXXXKKKKKKKKKKKKKKKKKKKKKKKKKKKKKKKKKXXXNNWWMMMMMMMMMMMMMMMMM

MMMMMMMMMMMMWNNXXKKK0O00KKKKKKKKOod0KKKKKOdoOKKKKKKKK0O0KKKXXNWWMMMMMMMMMMMMM

MMMMMMMMMWNXXKKK0xl:cdOKKKKKKKK0o..;ccccc,..dKKKKKKKKOd::ox0KKKXXNWMMMMMMMMMM

MMMMMMWWXXKKKOdc'.  c0KKKKKKKKk,            ;OKKKKKKKKO:  .'cxOKKKXNWWMMMMMM

MMMMWWXKKK0kl'      ,x0KKKKKK0l.            .l0KKKKKK0d'      .'lkKKKKXWMMMMM

MMMWNKKKKOl.          .,:clcc:,.            .,:cclc:,.         .lOKKKKNWMMM

MMWXKKKKk;                                                     ;kKKKKXWMM

MWNKKKKk;                                                     ;OKKKKNMM

MWXKKK0o.                                                     .oKKKKXWM

MWXKKK0l.                                                     .o0KKKXWM

MWXKKKKx.                                                     'xKKKKXWM

MMWXKKK0o.                                                   .o0KKKXWMM

MMMNXKKK0d'        .',,..    ...             ...    .',,'.       ,d0KKKXWMMM

MMMMWNKKKKOl'   .l000Oxc';oxkkd:.         .cdkkxo;,cx0000c.   'lOKKKKNWMMMM

MMMMMWWXKKKKKOo;..:kKKKK000KKKKK0kc.     .ckKKKKKK0OKKKKKKk;..:dOKKKXXWMMMMMM

MMMMMMMMWNXKKK0kdloxO0KKKKKKKKKKKKK0d'   'x0KKKKKKKKKKK0kdoldO0KKKXNWMMMMMMMMM

MMMMMMMMMMWNXXKKK0OO00KKKKKKKKKKKKK0x;.;kKKKKKKKKKKKKK00OO0KKKXXNWWMMMMMMMMMM

MMMMMMMMMMMMMMWWNNXXKKKKKKKKKKKKKKKKKKKOkOKKKKKKKKKKKKKKKKKKKXXNNWWMMMMMMMMMMMMM

MMMMMMMMMMMMMMMMMMWWWNNNXXXXKXXXXXXKKKXKKKKKXKXXXXXNNNWWWMMMMMMMMMMMMMMMMMMMMMM

--------------------------------------------------------------------------

El acceso a este dispositivo es solo para usuarios autorizados, si usted no

esta  expresamente autorizado, por favor desconectese inmediatamente.
```

Los accesos no autorizados estan en contra de la ley, y pueden estar

sujetos a penas criminales o civiles.
```
$
!
!
!
line con 0
 password 7 0822455D0A16
 login
!
line vty 0 4
 password 7 0822455D0A16
 login local
 transport input ssh
line vty 5 15
 login
!
!
!
!
end
```