```
!
version 15.0
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
hostname Switch/Equipos6-8&Coaches-Admin
enable secret 5 $1$mERr$hx5rVt7rPNoS4wqbXKX7m0
1
ip ssh version 2
ip domain-name reto.mx
username Switch/Equipos6-8&Coaches-Admin privilege 1 password 7 0822455D0A16
1
spanning-tree mode pvst
spanning-tree extend system-id
interface FastEthernet0/1
 description conectado a Switch-Medio
 switchport mode trunk
interface FastEthernet0/2
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/3
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/4
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/5
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/6
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/7
 description interfaces vlan 200
 switchport access vlan 200
 switchport mode access
interface FastEthernet0/8
 description interfaces vlan 200
 switchport access vlan 200
```

```
switchport mode access
interface FastEthernet0/9
description interfaces vlan 200
switchport access vlan 200
switchport mode access
interface FastEthernet0/10
description interfaces vlan 200
switchport access vlan 200
switchport mode access
interface FastEthernet0/11
description interfaces vlan 80
switchport access vlan 80
switchport mode access
interface FastEthernet0/12
description interfaces vlan 80
switchport access vlan 80
switchport mode access
interface FastEthernet0/13
description interfaces vlan 80
switchport access vlan 80
switchport mode access
interface FastEthernet0/14
description interfaces vlan 70
switchport access vlan 70
switchport mode access
interface FastEthernet0/15
description interfaces vlan 70
switchport access vlan 70
switchport mode access
interface FastEthernet0/16
description interfaces vlan 70
switchport access vlan 70
switchport mode access
interface FastEthernet0/17
description interfaces vlan 60
switchport access vlan 60
switchport mode access
interface FastEthernet0/18
description interfaces vlan 60
switchport access vlan 60
switchport mode access
interface FastEthernet0/19
description interfaces vlan 60
switchport access vlan 60
switchport mode access
interface FastEthernet0/20
```

```
interface FastEthernet0/21
interface FastEthernet0/22
interface FastEthernet0/23
interface FastEthernet0/24
interface GigabitEthernet0/1
interface GigabitEthernet0/2
interface Vlan1
no ip address
shutdown
interface Vlan200
ip address 192.168.5.2 255.255.255.240
ip default-gateway 192.168.5.1
banner motd $
MMMMMMMMMMMMMNNXXKKK0000KKKKKKK0od0KKKKKKOdoOKKKKKKKO00KKKXXNWWMMMMMMMMMMMM
MMMMMMMMMMNXXKKK0xl:cdOKKKKKKK0o..;ccccc,..dKKKKKKK0d::ox0KKKXXNWMMMMMMMMM
MMMMMMWXXKKKOdc'. c0KKKKKKKk,
                                  ;OKKKKKKKO: .'cxOKKKXNWWMMMMMM
MMMMWWXKKK0kl', x0KKKKKK0l. .l0KKKKKK0d'.'lkKKKKXWMMMMM
MMMWNKKKKOl.
          .,:clcc:,.
                                   .,:cclc:,.
                                                    .lokkkknwmmm
MMWXKKKKk;
                                                      ; kKKKKXWMM
MWNKKKKk;
                                                       ; OKKKKNMM
MWXKKK0o.
                                                       .oKKKKXWM
MWXKKK01.
                                                       .o0KKKXWM
MWXKKKKx.
                                                       'xKKKKXWM
MMWXKKK0o.
                                                      .ookkkxwmm
MMMNXKKK0d'
                                                     , d0KKKXWMMM
MMMMWNKKKKOl' .l0000xc';oxkkd:. .cdkkxo;,cx0000c. 'l0KKKKNWMMMM
MMMMMWXKKKKOo;..:kKKKKOOOKKKKKOkc. .ckKKKKKKOOKKKKKk;..:dOKKKXXWMMMMMM
MMMMMMMMNXKKK0kdlox00KKKKKKKKKKKK0d' 'x0KKKKKKKKKKkkk0kdold00KKKXNWMMMMMMM 'x0KKKKKKKKKKKKKkk0kdold00KKKXNWMMMMMMMM
MMMMMMMMMMMMNXXKKK00000KKKKKKKKKKKKKKX0x;.;kKKKKKKKKKKKKKK00000KKKXXNWWMMMMMMMMM
```

El acceso a este dispositivo es solo para usuarios autorizados, si usted no esta expresamente autorizado, por favor desconectese inmediatamente. Los accesos no autorizados estan en contra de la ley, y pueden estar sujetos a penas criminales o civiles. line con 0 password 7 0822455D0A16 login line vty 0 4 password 7 0822455D0A16 login local transport input ssh line vty 5 15

login

end