



Uruu OS

BUSINESS MANAGEMENT PLATFORM

TRAINING GUIDE

Installing & Using the Uruu Agent

A step-by-step guide for internet café and print-shop staff: how to add a computer to Uruu OS, and how to monitor and control it from your dashboard afterward.

What is the Uruu Agent?

The Uruu Agent is a small program that runs quietly on every computer at your internet café or print shop. It reports back to your Uruu OS dashboard so you always know what's happening — without walking over to check.

What it does:

Shows whether each PC is online, tracks who's using it and for how long, reports live CPU/RAM/disk usage, counts print jobs, and lets you Lock, Restart, or Shut down any PC remotely — right from your dashboard, no need to walk over.

What it needs:

A Windows PC with an internet connection. Installing it takes about two minutes and needs Administrator access on that PC once — after that, it runs on its own in the background, even after a restart.

Two people, two roles

Installing a new PC involves two short steps, usually done by two different people:

1 The Admin — generates a code

From **PC Agent Hub** in Uruu OS, an Admin clicks "Add a PC" and gets a one-line command with a unique code baked in. This works from anywhere — the Admin doesn't need to be at the café.

2 Whoever's at the PC — runs the command

They don't need to be an Admin, or know anything technical. They just paste the one-line command into PowerShell and press Enter. The PC appears in the dashboard within a few seconds.

Step 1: Generate an install code (Admin)

Do this from Uruu OS, on any device — you don't need to be at the café.

1 Open PC Agent Hub

Sign in to Uruu OS and go to **PC Agent Hub** in the left menu (Admin accounts only).

2 Click "Add a PC"

Optionally give the PC a name (e.g. "Station 4") — or leave it blank and Uruu OS will number it automatically (PC-01, PC-02, ...).

3 Copy the command

A one-line PowerShell command appears with the code already included. Copy it — you'll send this to whoever is at the new PC.

Illustrative mock-up of the "Add a PC" screen — not an exact screenshot.

Add a PC

Computer name (optional)

e.g. Station 4 — leave blank to auto-number

Command to send them

```
$env:URUU_CODE = "ABCD1234"; irm ../remote-install.ps  
1 | iex
```

Good to know: the code is valid for 48 hours and can only be used once. If it expires before anyone uses it, just click "Add a PC" again for a fresh one.

Step 2: Run the command (at the PC)

This is done once, on the actual computer being added. No Uruu OS login needed here.

1 Open PowerShell as Administrator

Right-click the Start button → **Terminal (Admin)** (or "Windows PowerShell (Admin)" on older Windows). Click "Yes" if prompted.

2 Paste the command and press Enter

Paste exactly what the Admin sent you. It will download the Agent, confirm the code, and install itself automatically — this takes about a minute.

3 Done

The PC now shows up in PC Agent Hub. It keeps running in the background from now on — even after the computer restarts — with nothing more to do.

```
PS C:\WINDOWS\system32> $env:URUU_CODE = "ABCD1234"; irm https://raw.githubusercontent.com/uchi-  
c/dube-man-system/main/pc-agent/remote-install.ps1 | iex  
Resolving install code...  
Code accepted - installing as PC-04.  
Downloading Uruu Agent...  
Handing off to the installer...  
✓ UruuAgent service installed and running.
```


Must be run as Administrator. If you see a permissions error, make sure you opened PowerShell using "Run as Administrator" — this is required to install a background service, and no install method can skip it.

Reading a PC's status

Each PC shows a live status badge in PC Agent Hub, based on how recently it last checked in:

STATUS	MEANING	COMMANDS AVAILABLE
● Online	Checked in within the last 60 seconds — actively connected.	Lock, Restart, Shutdown
● Standby	Checked in 1–2 minutes ago — briefly quiet, usually still fine.	None (wait for Online)
● Offline	No check-in for over 2 minutes — likely powered off or disconnected.	None

Illustrative mock-up of a PC's status card in PC Agent Hub.



Remote commands

🔒 Lock

Locks the screen instantly — useful between customers, or if someone left a PC unattended while signed in.

↺ Restart

Restarts the PC. Uruu OS will ask you to confirm first, since anyone using it loses unsaved work.

🔌 Shutdown

Powers the PC off completely — handy for closing up for the night without walking to every station.

Why is a button greyed out?

Commands only work while a PC shows **Online**. If it's Standby or Offline, wait for it to reconnect.

Common issues

"This code is invalid, expired, or already used"

Install codes work once and expire after 48 hours. Ask your Admin to generate a fresh one from PC Agent Hub → Add a PC.

PowerShell says I need to "Run as Administrator"

Close the window, right-click the Start button, choose **Terminal (Admin)** or **Windows PowerShell (Admin)**, and paste the command again. This step can't be skipped — installing a background service requires it.

The install finished, but the PC never appears in PC Agent Hub

Give it a minute — new PCs appear within one heartbeat (a few seconds once running). If it still doesn't show up after a few minutes, check that the PC has an internet connection, then try running the install command again — it's safe to run more than once.

A PC shows Offline but the computer is clearly on

The Agent service may have stopped. Ask an admin to re-run the same install command on that PC — this cleanly reinstalls and restarts the service without affecting anything else on the machine.

For admins — health check: from the install folder, run `.\install.ps1 -VerifyOnly` on the PC itself to confirm every setting is correct and see the service's recent log output.

Need help?

If something isn't covered here, reach out — we're happy to help get a PC connected.

WhatsApp: 0979 501 830 or 0764 502 661
Email: shadowrootsec@gmail.com