

Important

Wednesday, August 07, 2024 12:30 PM

- Utility file path

"C:\Users\13337\Downloads\13.2_ITK_Reference_Function 1\13.2_ITK_Reference_Function\index.html"

This file contains all the data related to ITK utility.

Item related data will be there under Modules/Integration Tool Kit/Item.

Search criteria – Integer / module / Verb(action) / class / Modifier

- Tcinit.h --> contains methods for logging in.
 - Tc_startup.h --> main function declaration.
 - AE – Dataset
 - BOM- bom
 - FI – Folder
 - SA/tcfile.h – File management
 - GRM – Relations
 - WSOM- search workspace objects
 - SA – System admin
 - Tccore- item.h, grm.h, aom_prop.h, aom.h, project.h, tc_type.h, workspaceObjects.h (where referenced), **custom.h(DLL)**
 - Tc – folder.h, envelope.h, preferences.h, emh.h
 - Ps – ps.h(where used)
 - Qry – qry.h
 - BOM – bom.h
- **AOM_refresh** is used for checking out and checking in for a particular object.
 - True – check-out
 - False – check-in
 - To add release status to an object use, **RELSTAT_add_release_status**.
 - To create a new status use, **RELSTAT_create_release_status**.

Extensions in DLL

To check all data related to extensions always check msg.h files.

For example: to check item related extensions check the following file - "D:\TC13\TC_ROOT\include\tccore\item_msg.h"

1. For all Project related operations use - "TC_assign_primary_obj_to_project".
2. While revising the revision use - "ITEM_copy_rev".
3. While using save as use - "ITEM_create_from_rev".
4. For BOM line related use - "BOMLine_add".
5. For delete operation use - "IMAN_delete".
6. For attaching secondary objects (datasets) use – "GRM_create".
7. To remove BOM lines use - "BOMLine_cut".
8. For new Item create use -"ITEM_Create".
9. For new Item revision create use -"ITEM_create_rev".

To get the class of particular business object use the following:

```
iCheckError(EPM_ask_root_task(tTask, &tRootTask));
iCheckError(EPM_ask_attachments(tRootTask, EPM_target_attachment, &iCount1, &Attachments));

if (iCount1 > 0)
{
    for (int i = 0; i < iCount1; i++)
    {
        iCheckError(POM_class_of_instance(tAttachments[i], &tClassId));
        iCheckError(POM_name_of_class(tClassId, &tClassName));
    }
}
```

Code for using file based operations:

```
const char* cFile_path = ITK_ask_cli_argument("-file=");

if (cFile_path != nullptr)
{
    ifstream fin(cFile_path);
    if (fin.is_open())
    {
        cout << "opened file successfully" << endl;

        tag_t tBomWindow = NULLTAG;
        iCheckError(BOM_create_window(&tBomWindow));

        iCheckError(AOM_save_with_extensions(tBomWindow));

        for (int i = 0; getline(fin, sLine); i++)
```

```

    {
        // Expected format: item_id|item_name
        size_t pos = sLine.find('|');
        if (pos != string::npos)
        {
            string item_id = sLine.substr(0, pos);
            string item_name = sLine.substr(pos + 1);

            const char* item_id1 = item_id.c_str();
            const char* item_name1 = item_name.c_str();
        }
    }

```

Code for tokenization

```

// Text:txt
// PDF:pdf

PREF_ask_char_value("Dataset_NamedReference_Pairs", &dataset_preference);
dataset_type = tc_strtok(preference_copy, ".");
named_ref_suffix = tc_strtok(NULL, ".");

```

For DLL

- o Extern"C" is used when:
 - o We need to use some C library in C++.
 - o We need export some C++ code to C.
 - o We need an ability to resolve symbol in shared library -- so we need to get rid mangling.
- o Header Files.
 - o Tccore- **custom.h**
 - o Tc- emh.h
- o Operations:
 - o TC_assign_primary_obj_to_project – checking while assigning project.
- o
- o

If you get this error in DLL, remove itk_main.obj header file from linker.

- o If a custom handler does not get hit on code while debugging, try to change the handler placement.