

Création VM Artica

Create: Virtual Machine

General OS System Disks CPU Memory Network Confirm

Node: SRVDEPLOY-S4P2 Resource Pool: SIO1

VM ID: 105

Name: SRV-Artica

Add to HA: ☐

Start at boot: ☐

Start/Shutdown order: any

Startup delay: default

Shutdown timeout: default

Tags

No Tags +

Help Advanced Back Next

Choisir ISO Artica

Create: Virtual Machine

General OS System Disks CPU Memory Network Confirm

☒ Use CD/DVD disc image file (iso)

Storage: local

ISO image: ISO_ARTICA.iso

Guest OS:

Type: Linux

Version: 6.x - 2.6 Kernel

☐ Use physical CD/DVD Drive

☐ Do not use any media

Advanced Back Next

Create: Virtual Machine

General

OS

System

Disks

CPU

Memory

Network

Confirm

Graphic card:

Default

SCSI Controller:

VirtIO SCSI single

Machine:

Default (i440fx)

Qemu Agent:

☐

Firmware

BIOS:

Default (SeaBIOS)

Add TPM:

☐

Help

Advanced ☒

Back

Next

Mettre en SATA Disk size (GiB) 50 et cocher la case SSD emulation

Create: Virtual Machine

General

OS

System

Disks

CPU

Memory

Network

Confirm

sata0

Disc

Bandwidth

Bus/Device:

SATA

0

Cache:

Default (No cache)

Storage:

local-lvm

Discard:

☐

Disk size (GiB):

50

IO thread:

☐

Format:

Raw disk image (raw)

SSD emulation:

☒

Backup:

☒

Read-only:

☐

Skip replication:

☐

Async IO:

Default (io_uring)

Add

Import

Help

Advanced ☒

Back

Next

Create: Virtual Machine

General OS System Disks **CPU** Memory Network Confirm

Sockets: 1 Type: x86-64-v2-AES

Cores: 1 Total cores: 1

VCPUs: 1 CPU units: 100

CPU limit: unlimited Enable NUMA: ☐

CPU Affinity: All Cores

Extra CPU Flags:

Default	- ☐ ☒ ☐ ☐ +	nested-virt	Controls nested virtualization, namely 'svm' for AMD CPUs and 'vmx' for Intel CPUs. Live migration still only works if it's the same flag on both sides. For Windows, use a CPU model similar to the host, with the same vendor!
Default	- ☐ ☒ ☐ ☐ +	md-clear	Required to let the guest OS know if MDS is mitigated correctly.
Default	- ☐ ☒ ☐ ☐ +	pcid	Meltdown fix cost reduction on Westmere, Sandy-, and IvyBridge Intel CPUs.
Default	- ☐ ☒ ☐ ☐ +	spec-ctrl	Allows improved Spectre mitigation with Intel CPUs.
Default	- ☐ ☒ ☐ ☐ +	ssbd	Protection for 'Speculative Store Bypass' for Intel models.

Help Advanced ☒ Back Next

Mettre 5go de Mémoire

Create: Virtual Machine

General OS System Disks CPU **Memory** Network Confirm

Memory (MiB): 5000

Minimum memory (MiB): 5000

Shares: Default (1000)

Ballooning Device: ☒

Allow KSM: ☒

Help Advanced ☒ Back Next

Bridge : vmbrSIO1

Create: Virtual Machine

General

OS

System

Disks

CPU

Memory

Network

Confirm

☐ No network device

Bridge:vmbrSIO1

Model:VirtIO (paravirtualized)

VLAN Tag:no VLAN

MAC address:auto

Firewall:☒

Disconnect:☐

Rate limit (MB/s):unlimited

MTU:Same as bridge

Multiqueue:

Help


Advanced☒

Back


Next

Installation Artica

Aller dans « Network »



Allez dans DNS



Mettre l'AD1 un DNS donc 192.168.17.1 en DNS 2 mettre 8.8.8.8

ENTER IP ADDRESS FOR THE DNS 1

Enter your IP address for the DNS number 1.
Example: 1.1.1.1

192.168.17.1

< OK > <Cancel>

En DNS 2 mettre 8.8.8.8

ENTER IP ADDRESS FOR THE DNS 2

Enter your IP address for the DNS number 2.
Example: 8.8.8.8

8.8.8.8_

< OK > <Cancel>

Aller dans eth0


[NETWORK - MENU]

You can use the UP/DOWN arrow keys
Choose the TASK


RECONF	Reconfigure/Rebuild Network
DNS	DNS setup (127.0.0.1, 192.168.17.1)
eth0	Modify eth0 interface [bc:24:11:4d:46:6b] (192.168.17.5/255.255.255.0)
STOPFW	Stop the FireWall
UNSTFW	Uninstall the FireWall
Broadcom	Install Broadcom driver
Realtek	Install Realtek/ralink drivers
Quit	Return to main menu

< OK >

Allez dans édit puis change Adress




Mettre l'IP de Artica ici c'est 192.168.17.5



Mettre le masque de sous réseau



Mettre la passerelle




ENTER IP ADDRESS FOR 'eth0'

Enter your gateway for the eth0 Interface.
Example: 111.112.113.114
If this interface is the main gateway of your network, set 0.0.0.0 here

192.168.17.254_

< OK > <Cancel>

Faire yes




NETWORK SETUP COMPLETE

Your networking system is now configured to use:
192.168.17.5/255.255.255.0 Gateway 192.168.17.254
Is this correct? Press 'Yes' to continue, or 'No' to exit


< Yes > < No >

Maintenant faire quit et exit jusqu'à arriver sur cette page



Puis aller dans son AD1 taper l'adresse [http://192.168.17.5 :9000](http://192.168.17.5:9000)

Puis on va arriver sur cette page



Taper l'ID : Manager et le mot de passe

