图像亮度变换

我们知道，图像都是由一个个像素值组成的，图像的亮度变换实际上还是图像像素值的变换。在本实验中，使用了亮度变换组件来对图像的亮度进行调整，下面具体介绍一下亮度变换的原理。

1. “亮度变换”组件

在讲解亮度时，需要和对比度一起来进行解释。

亮度调整：图像像素强度整体变高或者变低。

对比度调整：图像暗处像素强度变低，图像亮处像素强度变高，从而拉大中间某个区域范围的显示精度。



上图中，(a)把亮度调高，就是图片中的所有像素值加上了一个固定值；(b)把亮度调低，就是图片中的所有像素值减去了一个固定值；(c)增大像素对比度（白的地方更白，黑的地方更黑）；(d)减小像素对比度（整幅图都趋于一个颜色）；

OpenCV调整图像对比度和亮度时，公式为：$g(i,j)=\alpha f(i,j)+\beta$。但是不能浅显的讲$\alpha$是控制对比度，$\beta$是控制亮度的。

对比度：需要通过α、β一起控制（仅调整α只能控制像素强度0附近的对比度，而这种做法只会导致像素强度大于0的部分更亮而已，根本看不到对比度提高的效果）。

亮度：通过β控制。

本实验也是通过该公式进行调整对比度，那么$f(i,j)$代表某个点的像素值，经过调节β，就可以实现亮度变化，这里的取值范围是组件中的[-100，100]。由于输入的图片是三个通道的，所以三个通道都需要进行计算。

2.编程实例与步骤

需要通过元宇宙平台进入“人工智能虚拟仿真实验”界面和打开“华清远见人工智能虚拟仿真本地服务管理平台”软件。

2.1 （可选）使用“华清远见人工智能虚拟仿真本地服务管理平台”启动服务

服务启动一次之后就不需要再次启动了。

2.2 单击图像亮度变换实验进入

如果之前打开了进入了某个实验，可以点击“返回”回到主页即可。

2.3 拖出组件并连线

根据实验原理，将我们的逻辑抽象成组件之后，连线如下图所示。

2.4 验证

点击验证，如显示校验成功，即代表逻辑无误，验证按钮与校验成功界面如下图所示。



华清远见 fsdev.com.cn

2.5 运行

点击运行，可以实现功能运行，并显示结果输出，如下图所示。

2.6 代码生成

点击界面左下角的生成代码按钮，可生成本实验的Python代码，生成代码按钮如下图所示。

点击后可以查看该实验代码，代码会根据界面所选参数进行适配，点击复制可以将其复制，并粘贴在其它地方。

这里我们可以粘贴到软件的Jupyter中运行，“华清远见人工智能虚拟仿真本地服务管理平台”打开Jupyter，第一次打开Jupyter需要点击“打开CMD命令”，打开Jupyter后无需再次打开CMD，如下图所示。

华清远见 fsdev.com.cn

在弹出的CMD命令行中，输入python -m jupyterlab --notebook-dir .\\learn，点击回车，浏览器会自动跳转打开Jupyter，如下图所示。



```
F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\workspace>python
-m jupyterlab --notebook-dir .\\learn
[I 2022-12-26 09:28:37.282 ServerApp] jupyterlab | extension was successfully linked.
[W 2022-12-26 09:28:37.285 NotebookApp] 'shutdown_no_activity_timeout' has moved from NotebookApp to ServerApp. This con
fig will be passed to ServerApp. Be sure to update your config before our next release.
[I 2022-12-26 09:28:37.288 ServerApp] nbclassic | extension was successfully linked.
[I 2022-12-26 09:28:37.594 ServerApp] notebook_shim | extension was successfully linked.
[I 2022-12-26 09:28:37.613 ServerApp] notebook_shim | extension was successfully loaded.
[I 2022-12-26 09:28:37.613 LabApp] JupyterLab extension loaded from F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码\BS
架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\tools\Python\lib\site-packages\jupyterlab
[I 2022-12-26 09:28:37.613 LabApp] JupyterLab application directory is F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码
\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\tools\Python\share\jupyter\lab
[I 2022-12-26 09:28:37.616 ServerApp] jupyterlab | extension was successfully loaded.
[I 2022-12-26 09:28:37.623 ServerApp] nbclassic | extension was successfully loaded.
[I 2022-12-26 09:28:37.624 ServerApp] Serving notebooks from local directory: F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿
真\源码\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\workspace\learn
[I 2022-12-26 09:28:37.624 ServerApp] Jupyter Server 1.23.4 is running at:
[I 2022-12-26 09:28:37.624 ServerApp] http://localhost:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9ee7
[I 2022-12-26 09:28:37.624 ServerApp]  or http://127.0.0.1:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9e
e7
[I 2022-12-26 09:28:37.624 ServerApp] Use Control-C to stop this server and shut down all kernels (twice to skip confirm
ation).
[C 2022-12-26 09:28:37.646 ServerApp]

    To access the server, open this file in a browser:
        file:///C:/Users/82553/AppData/Roaming/jupyter/runtime/jpserver-27004-open.html
    Or copy and paste one of these URLs:
        http://localhost:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9ee7
```

如果没有自动跳转和打开浏览器，请输入下图中圈出的内容，每个人的该内容不一致，请复制自己的 弹出的。

```
F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\workspace>python
-m jupyterlab --notebook-dir .\\learn
[I 2022-12-26 09:28:37.282 ServerApp] jupyterlab | extension was successfully linked.
[W 2022-12-26 09:28:37.285 NotebookApp] 'shutdown_no_activity_timeout' has moved from NotebookApp to ServerApp. This con
fig will be passed to ServerApp. Be sure to update your config before our next release.
[I 2022-12-26 09:28:37.288 ServerApp] nbclassic | extension was successfully linked.
[I 2022-12-26 09:28:37.594 ServerApp] notebook_shim | extension was successfully linked.
[I 2022-12-26 09:28:37.613 ServerApp] notebook_shim | extension was successfully loaded.
[I 2022-12-26 09:28:37.613 LabApp] JupyterLab extension loaded from F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码\BS
架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\tools\Python\lib\site-packages\jupyterlab
[I 2022-12-26 09:28:37.613 LabApp] JupyterLab application directory is F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿真\源码
\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\tools\Python\share\jupyter\lab
[I 2022-12-26 09:28:37.616 ServerApp] jupyterlab | extension was successfully loaded.
[I 2022-12-26 09:28:37.623 ServerApp] nbclassic | extension was successfully loaded.
[I 2022-12-26 09:28:37.624 ServerApp] Serving notebooks from local directory: F:\00HQYJProject\20虚拟仿真\人工智能虚拟仿
真\源码\BS架构\华清远见人工智能虚拟仿真本地服务管理平台-源码\workspace\learn
[I 2022-12-26 09:28:37.624 ServerApp] Jupyter Server 1.23.4 is running at:
[I 2022-12-26 09:28:37.624 ServerApp] http://localhost:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9ee7
[I 2022-12-26 09:28:37.624 ServerApp]  or http://127.0.0.1:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9e
e7
[I 2022-12-26 09:28:37.624 ServerApp] Use Control-C to stop this server and shut down all kernels (twice to skip confirm
ation).
[C 2022-12-26 09:28:37.646 ServerApp]

    To access the server, open this file in a browser:
        file:///C:/Users/82553/AppData/Roaming/jupyter/runtime/jpserver-27004-open.html
    Or copy and paste one of these URLs:
        http://localhost:8888/lab?token=9025b4e91c0adabb6891df5e009926ca57c65132098d9ee7
```

将代码输入到Jupyter中，注意这里需要往Jupyter导入一张demo.png，在大多数情况下，这张照片最好不要是其它后缀修改成png后缀而来，而是直接后缀就是png。点击运行可以查看结果。

3. 实验现象

可以看到，实验结果为：



华清远见 fsdev.com.cn