


LAB 6 TASKS

Q1



```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet
1
      ^
% Invalid input detected at '^' marker.

s1(config)#interface fa0/1
s1(config-if)#ip address 10.33.1.2 255.255.255.0
      ^
% Invalid input detected at '^' marker.

s1(config-if)#ip address 10.33.1.2 255.255.255.0
      ^
% Invalid input detected at '^' marker.

s1(config-if)#
s1#
%SYS-5-CONFIG_I: Configured from console by console

s1#configure terminal
Enter configuration commands, one per line. End with CNTL/
s1(config)#interface vlan1
s1(config-if)#ip address 10.33.1.2
% Incomplete command.
s1(config-if)#ip address 10.33.1.2 255.255.255.0
s1(config-if)#no shutdown

s1(config-if)#
%LINK-3-UPDOWN: Interface Vlan1, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, char

s1(config-if)#interface fa0/1
s1(config-if)#no shutdown
s1(config-if)#exit
s1(config)#interface fa0/1
s1(config-if)#exit
s1(config)#exit
s1#
%SYS-5-CONFIG_I: Configured from console by console

s1#
```

```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname s2
s2(config)#ip address 10.33.1.3 255.255.255.0
```

```
      ^
% Invalid input detected at '^' marker.
```

```
s2(config)#interface vlan2
s2(config-if)#
%LINK-5-CHANGED: Interface Vlan2, changed state to up
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan2, changed state to up
```

```
s2(config-if)#ip address 10.33.1.3 255.255.255.0
s2(config-if)#no shutdown
s2(config-if)#exit
s2(config)#exit
s2#
```

```
%SYS-5-CONFIG_I: Configured from console by console
```

```
s2#|
```

```
%LINK-5-CHANGED: Interface FastEthernet0/5, changed state to up
```


```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/5, changed state to up
```



```
Switch>enable
Switch#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#hostname s3
s3(config)#interface vlan1
s3(config-if)#ip address 10.33.1.4 255.255.255.0
s3(config-if)#no shutdown
```


```
s3(config-if)#
%LINK-3-UPDOWN: Interface Vlan1, changed state to down
```

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up
```

```
s3(config-if)#exit
s3(config)#|
```







PC0(1)

PhysicalConfigDesktopProgrammingAttributes

Configure MailX

User Information

Your Name:ali

Email Addressali@gmail.com

Server Information

Incoming Mail Server10.33.1.12

Outgoing Mail Server10.33.1.12

Logon Information


User Name:ali


Password:●●●

SaveRemove

ClearReset

☐ Top





Server0

Physical Config **Services** Desktop Programming Attributes

SERVICES

HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP

FTP

Service On Off

User Setup

Username Password

☐ Write
☐ Read
☐ Delete
☐ Rename
☐ List

	Username	Password	Permission	
1	cisco	cisco	RWDNL	Add Save Remove

File

29

30

31

32

33

34

35

36

raedisthebest.txt

Remove

☐ Top

```

% Invalid input detected at '^' marker.

s1>enable
s1#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
s1(config)#enable secret cisco
s1(config)#line vty 0 15
s1(config-line)#password cisco
s1(config-line)#login
s1(config-line)#exit
s1(config)#

```

```

C:\>ping 10.33.1.12

Pinging 10.33.1.12 with 32 bytes of data:

Reply from 10.33.1.12: bytes=32 time=8ms TTL=128
Reply from 10.33.1.12: bytes=32 time<1ms TTL=128
Reply from 10.33.1.12: bytes=32 time<1ms TTL=128
Reply from 10.33.1.12: bytes=32 time<1ms TTL=128

Ping statistics for 10.33.1.12:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 8ms, Average = 2ms

C:\>telnet 10.33.1.12
Trying 10.33.1.12 ...
% Connection refused by remote host
C:\>telnet 10.33.1.2
Trying 10.33.1.2 ...Open

User Access Verification

Password:
s1>

```

Q2

```

Router(config)#interface fa0/0
Router(config-if)#ip address 10.33.1.0 255.255.255.0
Bad mask /24 for address 10.33.1.0
Router(config-if)#ip address 10.33.10.0 255.255.255.0
Bad mask /24 for address 10.33.10.0
Router(config-if)#ip address 10.33.1.10 255.255.255.0
Router(config-if)#ip address 10.33.1.10 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#interface fa1/0
Router(config-if)#ip address 10.33.2.10 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

Router(config-if)#exit
Router(config)#

```

Copy

```

R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#hostname R1
R1(config)#ip domain
% Unknown command or computer name, or unable to find computer address

R1(config)#ip domain-name raed.com
R1(config)#crypto key generate rsa
The name for the keys will be: R1.raed.com
Choose the size of the key modulus in the range of 360 to 2048 for your
General Purpose Keys. Choosing a key modulus greater than 512 may take
a few minutes.

How many bits in the modulus [512]: 4096
% A decimal number between 360 and 2048
How many bits in the modulus [512]: 2048
% Generating 2048 bit RSA keys, keys will be non-exportable...[OK]

R1(config)#ip ssh version 2
*Mar 1 0:19:30.613: %SSH-5-ENABLED: SSH 1.99 has been enabled
R1(config)#username cisco privilege 15 secret cisco
^
% Invalid input detected at '^' marker.

R1(config)#username cisco privilege 15 secret cisco
R1(config)#line vty 0 15
R1(config-line)#transport input ssh
R1(config-line)#login local
R1(config-line)#exit
R1(config)#

```

