


Install a new Stand Alone Window Server and Assign a new Static IP




The screenshot shows the Windows Server Manager interface for a local server named 'server2'. The left sidebar contains navigation links: Dashboard, Local Server (selected), All Servers, and File and Storage Services. The main area is divided into two sections: PROPERTIES and EVENTS.

PROPERTIES for server2



Property	Value
Computer name	server2
Workgroup	WORKGROUP
Last installed updates	Never
Windows Update	Download updates only, using Windows Update
Last checked for updates	Never
Windows Defender Firewall	Public: On
Remote management	Enabled
Remote Desktop	Disabled
NIC Teaming	Disabled
Ethernet	IPv4 address assigned by DHCP, IPv6 enabled
Operating system version	Microsoft Windows Server 2019 Datacenter Evaluation
Hardware information	innotek GmbH VirtualBox
Processors	Intel(R) Core(TM) i3-5005U CPU @ 2.00GHz
Installed memory (RAM)	2 GB
Total disk space	32.67 GB


EVENTS
All events | 29 total

Server Name	ID	Severity	Source	Log	Date and Time
SERVER2	134	Warning	Microsoft-Windows-Time-Service	System	8/29/2021 9:19:46 AM
SERVER2	134	Warning	Microsoft-Windows-Time-Service	System	8/29/2021 9:19:36 AM
SERVER2	134	Warning	Microsoft-Windows-Time-Service	System	8/29/2021 9:00:53 AM



This screenshot is identical to the one above, showing the Windows Server Manager interface for 'server2'. The layout, including the sidebar, PROPERTIES section, and EVENTS table, is the same. A mouse cursor is visible pointing at the 'Ethernet' property value, which is 'IPv4 address assigned by DHCP, IPv6 enabled'.







And Refresh the Server you may see the Assigned Static IP Address.

Now move towards installation process of the DNS Role


1. Go to Manage
2. Click on Add Roles & Features




Then click on Next button




Then click on Next Button




Make sure this server2 selected or single as shown on your laptop and then click on Next button




Then select DNA Server after that DNS Server Features Windows PopUp so there click on the Add Features Button




In this windows keep it as default



Then click on the next button





And then click on install, at the end this success message shown.



1: you see that DNS installed at sidebar

Now we move towards the DNS Configuration







2: DNS Server Manager

- * **Forward lookup zone** resolves/translates domain name/hostname into IP Address.
- * **Forward Lookup Zone** contains a mapping between hostnames and IP Addresses.

- * **Reverse Lookup Zone** resolves/translates IP Address into domain name/hostname.
- * **Reverse Lookup Zone** has a mapping that links IP Addresses to hostnames.
- * **Forward Lookup Zone** : Name to IP Address.
- * **Reverse Lookup Zone** : IP Address to Name.





** **Primary Zone** is authoritative/master copy of DNS Zone, in which resource records are created and managed.*

** All changes to a Zone are made on the Primary Zone*

** **Secondary Zone** is a copy of DNS Zone that contains a read only copy of primary Zone.*

** Information in a secondary Zone is replicated from the Primary Zone.*

secondary zone always create on the second server, on which server the Primary Zone installed secondary zone not be installed

** **Stub Zone** is Copy of a zone that contains only records used to locate name servers*

** **Active Directory Integrated Zone** : Zone data is stored in AD DS rather than in zone files*

New Zone Wizard

Zone Name
What is the name of the new zone?

The zone name specifies the portion of the DNS namespace for which this server is authoritative. It might be your organization's domain name (for example, microsoft.com) or a portion of the domain name (for example, newzone.microsoft.com). The zone name is not the name of the DNS server.

Zone name:
hptinfotech.com

< Back Next > Cancel

New Zone Wizard

Zone File
You can create a new zone file or use a file copied from another DNS server.

Do you want to create a new zone file or use an existing file that you have copied from another DNS server?

☒ Create a new file with this file name:
hptinfotech.com.dns

☐ Use this existing file:

To use this existing file, ensure that it has been copied to the folder %SystemRoot%\system32\dns on this server, and then click Next.

< Back Next > Cancel

New Zone Wizard

Dynamic Update

You can specify that this DNS zone accepts secure, nonsecure, or no dynamic updates.

Dynamic updates enable DNS client computers to register and dynamically update their resource records with a DNS server whenever changes occur.

Select the type of dynamic updates you want to allow:

- ☐ Allow only secure dynamic updates (recommended for Active Directory)
This option is available only for Active Directory-integrated zones.
- ☐ Allow both nonsecure and secure dynamic updates
Dynamic updates of resource records are accepted from any client.
 This option is a significant security vulnerability because updates can be accepted from untrusted sources.
- ☒ Do not allow dynamic updates
Dynamic updates of resource records are not accepted by this zone. You must update these records manually.

< Back Next > Cancel

New Zone Wizard

Completing the New Zone Wizard

You have successfully completed the New Zone Wizard. You specified the following settings:

Name:	hptinfotech.com
Type:	Standard Primary
Lookup type:	Forward
File name:	hptinfotech.com.dns


Note: You should now add records to the zone or ensure that records are updated dynamically. You can then verify name resolution using nslookup.

To close this wizard and create the new zone, click Finish.

< Back Finish Cancel

A Records : IPv4 Addresses.

*AAAA Records : IPv6 Addresses.



New Host [X]


Name (uses parent domain name if blank):

Fully qualified domain name (FQDN):


IP address:

☐ Create associated pointer (PTR) record

Now we verify it



Then type your complete domain which was created like www.yourdomain.com you see the complete information and now move towards Reverse Zone



New Zone Wizard

Reverse Lookup Zone Name
A reverse lookup zone translates IP addresses into DNS names.

Choose whether you want to create a reverse lookup zone for IPv4 addresses or IPv6 addresses.

☒ IPv4 Reverse Lookup Zone
☐ IPv6 Reverse Lookup Zone

< Back Next > Cancel

New Zone Wizard

Reverse Lookup Zone Name
A reverse lookup zone translates IP addresses into DNS names.

To identify the reverse lookup zone, type the network ID or the name of the zone.

☒ Network ID:
192.168.1

The network ID is the portion of the IP addresses that belongs to this zone. Enter the network ID in its normal (not reversed) order.

If you use a zero in the network ID, it will appear in the zone name. For example, network ID 10 would create zone 10.in-addr.arpa, and network ID 10.0 would create zone 0.10.in-addr.arpa.

☐ Reverse lookup zone name:
1.168.192.in-addr.arpa

< Back Next > Cancel

New Zone Wizard

Zone File

You can create a new zone file or use a file copied from another DNS server.

Do you want to create a new zone file or use an existing file that you have copied from another DNS server?

☒ Create a new file with this file name:

1. 168.192.in-addr.arpa.dns

☐ Use this existing file:

To use this existing file, ensure that it has been copied to the folder %SystemRoot%\system32\dns on this server, and then click Next.

< Back Next > Cancel

New Zone Wizard

Dynamic Update

You can specify that this DNS zone accepts secure, nonsecure, or no dynamic updates.

Dynamic updates enable DNS client computers to register and dynamically update their resource records with a DNS server whenever changes occur.


Select the type of dynamic updates you want to allow:

☐ Allow only secure dynamic updates (recommended for Active Directory)
This option is available only for Active Directory-integrated zones.



☐ Allow both nonsecure and secure dynamic updates
Dynamic updates of resource records are accepted from any client.
 This option is a significant security vulnerability because updates can be accepted from untrusted sources.



☒ Do not allow dynamic updates
Dynamic updates of resource records are not accepted by this zone. You must update these records manually.



< Back Next > Cancel




Now we create the Pointer Record








Then click OK



3 Process Completed




Now again type your created domain
www.domainname.com and then type your IP address


Now again verify it from your Windows Server 2019 Command Prompt

Type on CMD: nslookup www.domainname.com

Also ping on the CMD ping www.domainname.com

Next Step is now link Windows 10 with DNS server for Mail & PTR record for windows Client





After that open the Reverser Lookup Zone, Refresh it and see that there new IP added which is 192.168.1.100

Now again open the Windows Server CMD and type there nslookup www.yourdomainname.com

And again type nslookup 192.168.1.110

Also ping there ping mail.yourdomainname.com

