




Go to DNS machine (Go to Server1 Where you create your primary Domain)



Then you see the DNS Manager



As see above in the created Server the Forward Lookup Zone already installed as when ADDS installed and with ADDS installation DNS default installed.



And now start create New Zone (of Reverse Lookup Zone)

New Zone Wizard

Zone Type
The DNS server supports various types of zones and storage.

Select the type of zone you want to create:

☒ Primary zone
Creates a copy of a zone that can be updated directly on this server.

☐ Secondary zone
Creates a copy of a zone that exists on another server. This option helps balance the processing load of primary servers and provides fault tolerance.

☐ Stub zone
Creates a copy of a zone containing only Name Server (NS), Start of Authority (SOA), and possibly glue Host (A) records. A server containing a stub zone is not authoritative for that zone.

☒ Store the zone in Active Directory (available only if DNS server is a writeable domain controller)

< Back Next > Cancel

New Zone Wizard

Active Directory Zone Replication Scope
You can select how you want DNS data replicated throughout your network.

Select how you want zone data replicated:

☐ To all DNS servers running on domain controllers in this forest: hpit.com

☒ To all DNS servers running on domain controllers in this domain: hpit.com

☐ To all domain controllers in this domain (for Windows 2000 compatibility): hpit.com

☐ To all domain controllers specified in the scope of this directory partition:

< Back Next > Cancel

New Zone Wizard

Reverse Lookup Zone Name

A reverse lookup zone translates IP addresses into DNS names.



Choose whether you want to create a reverse lookup zone for IPv4 addresses or IPv6 addresses.

☒ IPv4 Reverse Lookup Zone

☐ IPv6 Reverse Lookup Zone

< Back

Next >

Cancel

New Zone Wizard

Reverse Lookup Zone Name

A reverse lookup zone translates IP addresses into DNS names.



To identify the reverse lookup zone, type the network ID or the name of the zone.

☒ Network ID:

192.168.1

The network ID is the portion of the IP addresses that belongs to this zone. Enter the network ID in its normal (not reversed) order.

If you use a zero in the network ID, it will appear in the zone name. For example, network ID 10 would create zone 10.in-addr.arpa, and network ID 10.0 would create zone 0.10.in-addr.arpa.

☐ Reverse lookup zone name:

1.168.192.in-addr.arpa

< Back

Next >

Cancel

New Zone Wizard

Dynamic Update

You can specify that this DNS zone accepts secure, nonsecure, or no dynamic updates.

Dynamic updates enable DNS client computers to register and dynamically update their resource records with a DNS server whenever changes occur.

Select the type of dynamic updates you want to allow:

- ☒ Allow only secure dynamic updates (recommended for Active Directory)
This option is available only for Active Directory-integrated zones.
- ☐ Allow both nonsecure and secure dynamic updates
Dynamic updates of resource records are accepted from any client.
 This option is a significant security vulnerability because updates can be accepted from untrusted sources.
- ☐ Do not allow dynamic updates
Dynamic updates of resource records are not accepted by this zone. You must update these records manually.

< Back **Next >** Cancel

New Zone Wizard

Completing the New Zone Wizard

You have successfully completed the New Zone Wizard. You specified the following settings:

Name: 1.168.192.in-addr.arpa


Type: Active Directory-Integrated Primary

Lookup type: Reverse


Note: You should now add records to the zone or ensure that records are updated dynamically. You can then verify name resolution using nslookup.

To close this wizard and create the new zone, click Finish.

< Back **Finish** Cancel




As now our Reverse lookup zone created




Here is the concept Further Configuration

Now create Host Record for our Client(s)





Click on any blank area in Forward lookup zone server name after selecting it and you see the above options




Here Name should be as per your Client OS Name and IP Address should be your Client OS address, so let first confirm from there


Now go to the Reverse LookUp zone and create new PTR




Here the Host IP Address should be as per your Client OS IP Address
And then click on Browse



Then double click on Server1 (or any server name which you detect)



Then double click on forward lookup zone



And after last step you see your PC name which is PC1 or whatever you've created



After that you clearly see the Host Name as configured

And now create PTR for your Server1

New Resource Record

Pointer (PTR)

Host IP Address:
192.168.1.100

Fully qualified domain name (FQDN):
100.1.168.192.in-addr.arpa

Host name:
 Browse...

☐ Allow any authenticated user to update all DNS records with the same name. This setting applies only to DNS records for a new name.

OK Cancel

Browse

Look in: hpit.com

Records:


Name	Type	Data	Timestamp
_tcp			
_udp			
DomainDns...			
ForestDnsZ...			
(same as p...	Host (A)	192.168.1....	7/18/2021...
server1	Host (A)	192.168.1....	static
pc1	Host (A)	192.168.1....	

Selection: server1.hpit.com


Record types: Hosts (A or AAAA Records)

OK Cancel

And after going from all steps you see that option so select the Server1 and ok



Now Restart your Server1 to see the implementations /changes



Now Launch the NSLOOPUP of Server1

And type nslookup.domainname.com and vice versa

Similarly for pc1.domainname.com and vice versa

And now verify all things from your Server CMD and type there

Nslookup server1.domainname.com and vice versa with IP address

And similar for nslookup pc1.domainname.com and vice versa

And also ping it

And also verify all things from your PC

So from windows Right click on the **Network icon -> **Open network and sharing center** -> **Ethernet** -> **go to properties** -> **select IPV4 option** -> **click on properties****

And you see below all default things in the wizard



Make sure windows OS should be logged in as Admin, open it CMD and run nslookup.domainname.com and vice versa