

Created on....17.08.2016      Last changed on/by..... 29.06.2026 ABAP7  
Author.....ABAP4

---

Title.....SAP-ASRS SQL Data Push

Type.....1      Reporting

Status.....

Application.....

Class.....

Logical database.....

    from Application....

Selection screen.....

Authorization group...

Package.....ZMM

    Start by Variants

    Deactivate editor lock

X Fixed point arithmetic active

```
1  *&-----*
2  *& Report  ZDEMO_SQL_ASRS_SAP
3  *&
4  *&-----*
5  *&
6  *&
7  *&-----*
8
9  REPORT zmm_sql_asrs_sap_push.
10
11  TABLES: zmm_asrs.
12
13  SELECT-OPTIONS: s_type for zmm_asrs-msg_trans_type.
14
15  DATA: gs_asrs TYPE zmm_asrs,
16         gt_asrs TYPE STANDARD TABLE OF zmm_asrs,
17         gt_con  TYPE STANDARD TABLE OF zmm_dbcon_asrs,
18         gs_con  TYPE zmm_dbcon_asrs.
19  FIELD-SYMBOLS <fs_asrs> TYPE zmm_asrs.
20  DATA: dbs TYPE dbcon-con_name.
21  DATA: con(20) TYPE c.
22
23
24  START-OF-SELECTION.
25
26      SELECT *
27          FROM zmm_dbcon_asrs
28          INTO TABLE gt_con.
29
30
31
32
33
34
35
36  *WRITE sy-subrc.
37
38
39
40  DATA: lv_date TYPE char10.
41  DATA: lv_date1 TYPE char10.
42  DATA: lv_date2 TYPE char10.
43  SELECT *
44      FROM zmm_asrs
45      INTO CORRESPONDING FIELDS OF TABLE gt_asrs
46      WHERE msg_trans_type in s_type
47      AND trf_status = 'N'.
48  * lv_date = sy-datum.
49  * exec SQL.
50  * SELECT MSG_REC_ID FROM HOST_TO_WMS_TEST INTO :gs_asrs-msg_rec_id
51  * ENDEXEC.
52  DATA: exc_ref TYPE REF TO cx_sy_native_sql_error,
53         error_text TYPE string.
54
55  SORT gt_asrs BY plant.
56  LOOP AT gt_asrs ASSIGNING <fs_asrs>.
57      ON CHANGE OF <fs_asrs>-plant.
58          READ TABLE gt_con INTO gs_con WITH KEY werks = <fs_asrs>-plant.
59          IF sy-subrc <> 0.
60              CONTINUE.
61          ENDIF.
```

```
62      TRY.
63          IF con IS NOT INITIAL.
64              EXEC SQL.
65                  DISCONNECT :con
66              ENDEXEC.
67          ENDIF.
68          CLEAR con.
69          EXEC SQL. "#EC CI_EXECSQL
70              CONNECT TO :gs_con-DBCON
71          ENDEXEC.
72          EXEC SQL. "#EC CI_EXECSQL
73              GET CONNECTION :CON
74          ENDEXEC.
75          EXEC SQL.
76              SET CONNECTION :gs_con-DBCON
77          ENDEXEC.
78          CATCH cx_sy_native_sql_error INTO exc_ref.
79      ENDTRY.
80  ENDON.
81  gs_asrs = <fs_asrs>.
82
83  lv_date = gs_asrs-msg_dt_def.
84  IF gs_asrs-msg_dt_trm IS NOT INITIAL.
85      lv_date1 = gs_asrs-msg_dt_trm.
86  ENDIF.
87  IF gs_asrs-mfg_date IS NOT INITIAL.
88      lv_date2 = gs_asrs-mfg_date.
89  ENDIF.
90  TRY.
91      EXEC SQL.
92          INSERT INTO  host_to_wms  (MSG_SRC,
93                                     MSG_REC_ID,
94                                     MSG_TRANS_TYPE,
95                                     MSG_ACTION,
96                                     MSG_RET_SRC,
97                                     MSG_RET_REC_ID,
98                                     MSG_RET_TRANS_ID,
99                                     MSG_DT_DEF,
100                                    MSG_DT_TRM,
101                                    MSG_ERR,
102                                    MSG_ERR_DESC,
103                                    MSG_STAT,
104                                    GR_NO,
105                                    REQ_ID,
106                                    REQ_TYPE,
107                                    MAT_CODE,
108                                    DESCRIPTION,
109                                    UOM,
110                                    ITEM_TYPE,
111                                    SAP_BATCH,
112                                    QTY,
113                                    STATUS,
114                                    TOTAL_PACK,
115                                    MFG_DATE,
116                                    MANUFACTURER,
117                                    MFG_BATCH,
118                                    LINE_ITEM,
119                                    PLANT,
120                                    OLD_STATUS)
121          VALUES (
122                                     :gs_asrs-MSG_SRC
123                                     ,
124                                     :gs_asrs-MSG_REC_ID
125                                     ,
```

```
123                                     :gs_asrs-MSG_TRANS_TYPE ,
124                                     :gs_asrs-MSG_ACTION ,
125                                     :gs_asrs-MSG_RET_SRC ,
126                                     :gs_asrs-MSG_RET_REC_ID ,
127                                     :gs_asrs-MSG_RET_TRANS_ID ,
128                                     :lv_date,
129                                     :lv_date1,
130                                     :gs_asrs-MSG_ERR ,
131                                     :gs_asrs-MSG_ERR_DESC ,
132                                     :gs_asrs-MSG_STAT ,
133                                     :gs_asrs-GR_NO ,
134                                     :gs_asrs-REQ_ID ,
135                                     :gs_asrs-REQ_TYPE ,
136                                     :gs_asrs-MAT_CODE ,
137                                     :gs_asrs-DESCRIPTION ,
138                                     :gs_asrs-UOM ,
139                                     :gs_asrs-ITEM_TYPE ,
140                                     :gs_asrs-SAP_BATCH ,
141                                     :gs_asrs-QTY ,
142                                     :gs_asrs-STATUS ,
143                                     :gs_asrs-TOTAL_PACK ,
144                                     :lv_date2,
145                                     :gs_asrs-MANUFACTURER ,
146                                     :gs_asrs-MFG_BATCH ,
147                                     :gs_asrs-LINE_ITEM ,
148                                     :gs_asrs-PLANT,
149                                     :gs_asrs-OLD_STATUS )
150     ENDEXEC.
151
152     CATCH cx_sy_native_sql_error INTO exc_ref.
153       error_text = exc_ref->get_text( ).
154
155     CONTINUE.
156   ENDTRY.
157
158   COMMIT WORK AND WAIT .
159
160   * EXEC SQL.
161   *   DISCONNECT :con
162   * ENDEXEC.
163   <fs_asrs>-trf_status = 'Y'.
164   ENDLLOOP.
165
166   IF con IS NOT INITIAL.
167     EXEC SQL.
168       DISCONNECT :con
169     ENDEXEC.
170   ENDIF.
171   MODIFY zmm_asrs FROM TABLE gt_asrs.
```

Title:  
SAP-ASRS SQL Data Push

---

Selection texts:

S\_TYPE  
D .

DATABASE OPERATIONS

SELECT:

|                                           | Line | Page |
|-------------------------------------------|------|------|
| ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH       | 44   | 2    |
| ZMM_DBCON_ASRS..... ZMM_SQL_ASRS_SAP_PUSH | 27   | 2    |

---

MODIFY:

|                                     | Line | Page |
|-------------------------------------|------|------|
| ZMM_ASRS..... ZMM_SQL_ASRS_SAP_PUSH | 171  | 4    |

---

INTERNAL TABLE OPERATIONS

READ TABLE:

|                                   | Line | Page |
|-----------------------------------|------|------|
| GT_CON..... ZMM_SQL_ASRS_SAP_PUSH | 58   | 2    |

---