

Created on....17.08.2016 Last changed on/by..... 29.06.2026 ABAP7
Author.....ABAP4

Title.....SAP-ASRS SQL Data Push

Type.....1 Reporting

Status.....

Application.....

Class.....

Logical database.....

 from Application....

Selection screen.....

Authorization group...

Package.....ZMM

 Start by Variants

 Deactivate editor lock

X Fixed point arithmetic active

```
1  *&-----*
2  *& Report  ZDEMO_SQL_ASRS_SAP
3  *&
4  *&-----*
5  *&
6  *&
7  *&-----*
8
9  REPORT zmm_sql_asrs_sap_push_parfull.
10
11 TABLES: zmm_asrs.
12
13 SELECT-OPTIONS: s_type for zmm_asrs-msg_trans_type.
14
15 DATA: gs_asrs TYPE zmm_asrs,
16         gt_asrs TYPE STANDARD TABLE OF zmm_asrs,
17         gt_con TYPE STANDARD TABLE OF zmm_dbcon_asrs,
18         gs_con TYPE zmm_dbcon_asrs.
19 FIELD-SYMBOLS <fs_asrs> TYPE zmm_asrs.
20 DATA: dbs TYPE dbcon-con_name.
21 DATA: con(20) TYPE c.
22
23
24 START-OF-SELECTION.
25
26     SELECT *
27         FROM zmm_dbcon_asrs
28         INTO TABLE gt_con.
29
30
31
32
33
34
35
36 *WRITE sy-subrc.
37
38
39
40 DATA: lv_date TYPE char10.
41 DATA: lv_date1 TYPE char10.
42 DATA: lv_date2 TYPE char10.
43 SELECT *
44     FROM zmm_asrs
45     INTO CORRESPONDING FIELDS OF TABLE gt_asrs
46     WHERE msg_trans_type in s_type
47     AND trf_status = 'N'.
48 *   lv_date = sy-datum.
49 *   exec SQL.
50 *   SELECT MSG_REC_ID   FROM HOST_TO_WMS_TEST INTO :gs_asrs-msg_rec_id
51 *   ENDEXEC.
52 DATA: exc_ref    TYPE REF TO cx_sy_native_sql_error,
53         error_text TYPE string.
54
55 SORT gt_asrs BY plant.
56 LOOP AT gt_asrs ASSIGNING <fs_asrs>.
57     ON CHANGE OF <fs_asrs>-plant.
58         READ TABLE gt_con INTO gs_con WITH KEY werks = <fs_asrs>-plant.
59         IF sy-subrc <> 0.
60             CONTINUE.
61         ENDIF.
```

```
62      TRY.
63          IF con IS NOT INITIAL.
64              EXEC SQL.
65                  DISCONNECT :con
66              ENDEXEC.
67          ENDIF.
68          CLEAR con.
69          EXEC SQL. "#EC CI_EXECSQL
70              CONNECT TO :gs_con-DBCON
71          ENDEXEC.
72          EXEC SQL. "#EC CI_EXECSQL
73              GET CONNECTION :CON
74          ENDEXEC.
75          EXEC SQL.
76              SET CONNECTION :gs_con-DBCON
77          ENDEXEC.
78          CATCH cx_sy_native_sql_error INTO exc_ref.
79      ENDTRY.
80  ENDON.
81  gs_asrs = <fs_asrs>.
82
83  lv_date = gs_asrs-msg_dt_def.
84  IF gs_asrs-msg_dt_trm IS NOT INITIAL.
85      lv_date1 = gs_asrs-msg_dt_trm.
86  ENDIF.
87  IF gs_asrs-mfg_date IS NOT INITIAL.
88      lv_date2 = gs_asrs-mfg_date.
89  ENDIF.
90  TRY.
91      EXEC SQL.
92          INSERT INTO host_to_wms (MSG_SRC,
93                                  MSG_REC_ID,
94                                  MSG_TRANS_TYPE,
95                                  MSG_ACTION,
96                                  MSG_DT_DEF,
97                                  MSG_STAT,
98                                  REQ_TYPE,
99                                  MAT_CODE,
100                                 SAP_BATCH,
101                                 QTY,
102                                 STATUS,
103                                 plant,
104                                 OLD_STATUS)
105          VALUES (
106                  :gs_asrs-MSG_SRC ,
107                  :gs_asrs-MSG_REC_ID ,
108                  :gs_asrs-MSG_TRANS_TYPE ,
109                  :gs_asrs-MSG_ACTION ,
110                  :lv_date,
111                  :gs_asrs-MSG_STAT ,
112                  :gs_asrs-REQ_TYPE ,
113                  :gs_asrs-MAT_CODE ,
114                  :gs_asrs-SAP_BATCH ,
115                  :gs_asrs-QTY ,
116                  :gs_asrs-STATUS ,
117                  :gs_asrs-plant,
118                  :gs_asrs-OLD_STATUS )
119      ENDEXEC.
120  CATCH cx_sy_native_sql_error INTO exc_ref.
121      error_text = exc_ref->get_text( ).
122
```

```
123         CONTINUE.
124     ENDTRY.
125
126     COMMIT WORK AND WAIT .
127
128     * EXEC SQL.
129     *     DISCONNECT :con
130     * ENDEXEC.
131     <fs_asrs>-trf_status  = 'Y'.
132 ENDLOOP.
133
134 IF con IS NOT INITIAL.
135     EXEC SQL.
136         DISCONNECT :con
137     ENDEXEC.
138 ENDIF.
139 MODIFY zmm_asrs FROM TABLE gt_asrs.
```

Title:
SAP-ASRS SQL Data Push

Selection texts:

S_TYPE
D .

DATABASE OPERATIONS

SELECT:

		Line	Page
ZMM_ASRS.....	ZMM_SQL_ASRS_SAP_PUSH_PARFULL	44	2
ZMM_DBCON_ASRS.....	ZMM_SQL_ASRS_SAP_PUSH_PARFULL	27	2

MODIFY:

		Line	Page
ZMM_ASRS.....	ZMM_SQL_ASRS_SAP_PUSH_PARFULL	139	4

INTERNAL TABLE OPERATIONS

READ TABLE:

	Line	Page
GT_CON..... ZMM_SQL_ASRS_SAP_PUSH_PARFULL	58	2
