Created on....28.05.2013 Last changed on/by..... 16.02.2024 SAP
Author.....SAP

Title.....G/L Account Line Item Browser (G/L View)

Type.....1 Reporting
Status.....
Application.....F Financial accou
Class.....
Logical database.....
from Application.... Financial accou
Selection screen.....
Authorization group...
Package.....FAGL_REPORTING_EN

Start by Variants
Deactivate editor lock
X Fixed point arithmetic active

```
*&---------------------------------------------------------------------*
*& Report  FAGL_LINE_ITEM_BROWSER
*&
*&---------------------------------------------------------------------*
*&
*&
*&---------------------------------------------------------------------*
REPORT  fagl_line_item_browser
  MESSAGE-ID fagl_account_balance.

INCLUDE fagl_line_item_browser_top.
INCLUDE fagl_line_item_browser_ptop. " PIVB specific variables
INCLUDE fagl_line_item_browser_pcld. " local class def.
INCLUDE fagl_line_item_browser_ps01. " selection screen

INCLUDE fagl_line_item_browser_gpc.  "3031177

*---------------------------------------------------------------------*
AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_layout.
  PERFORM disvar_value_request
    USING
      sy-repid
      gc_handle_main
    CHANGING
      p_layout.

*---------------------------------------------------------------------*
AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_dfile.
  PERFORM filename_value_request
    CHANGING
      p_dfile.

*---------------------------------------------------------------------*
AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_pcgrp.
  PERFORM group_value_request
    USING
      gc_s_setclass-pc_group
      'P_PCGRP'
    CHANGING
      p_pcgrp.

*---------------------------------------------------------------------*
AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_acgrp.
  PERFORM group_value_request
    USING
      gc_s_setclass-acct_group
      'P_ACGRP'
    CHANGING
      p_acgrp.

*---------------------------------------------------------------------*
AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_setbuk.  "begin of "n2869685
  PERFORM set_value_request
    USING
      'BUKRS'                                              "#EC NO_TEXT
    CHANGING
      p_setbuk.

AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_setrac.
  PERFORM set_value_request
    USING
```

```
62          'RACCT'                                                  "#EC NO_TEXT
63        CHANGING
64          p_setrac.
65
66    AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_setven.
67      PERFORM set_value_request
68        USING
69          'LIFNR'                                                  "#EC NO_TEXT
70        CHANGING
71          p_setven.
72
73    AT SELECTION-SCREEN ON VALUE-REQUEST FOR p_setcus.
74      PERFORM set_value_request
75        USING
76          'KUNNR'                                                  "#EC NO_TEXT
77        CHANGING
78          p_setcus.                                              "end of "n2869685
79
80    AT SELECTION-SCREEN ON BLOCK prctr.
81      PERFORM selection_screen_prctr.
82
83    AT SELECTION-SCREEN ON BLOCK acgrp.
84      PERFORM selection_screen_racct.
85
86    *---------------------------------------------------------------------*
87    LOAD-OF-PROGRAM.
88
89    * register ABAP report events to be handled
90      gr_screen = cl_kess_free_selection=>get_instance( ).
91      SET HANDLER cl_screen_handler=>init_sel_screen    FOR gr_screen.
92      SET HANDLER cl_screen_handler=>initialization     FOR gr_screen.
93      SET HANDLER cl_screen_handler=>start_selection    FOR gr_screen.
94      SET HANDLER cl_screen_handler=>sel_screen         FOR gr_screen.
95      SET HANDLER cl_screen_handler=>sel_screen_output  FOR gr_screen.
96      SET HANDLER cl_screen_handler=>fieldcat_adjust    FOR gr_screen.
97
98    *---------------------------------------------------------------------*
99      INCLUDE fagl_line_item_browser_pforms.
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_CHOOSE_LEDGER .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  choose_ledger
6  *&---------------------------------------------------------------------*
7  FORM choose_ledger
8              TABLES it_chosen_values TYPE ty_sval
9              USING uc_relevant_ledger TYPE rldnr_flex
10             CHANGING cc_new_ledger TYPE rldnr_flex.
11
12   INCLUDE <icon>.
13
14   DATA ic_icon_okay LIKE icon-name.
15   DATA ic_icon_save LIKE icon-name.
16
17 * set exporting parameters for function modul
18 * POPUP_GET_VALUES_USER_BUTTONS
19 *  it_chosen_values-tabname = 'T881'.
20 *  it_chosen_values-fieldname = 'RLDNR'.
21   LOG-POINT ID fins_udoc.
22   IF cl_fins_acdoc_util=>get_acdoc_activation_status( ) = if_fins_acdoc_
   constants=>gc_acdoc_activation_status-inactive.
23     it_chosen_values-tabname = 'BKPF'.
24   ELSE.
25     it_chosen_values-tabname = if_fins_acdoc_constants=>gc_tabname_acdoc
   a.
26   ENDIF.
27   it_chosen_values-fieldname = 'RLDNR'.
28   it_chosen_values-field_obl = 'X'.
29   it_chosen_values-value     = uc_relevant_ledger.
30   APPEND it_chosen_values.
31
32   ic_icon_okay = icon_okay.
33   ic_icon_save = icon_system_save.
34
35 * call function modul
36
37   CALL FUNCTION 'POPUP_GET_VALUES_USER_BUTTONS'
38     EXPORTING
39 *     F1_FORMNAME         = ' '
40 *     F1_PROGRAMNAME      = ' '
41       f4_formname         = 'F4_LEDGER'
42       f4_programname      = 'FAGL_ACCOUNT_BALANCE'
43       formname            = 'CHECK_OK_CODES'
44       programname         = 'FAGL_ACCOUNT_BALANCE'
45       popup_title         = 'Ledger setzen'(025)
46       ok_pushbuttontext   = ''
47       icon_ok_push        = ic_icon_okay
48       quickinfo_ok_push   = TEXT-008
49       first_pushbutton    = ' '
50       icon_button_1       = ic_icon_save
51       quickinfo_button_1  = TEXT-009
52 *     SECOND_PUSHBUTTON   = ' '
53 *     ICON_BUTTON_2       =
54 *     QUICKINFO_BUTTON_2  = ' '
55       start_column        = '25'
56       start_row           = '7'
57 *     NO_CHECK_FOR_FIXED_VALUES       = ' '
58 * IMPORTING
59 *     RETURNCODE          =
```

```
60      TABLES
61        fields              = it_chosen_values
62      EXCEPTIONS
63        error_in_fields     = 1
64        OTHERS              = 2.
65
66    IF sy-subrc <> 0.
67      MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
68              WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
69    ENDIF.
70
71    cc_new_ledger = it_chosen_values-value.
72
73  ENDFORM.                    " choose_ledger
74
75  *&---------------------------------------------------------------------*
76  *&      Form  f4_ledger
77  *&---------------------------------------------------------------------*
78  *       text
79  *----------------------------------------------------------------------*
80  FORM f4_ledger USING tabname TYPE tabname fieldname TYPE fieldname displ
    ay TYPE flag
81                 CHANGING returncode TYPE char1 value TYPE c.
82
83    LOG-POINT ID fins_udoc SUBKEY 'FGL'.
84
85    DATA: lt_return     TYPE TABLE OF ddshretval,
86          ls_return     TYPE ddshretval,
87          ld_searchhelp TYPE shlpname.
88
89    ASSERT tabname = 'BKPF' OR tabname = if_fins_acdoc_constants=>gc_tabna
    me_acdoca AND fieldname = 'RLDNR'.
90
91    CASE tabname.
92      WHEN 'BKPF'.
93        ld_searchhelp = 'FAGL_RLDNR_WITH_DEPENDENT'.
94      WHEN if_fins_acdoc_constants=>gc_tabname_acdoca.
95        ld_searchhelp = 'FINS_LEDGER'.
96      WHEN OTHERS.
97        ASSERT 1 = 2.
98    ENDCASE.
99
100   CALL FUNCTION 'F4IF_FIELD_VALUE_REQUEST'
101     EXPORTING
102       tabname           = tabname
103       fieldname         = fieldname
104       searchhelp        = ld_searchhelp
105 *     SHLPPARAM         = ' '
106 *     DYNPPROG          = ' '
107 *     DYNPNR            = ' '
108 *     DYNPROFIELD       = ' '
109 *     STEPL             = 0
110       value             = CONV help_info-fldvalue( value )
111 *     MULTIPLE_CHOICE   = ' '
112 *      display           = display
113 *     SUPPRESS_RECORDLIST       = ' '
114 *     CALLBACK_PROGRAM  = ' '
115 *     CALLBACK_FORM     = ' '
116 *     SELECTION_SCREEN  = ' '
117 *  IMPORTING
118 *     USER_RESET        =
```

```
119       TABLES
120         return_tab        = lt_return
121       EXCEPTIONS
122         field_not_found   = 1
123         no_help_for_field = 2
124         inconsistent_help = 3
125         no_values_found   = 4
126         OTHERS            = 5.
127     IF sy-subrc <> 0.
128       MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
129                  WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
130     ENDIF.
131
132     READ TABLE lt_return INTO ls_return INDEX 1.
133     IF sy-subrc NE 0.
134       returncode = 'A'.
135     ELSE.
136       CLEAR returncode.
137       value = ls_return-fieldval.
138     ENDIF.
139
140   ENDFORM.                                                    "f4_ledger
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_HR_ONLY_CHECK .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  hr_only_check
6  *&---------------------------------------------------------------------*
7  FORM hr_only_check  CHANGING p_cc_hr_only TYPE boolean.
8    DATA: ld_appl_system_type LIKE tcesyst-devtype.
9    CONSTANTS: c_erp_system LIKE tcesyst-devtype VALUE 'T',
10             c_hr_system  LIKE tcesyst-devtype VALUE 'H'.
11
12   CALL FUNCTION 'RH_APPLICATION_SYSTEM_CHECK'
13     IMPORTING
14       application_system_type = ld_appl_system_type
15     EXCEPTIONS
16       system_type_unknown     = 1
17       basis_system            = 2
18       OTHERS                  = 3.
19   IF sy-subrc <> 0.
20 *   ERROR: NO APPLICATION SYSTEM -> DUMP
21     RAISE no_application_system.
22   ELSE.
23     CASE ld_appl_system_type.
24       WHEN c_erp_system.
25 *       ENTERPRISE SYSTEM ( = TOTAL SAP R/3 SYSTEM )
26         p_cc_hr_only = '-'.
27       WHEN c_hr_system.
28 *       HR STAND ALONE
29         p_cc_hr_only = 'X'.
30       WHEN OTHERS.
31 *       ERROR: UNKNOWN APPLICATION SYSTEM -> worst
32         p_cc_hr_only = '='.
33     ENDCASE.
34   ENDIF.
35
36
37 ENDFORM.                    " hr_only_check
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_CL5
3  *&---------------------------------------------------------------------*
4    METHOD start_selection.
5      CHECK gd_exit IS INITIAL.
6      PERFORM main.
7    ENDMETHOD.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_CL7
3  *&---------------------------------------------------------------------*
4    METHOD sel_screen_output.
5      PERFORM selection_screen_output.
6    ENDMETHOD.
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_CL8
*&---------------------------------------------------------------------*
METHOD fieldcat_adjust.
*---------------------------------------------------------------------*
  DATA ls_sel_view                TYPE rsdsqcat.
  DATA ld_base_table              TYPE tabname.
  DATA lt_excluded_fields         TYPE rsdsselopt_t.
  DATA ls_range                   TYPE rsdsselopt.
  DATA lt_table_range             TYPE rsds_trange.           "n2748811
*---------------------------------------------------------------------*
  FIELD-SYMBOLS <ls_fcat>         TYPE kess_ys_fcat.
  FIELD-SYMBOLS <ls_trange>       TYPE rsds_range.            "n2748811
  FIELD-SYMBOLS <ls_frange>       TYPE rsds_frange.           "n2748811
*---------------------------------------------------------------------*
  PERFORM sel_view_check_get
    USING
      gd_sel_view
    CHANGING
      ls_sel_view
      ld_base_table.

  CALL FUNCTION 'FAGL_HDB_CUST_SVIEW_EXCL_FLDS'
    EXPORTING
      ed_appl            = gc_hdb_appl-financials
      ed_subappl         = gd_subapplication
      es_sel_view        = ls_sel_view
    IMPORTING
      it_excl_fields_sel = lt_excluded_fields.

  ls_range-sign   = 'I'.
  ls_range-option = 'EQ'.
  ls_range-low    = 'COUNTER'.
  APPEND ls_range
    TO lt_excluded_fields.

*** Note 2871375: Prioritize KESS over additional restrictions
***                (too confusing otherwise)
** If the user has pre-filled values with BAdI meth. "begin of "n2748811
** CREATE_DEFAULT_RESTRICTIONS, exclude from KESS
** since both Selection criteria are linked with logical OR
*  IF go_badi_lib IS NOT INITIAL.
*    CALL BADI go_badi_lib->create_default_restrictions
*      EXPORTING
*        id_sel_view     = gd_sel_view
*      CHANGING
*        ct_table_range  = lt_table_range.
*
*    CLEAR ls_range.
*    ls_range-sign   = 'I'.
*    ls_range-option = 'EQ'.
*    LOOP AT lt_table_range ASSIGNING <ls_trange>.
*      LOOP AT <ls_trange>-frange_t ASSIGNING <ls_frange>.
*        ls_range-low = <ls_frange>-fieldname.
*        COLLECT ls_range INTO lt_excluded_fields.
*      ENDLOOP.
*    ENDLOOP.
*  ENDIF.                                              "end of "n2748811

  LOOP AT et_fcat
    ASSIGNING <ls_fcat>.
```

```
62      IF <ls_fcat>-fieldname IN lt_excluded_fields.
63        <ls_fcat>-excluded = abap_true.
64      ENDIF.
65    ENDLOOP.
66
67    gr_screen->set_fcat( et_fcat ).
68
69  ENDMETHOD.
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F02 .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  INITIALIZATION
6  *&---------------------------------------------------------------------*
7  FORM initialization .
8  *---------------------------------------------------------------------*
9    STATICS sd_done.
10 *---------------------------------------------------------------------*
11   DATA ls_text                LIKE smp_dyntxt.
12   DATA ls_dfies               TYPE dfies.
13   DATA lt_textpool            TYPE STANDARD TABLE OF textpool.
14   DATA ls_textpool            TYPE textpool.
15   DATA lt_hdb_range           TYPE hdb_t_range.
16   DATA ls_hdb_range           TYPE hdb_s_range.
17   DATA ld_data_source         TYPE tabname.
18   DATA ld_string              TYPE string.
19   DATA lth_string             TYPE HASHED TABLE OF string
20                               WITH UNIQUE DEFAULT KEY.
21   DATA ld_tabname             TYPE tabname.
22   DATA lt_view                TYPE viewnames.
23   DATA ld_pivb_last_tab       TYPE usr05-parva.
24   DATA ld_par_fit_x(16).                                    "n2584751
25   DATA ld_fagl_sett_value     TYPE fagl_settings-param_value."n2869685
26
27   data ls_sel_view            type rsdsqcat.
28 *---------------------------------------------------------------------*
29   FIELD-SYMBOLS <text>        LIKE gd_xoim.
30 *---------------------------------------------------------------------*
31   CHECK sd_done IS INITIAL.
32   sd_done = abap_true.
33
34   s_ccode-sign   = s_racct-sign = s_cust-sign = s_vend-sign  = 'I'.
      "3107804
35   s_ccode-option = s_racct-option = s_cust-option = s_vend-option  = 'EQ
   '. "3107804
36
37 * get utility
38   go_util = cl_fagl_lib_util_factory=>get_instance( sy-repid ).
39
40   IF p_appl IS INITIAL.
41 * Try to decide what is relevant
42 * >> Main program name
43   CASE sy-repid.
44     WHEN 'FAGL_LINE_ITEM_BROWSER_AP'.
45       p_appl = gc_hdb_subappl-s_payables-line_item_browser.
46     WHEN 'FAGL_LINE_ITEM_BROWSER_CGL'.
47       p_appl = gc_hdb_subappl-s_classic_gl-line_item_browser.
48     WHEN 'FAGL_LINE_ITEM_BROWSER_AR'.
49       p_appl = gc_hdb_subappl-s_receivables-line_item_browser.
50     WHEN 'FAGL_LINE_ITEM_BROWSER'.
51       p_appl = gc_hdb_subappl-s_newgl-gl_view.
52     WHEN 'FAGL_LINE_ITEM_BROWSER_EV'.
53       p_appl = gc_hdb_subappl-s_newgl-entry_view.
54     WHEN 'FAGL_LINE_ITEM_BROWSER_PCA'.
55       p_appl = gc_hdb_subappl-s_pca-line_item_browser.
56     WHEN 'FAGL_LINE_ITEM_BROWSER_SL'.
57       p_appl = gc_hdb_subappl-s_special_ledger-line_item_browser.
58   ENDCASE.
59   ENDIF.
```

```
 60
 61  * set data view
 62    ge_appl_view = switch #( p_appl when gc_hdb_subappl-s_newgl-gl_view th
    en fi_gl
 63                                    when gc_hdb_subappl-s_pca-line_item_br
    owser then pca
 64                                    when gc_hdb_subappl-s_special_ledger-l
    ine_item_browser then sl
 65                                    else fi_entry ).
 66
 67  * register main selection type
 68    CASE p_appl.
 69      WHEN gc_hdb_subappl-s_newgl-gl_view
 70        OR gc_hdb_subappl-s_newgl-entry_view
 71        OR gc_hdb_subappl-s_classic_gl-line_item_browser.
 72        go_util->register( value #( ( 'hkont;s_racct' ) ) ).
 73        go_util->register( value #( ( 'bukrs;s_ccode' ) ) ).
 74      WHEN gc_hdb_subappl-s_receivables-line_item_browser.
 75        go_util->register( value #( ( 'kunnr;s_cust' ) ( 'koart;s_acctp' )
     ) ).
 76        go_util->register( value #( ( 'bukrs;s_ccode' ) ) ).
 77      WHEN gc_hdb_subappl-s_payables-line_item_browser.
 78        go_util->register( value #( ( 'lifnr;s_vend' ) ( 'koart;s_acctp' )
     ) ).
 79        go_util->register( value #( ( 'bukrs;s_ccode' ) ) ).
 80      WHEN gc_hdb_subappl-s_pca-line_item_browser.
 81        go_util->register( value #( ( 'kokrs;s_coarea'     )
 82                                    ( 'rbukrs;s_ccode'     )
 83                                    ( 'racct;s_racct'      )
 84                                    ( 'ryear;s_ryear'      )
 85                                    ( 'poper;s_period'     )
 86                                    ( 'rprctr;s_rprctr'    )
 87                                    ( 'activ;s_activ'      ) "N3231363
 88                                    ( 'rhoart;s_rhoart'    )
 89                                    ( 'docnr;s_docnr'      )
 90                                    ( 'refdocnr;s_rdocnr' ) ) ).
 91      WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
 92      WHEN OTHERS.
 93        go_util->register( value #( ( 'hkont;s_racct' ) ) ).
 94        go_util->register( value #( ( 'kunnr;s_cust' ) ( 'koart;s_acctp' )
     ) ).
 95        go_util->register( value #( ( 'lifnr;s_vend' ) ( 'koart;s_acctp' )
     ) ).
 96        go_util->register( value #( ( 'bukrs;s_ccode' ) ) ).
 97    ENDCASE.
 98
 99    CASE p_appl.
100      WHEN gc_hdb_subappl-s_payables-line_item_browser.
101        MOVE-CORRESPONDING s_racct TO s_vend.
102        IF sy-calld IS INITIAL.                              "n3026074
103          GET PARAMETER ID 'LIF' FIELD s_vend-low.
104        ENDIF.                                               "n3026074
105        IF s_vend-low IS NOT INITIAL.
106          APPEND s_vend.
107        ENDIF.
108        GET PARAMETER ID 'FIT_X_AP' FIELD ld_par_fit_x.      "n2584751
109        p_ty_ar = ld_par_fit_x+4(1).                         "n2584751
110      WHEN gc_hdb_subappl-s_classic_gl-line_item_browser.
111        IF sy-calld IS INITIAL.                              "n3026074
112          GET PARAMETER ID 'ACC' FIELD s_racct-low.
113        ENDIF.                                               "n3026074
```

```
114       IF s_racct-low IS NOT INITIAL.
115         APPEND s_racct.
116       ENDIF.
117       GET PARAMETER ID 'FIT_X_GL' FIELD ld_par_fit_x.       "n2584751
118     WHEN gc_hdb_subappl-s_receivables-line_item_browser.
119       IF sy-calld IS INITIAL.                               "n3026074
120         GET PARAMETER ID 'KUN' FIELD s_cust-low.
121       ENDIF.                                                "n3026074
122       IF s_cust-low IS NOT INITIAL.
123         APPEND s_cust.
124       ENDIF.
125       GET PARAMETER ID 'FIT_X_AR' FIELD ld_par_fit_x.       "n2584751
126       p_ty_ap = ld_par_fit_x+4(1).                          "n2584751
127     WHEN gc_hdb_subappl-s_newgl-gl_view.
128       IF sy-calld IS INITIAL.                               "n3026074
129         GET PARAMETER ID 'ACC' FIELD s_racct-low.
130       ENDIF.                                                "n3026074
131       IF s_racct-low IS NOT INITIAL.
132         APPEND s_racct.
133       ENDIF.
134
135       IF gd_modif_2818431 = abap_undefined.       "begin of "n2816760
136         CALL FUNCTION 'FAGL_GET_FAGL_SETTINGS'
137           EXPORTING
138             id_param_name       = 'FAGL_BROWSE_N2818431'
139           IMPORTING
140             ed_value            = ld_fagl_sett_value.
141         gd_modif_2818431 = ld_fagl_sett_value.
142       ENDIF.                                        "end of "n2816760
143     WHEN gc_hdb_subappl-s_newgl-entry_view.
144       IF sy-calld IS INITIAL.                               "n3026074
145         GET PARAMETER ID 'ACC' FIELD s_racct-low.
146       ENDIF.                                                "n3026074
147       IF s_racct-low IS NOT INITIAL.
148         APPEND s_racct.
149       ENDIF.
150     WHEN gc_hdb_subappl-s_pca-line_item_browser.
151       p_ledger = '8A'.
152     WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
153       IF p_ledger IS INITIAL.
154         GET PARAMETER ID 'GLN'
155           FIELD p_ledger.
156       ENDIF.
157       CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
158         EXPORTING
159           id_rldnr           = p_ledger
160         IMPORTING
161           ed_tabname         = gd_sel_view
162         EXCEPTIONS
163           ledger_not_allowed = 1
164           table_not_allowed  = 2
165           view_not_generated = 3
166           OTHERS             = 4.
167       IF sy-subrc <> 0.
168         MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
169                 WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
170         LEAVE PROGRAM.
171       ENDIF.
172
173 *     create dummy entry to collect psx_item and psx_kess in GD20H
174       append value #( tablename = gd_sel_view ) to psx_item-trange.
```

```
175    ENDCASE.
176
177    IF ld_par_fit_x IS NOT INITIAL.                          "begin "n2584751
178      p_ty_nor = ld_par_fit_x(1).
179      p_ty_spg = ld_par_fit_x+1(1).
180      p_ty_nit = ld_par_fit_x+2(1).
181      p_ty_pit = ld_par_fit_x+3(1).
182    ENDIF.                                                   "end "n2584751
183
184    IF p_appl IS NOT INITIAL.
185      gd_hide_appl = abap_true.
186    ENDIF.
187
188    IF sy-calld IS INITIAL.                                    "n3026074
189      GET PARAMETER ID 'BUK' FIELD s_ccode-low.
190    ENDIF.                                                     "n3026074
191    IF s_ccode-low IS NOT INITIAL.
192      APPEND s_ccode.
193    ENDIF.
194
195    CALL FUNCTION 'FAGL_DBCON_GET_APPL'
196      IMPORTING
197        e_hdb_is_primary = gd_hdb_is_primary.
198
199    CASE p_appl.
200      WHEN gc_hdb_subappl-s_newgl-gl_view.
201        ls_text-icon_id   = icon_summarize_undo.
202        ls_text-icon_text =
203        ls_text-text      = 'Entry View'(035).
204        sscrfields-functxt_02 = ls_text.
205      WHEN gc_hdb_subappl-s_newgl-entry_view.
206        ls_text-icon_id   = icon_summarize_undo.
207        ls_text-icon_text =
208        ls_text-text      = 'G/L View'(036).
209        sscrfields-functxt_02 = ls_text.
210    ENDCASE.
211
212    IF ge_appl_view = fi_gl or ge_appl_view = sl.
213      ls_text-icon_id = icon_other_object.
214      ls_text-icon_text = ls_text-text = 'Choose Ledger'(034).
215      sscrfields-functxt_03 = ls_text.
216    ENDIF.
217
218    gd_subapplication = p_appl.
219    IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
220      OR gd_subapplication = gc_hdb_subappl-s_newgl-entry_view.
221      gd_subapplication = fbcon_hdb_subappl-s_new_gl-line_item_browser.
222    ENDIF.
223
224    IF gd_subapplication <> gc_hdb_subappl-s_special_ledger-line_item_brow
       ser.
225      CALL FUNCTION 'HDB_SETT_AUTHORITY_CHECK'
226      EXPORTING
227        id_application    = gc_hdb_appl-financials
228        id_subapplication = gd_subapplication
229        id_activity       = '03'
230      EXCEPTIONS
231        OTHERS            = 1.
232
233    IF sy-subrc = 0.
234      CLEAR ls_text.
```

```
235       ls_text-icon_id = icon_table_settings.
236       CALL FUNCTION 'DDIF_FIELDINFO_GET'
237         EXPORTING
238           tabname   = 'SETUP'
239           all_types = 'X'
240         IMPORTING
241           dfies_wa  = ls_dfies.
242
243       ls_text-text          = ls_dfies-scrtext_m.
244         sscrfields-functxt_04 = ls_text.
245       ENDIF.
246     ENDIF.
247
248     CALL FUNCTION 'FAGL_GET_FAGL_SETTINGS'
249     EXPORTING
250       id_param_name       = 'FAGL_LIB_SETS' "#EC NO_TEXT
251     IMPORTING
252       ed_value            = ld_fagl_sett_value.
253     gd_consider_sets = ld_fagl_sett_value.
254
255     "Activate worklist feature if desired             "begin of "n2767139
256     IF gd_consider_sets <> abap_true.
257       GET PARAMETER ID 'FI_WORKLISTS_FLAG' FIELD gd_consider_worklists.
258     ENDIF.
259
260     IF gd_consider_worklists = abap_true
261       OR gd_consider_sets = abap_true.
262       READ TEXTPOOL 'FAGL_LINE_ITEM_BROWSER_CGL'
263         INTO lt_textpool.
264       SORT lt_textpool BY key ASCENDING.
265
266   **  Get texts for buttons
267       READ TABLE lt_textpool
268         WITH KEY key = 'WL0'
269         INTO ls_textpool
270         TRANSPORTING ALL FIELDS
271         BINARY SEARCH.
272       gs_text_wl-activate = ls_textpool-entry.
273
274       READ TABLE lt_textpool
275         WITH KEY key = 'WL1'
276         INTO ls_textpool
277         TRANSPORTING ALL FIELDS
278         BINARY SEARCH.
279       gs_text_wl-deactivate = ls_textpool-entry.
280
281       READ TABLE lt_textpool
282         WITH KEY key = 'ST0'
283         INTO ls_textpool
284         TRANSPORTING ALL FIELDS
285         BINARY SEARCH.
286       gs_text_set-activate = ls_textpool-entry.
287
288       READ TABLE lt_textpool
289         WITH KEY key = 'ST1'
290         INTO ls_textpool
291         TRANSPORTING ALL FIELDS
292         BINARY SEARCH.
293       gs_text_set-deactivate = ls_textpool-entry.
294
295       IF gd_consider_worklists = abap_true.
```

```
296         IF gd_worklist_active = abap_true.
297           "Deactivate Worklist
298           sscrfields-functxt_05 = gs_text_wl-deactivate.
299         ELSE.
300           "Activate Worklist
301           sscrfields-functxt_05 = gs_text_wl-activate.
302         ENDIF.
303       ENDIF.
304
305       IF gd_consider_sets = abap_true.
306         IF gd_sets_active = abap_true.
307           "Deactivate Sets
308           sscrfields-functxt_05 = gs_text_set-deactivate.
309         ELSE.
310           "Activate Sets
311           sscrfields-functxt_05 = gs_text_set-activate.
312         ENDIF.
313       ENDIF.
314     ELSE.
315       CLEAR sscrfields-functxt_05.
316     ENDIF.                                              "end of "n2767139
317
318   * Set Selection View according to current findings.
319     if cl_fagl_lib_cds_util=>is_cds_on( iv_appl = gc_hdb_appl-financials i
    v_subappl = gd_subapplication ) = abap_true.
320       gd_sel_view = cl_fagl_lib_cds_util=>get_view( iv_appl = gc_hdb_appl-
    financials iv_subappl = conv #( p_appl ) ).
321       gd_cds_on = abap_true.
322     else.
323   * Get settings for data source
324       CASE p_appl.
325         WHEN gc_hdb_subappl-s_pca-line_item_browser.
326           gd_sel_view = gc_s_hdb_ddic-pca_line_items_ext.
327         WHEN gc_hdb_subappl-s_receivables-line_item_browser.
328           gd_sel_view = gc_s_hdb_ddic-ar_line_items.
329         WHEN gc_hdb_subappl-s_payables-line_item_browser.
330           gd_sel_view = gc_s_hdb_ddic-ap_line_items.
331         WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
332           CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
333             EXPORTING
334               id_rldnr           = p_ledger
335             IMPORTING
336               ed_tabname         = gd_sel_view
337             EXCEPTIONS
338               OTHERS     = 0.
339         WHEN OTHERS.
340           if ge_appl_view = fi_gl.
341             gd_sel_view = gc_s_hdb_ddic-gl_view_ext.
342           else.
343             gd_sel_view = gc_s_hdb_ddic-gl_line_items.
344           endif.
345       ENDCASE.
346     endif.
347
348     IF ge_appl_view = fi_gl or ge_appl_view = sl.
349       PERFORM find_relevant_ledger
350         CHANGING
351           p_ledger.
352     ENDIF.
353
354     PERFORM layouts_check.
```

```
355
356 * Check whether views need to be generated
357   if gd_cds_on = abap_true.
358     cl_fagl_lib_cds_util=>regenerate(
359       exporting
360         iv_reset    = abap_false
361         iv_save_log = abap_false
362         iv_no_display = abap_true
363         iv_view = gd_sel_view ).
364   else.
365     APPEND gd_sel_view TO lt_view.
366     CALL FUNCTION 'FAGL_VIEWS_GENERATE_ALL'
367       EXPORTING
368         id_force_view_generation = space
369         id_force_org_generation  = space
370         it_required_views        = lt_view.
371   endif.
372
373   CALL FUNCTION 'ICON_CREATE'
374     EXPORTING
375       name       = icon_information
376       text       = 'Careful when specifying year and period'(033)
377       add_stdinf = space
378     IMPORTING
379       result     = gd_ypcmt
380     EXCEPTIONS
381       OTHERS     = 0.
382
383   CALL FUNCTION 'DDIF_FIELDINFO_GET'
384     EXPORTING
385       tabname   = 'FAGL_OPEN_ITEM_INCL_NON_OI_ACC'
386       all_types = 'X'
387     IMPORTING
388       dfies_wa  = ls_dfies.
389
390   gd_xoim = ls_dfies-reptext.
391
392   CALL FUNCTION 'DDIF_FIELDINFO_GET'
393     EXPORTING
394       tabname   = 'FAGL_DOWNLOAD_FIRST_LIST'
395       all_types = 'X'
396     IMPORTING
397       dfies_wa  = ls_dfies.
398
399   gd_outfi = ls_dfies-reptext.
400
401   CALL FUNCTION 'DDIF_FIELDINFO_GET'
402     EXPORTING
403       tabname   = 'FAGL_DOWNLOAD_DISPLAY_RESULT'
404       all_types = 'X'
405     IMPORTING
406       dfies_wa  = ls_dfies.
407
408   gd_outli = ls_dfies-reptext.
409
410   CALL FUNCTION 'DDIF_FIELDINFO_GET'
411     EXPORTING
412       tabname   = 'FAGL_DOWNLOAD_PRES_SERVER'
413       all_types = 'X'
414     IMPORTING
415       dfies_wa  = ls_dfies.
```

```
416
417     gd_dpres = ls_dfies-reptext.
418
419     CALL FUNCTION 'DDIF_FIELDINFO_GET'
420       EXPORTING
421         tabname   = 'FAGL_DOWNLOAD_APPL_SERVER'
422         all_types = 'X'
423       IMPORTING
424         dfies_wa  = ls_dfies.
425
426     gd_dappl = ls_dfies-reptext.
427
428     CALL FUNCTION 'DDIF_FIELDINFO_GET'
429       EXPORTING
430         tabname   = 'FAGL_DOWNLOAD_MODE_RAW'
431         all_types = 'X'
432       IMPORTING
433         dfies_wa  = ls_dfies.
434
435     gd_dmraw = ls_dfies-reptext.
436
437     CALL FUNCTION 'DDIF_FIELDINFO_GET'
438       EXPORTING
439         tabname   = 'FAGL_DOWNLOAD_MODE_XML'
440         all_types = 'X'
441       IMPORTING
442         dfies_wa  = ls_dfies.
443
444     gd_dmxml = ls_dfies-reptext.
445
446     CALL FUNCTION 'DDIF_FIELDINFO_GET'
447       EXPORTING
448         tabname   = 'FAGL_DOWNLOAD_MODE_CMP'
449         all_types = 'X'
450       IMPORTING
451         dfies_wa  = ls_dfies.
452
453     gd_dmcmp = ls_dfies-reptext.
454
455     CALL FUNCTION 'DDIF_FIELDINFO_GET'
456       EXPORTING
457         tabname   = 'FAGL_DOWNLOAD_WR_HEAD'
458         all_types = 'X'
459       IMPORTING
460         dfies_wa  = ls_dfies.
461
462     gd_dwhdr = ls_dfies-reptext.
463
464     CALL FUNCTION 'DDIF_FIELDINFO_GET'
465       EXPORTING
466         tabname   = 'FAGL_DOWNLOAD_WR_META'
467         all_types = 'X'
468       IMPORTING
469         dfies_wa  = ls_dfies.
470
471     gd_dwmta = ls_dfies-reptext.
472
473     CALL FUNCTION 'DDIF_FIELDINFO_GET'                    "n2494719
474       EXPORTING                                           "n2494719
475         tabname   = 'FAGL_YEC_DATA_SEL'                   "n2494719
476         all_types = 'X'                                   "n2494719
```

```
477       IMPORTING                                                    "n2494719
478         dfies_wa  = ls_dfies.                                      "n2494719
479
480     gd_tygly = ls_dfies-reptext.                                   "n2494719
481
482     CALL FUNCTION 'DDIF_FIELDINFO_GET'                             "n2816760
483       EXPORTING                                                    "n2816760
484         tabname   = 'FAGL_LEDGER_EXT_ONLY_SEL'                     "n2816760
485         all_types = 'X'                                            "n2816760
486       IMPORTING                                                    "n2816760
487         dfies_wa  = ls_dfies.                                      "n2816760
488
489     gd_exrld = ls_dfies-reptext.                                   "n2816760
490
491     CALL FUNCTION 'DDIF_FIELDINFO_GET'
492       EXPORTING
493         tabname   = 'FAGL_ENFOJ'
494         all_types = 'X'
495       IMPORTING
496         dfies_wa  = ls_dfies.
497
498     ASSIGN ('GD_ENFOJ') TO <text>.
499     IF sy-subrc = 0.
500       <text> = ls_dfies-scrtext_l.
501     ENDIF.
502
503     READ TEXTPOOL 'FAGL_LINE_ITEM_BROWSER_CGL'
504       INTO lt_textpool.
505
506     LOOP AT lt_textpool
507       INTO  ls_textpool.
508       CASE ls_textpool-key.
509         WHEN 'B05'.
510           textb05 = ls_textpool-entry.
511         WHEN 'B07'.
512           textb07 = ls_textpool-entry.
513         WHEN 'B10'.
514           textb10 = ls_textpool-entry.
515         WHEN 'B12'.
516           textb12 = ls_textpool-entry.
517         WHEN 'B14'.
518           textb14 = ls_textpool-entry.
519         WHEN 'B15'.
520           textb15 = ls_textpool-entry.
521         WHEN 'B16'.
522           textb16 = ls_textpool-entry.
523         WHEN 'B18'.
524           textb18 = ls_textpool-entry.
525         WHEN 'B20'.
526           textb20 = ls_textpool-entry.
527         WHEN 'B25'.
528           textb25 = ls_textpool-entry.
529         WHEN '044'.                                                "n1974538
530           text044 = ls_textpool-entry.                             "n1974538
531         WHEN '045'.
532           text045 = ls_textpool-entry.
533         WHEN '046'.                                                "n2247001
534           text046 = ls_textpool-entry.                             "n2247001
535         WHEN '047'.                                                "n2436588
536           gd_dconv = ls_textpool-entry.                            "n2436588
537       ENDCASE.
```

```
538    ENDLOOP.
539
540    TRY.                                                          "n2316951
541        GET BADI go_badi_lib.                                     "n2316951
542      CATCH cx_badi_not_implemented.                              "n2316951
543    ENDTRY.                                                       "n2316951
544
545    GET PARAMETER ID 'PIVB_LAST_TAB' FIELD ld_pivb_last_tab.
546    IF ld_pivb_last_tab IS INITIAL.
547      ld_pivb_last_tab = 'TAB2'.
548      SET PARAMETER ID 'PIVB_LAST_TAB' FIELD ld_pivb_last_tab.
549    ENDIF.
550
551    perform sel_view_check_get using gd_sel_view
552                                changing ls_sel_view
553                                         gd_base_view.
554  * fallback for SL browser
555    if gd_base_view is initial.
556      gd_base_view = ls_sel_view-name.
557    endif.
558
559  * display extended download options
560    call function 'FAGL_GET_FAGL_SETTINGS'
561    exporting
562      id_param_name       = 'FAGL_LIB_EX_DWLN_OPT'
563    importing
564      ed_value            = ld_fagl_sett_value.
565    gv_ext_download_options = xsdbool( ld_fagl_sett_value is not initial )
    .
566
567  ENDFORM.                    " INITIALIZATION
568  *&---------------------------------------------------------------------*
569  *&      Form  LAYOUTS_CHECK
570  *&---------------------------------------------------------------------*
571  FORM layouts_check .                                  "new since "n2414462
572  *---------------------------------------------------------------------*
573    DATA ld_log_group               TYPE slis_loggr.
574    DATA ld_rldnr                   TYPE rldnr.
575    DATA lt_ltdx                    TYPE STANDARD TABLE OF ltdx.
576    DATA lt_ltdxd                   TYPE STANDARD TABLE OF ltdxd.
577    DATA lt_ltdxt                   TYPE STANDARD TABLE OF ltdxt.
578  *---------------------------------------------------------------------*
579    FIELD-SYMBOLS <ls_ltdx>         TYPE ltdx.
580    FIELD-SYMBOLS <ls_ltdxd>        TYPE ltdxd.
581    FIELD-SYMBOLS <ls_ltdxt>        TYPE ltdxt.
582  *---------------------------------------------------------------------*
583    CHECK sy-repid <> 'FAGL_LINE_ITEM_BROWSER_SL'.
584
585    SELECT SINGLE log_group
586      FROM ltdx
587      INTO ld_log_group
588      WHERE relid = 'LT'
589      AND   report = sy-repid
590      AND   log_group > space.
591
592    CHECK sy-subrc = 0.
593
594    CALL FUNCTION 'FAGL_GET_LEADING_LEDGER'
595      IMPORTING
596        e_rldnr   = ld_rldnr
597      EXCEPTIONS
```

```
598         not_found = 0.
599
600       SELECT *
601         FROM ltdx
602         INTO TABLE lt_ltdx
603         WHERE relid = 'LT'
604         AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'
605         AND   log_group > space.
606
607       LOOP AT lt_ltdx
608         ASSIGNING <ls_ltdx>.
609         CASE <ls_ltdx>-report.
610           WHEN 'FAGL_LINE_ITEM_BROWSER'.
611             IF ld_rldnr IS INITIAL.
612               ld_rldnr = <ls_ltdx>-log_group.
613             ENDIF.
614             IF <ls_ltdx>-log_group <> ld_rldnr.
615               DELETE lt_ltdx.
616               CONTINUE.
617             ENDIF.
618           WHEN 'FAGL_LINE_ITEM_BROWSER_SL'.
619             CONTINUE.
620         ENDCASE.
621         CLEAR <ls_ltdx>-log_group.
622       ENDLOOP.
623
624       DELETE FROM ltdx
625         WHERE relid  =    'LT'
626         AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'
627         AND   log_group > space.
628
629       INSERT ltdx
630         FROM TABLE lt_ltdx
631         ACCEPTING DUPLICATE KEYS.
632
633       FREE lt_ltdx.
634
635       SELECT *
636         FROM ltdxd                                          "#EC CI_GENBUFF
637         INTO TABLE lt_ltdxd
638         WHERE relid  =    'LT'
639         AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'.
640
641       LOOP AT lt_ltdxd
642         ASSIGNING <ls_ltdxd>.
643         CASE <ls_ltdxd>-report.
644           WHEN 'FAGL_LINE_ITEM_BROWSER'.
645             IF ld_rldnr IS INITIAL.
646               ld_rldnr = <ls_ltdxd>-log_group.
647             ENDIF.
648             IF <ls_ltdxd>-log_group <> ld_rldnr.
649               DELETE lt_ltdxd.
650               CONTINUE.
651             ENDIF.
652           WHEN 'FAGL_LINE_ITEM_BROWSER_SL'.
653             CONTINUE.
654         ENDCASE.
655         CLEAR <ls_ltdxd>-log_group.
656       ENDLOOP.
657
658       DELETE FROM ltdxd
```

```
659       WHERE relid  =    'LT'
660       AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'              "n3470124
661       AND   log_group > space.                                 "n3470124
662
663     INSERT ltdxd
664       FROM TABLE lt_ltdxd
665       ACCEPTING DUPLICATE KEYS.
666
667     SELECT *
668       FROM ltdxt                                           "#EC CI_GENBUFF
669       INTO TABLE lt_ltdxt
670       WHERE relid  =    'LT'
671       AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'.
672
673     LOOP AT lt_ltdxt
674       ASSIGNING <ls_ltdxt>.
675       CASE <ls_ltdxt>-report.
676         WHEN 'FAGL_LINE_ITEM_BROWSER'.
677           IF ld_rldnr IS INITIAL.
678             ld_rldnr = <ls_ltdxt>-log_group.
679           ENDIF.
680           IF <ls_ltdxt>-log_group <> ld_rldnr.
681             DELETE lt_ltdxt.
682             CONTINUE.
683           ENDIF.
684         WHEN 'FAGL_LINE_ITEM_BROWSER_SL'.
685           CONTINUE.
686       ENDCASE.
687       CLEAR <ls_ltdxt>-log_group.
688     ENDLOOP.
689
690     DELETE FROM ltdxt
691       WHERE relid  =    'LT'
692       AND   report LIKE 'FAGL_LINE_ITEM_BROWSER%'              "n3470124
693       AND   log_group > space.                                 "n3470124
694
695     INSERT ltdxt
696       FROM TABLE lt_ltdxt
697       ACCEPTING DUPLICATE KEYS.
698
699     CALL FUNCTION 'DB_COMMIT'.
700
701   ENDFORM.
```

```
*---------------------------------------------------------------------*
***INCLUDE FAGL_LINE_ITEM_BROWSER_F03 .
*---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  SELECTION_SCREEN_OUTPUT
*&---------------------------------------------------------------------*
FORM selection_screen_output .
*---------------------------------------------------------------------*
  CONSTANTS  lc_id            TYPE vrm_id
                              VALUE 'P_APPL'. "name of field on screen
*---------------------------------------------------------------------*
  STATICS sd_ledger_sel.
  STATICS sd_yearper_sel.
  STATICS sd_subapplication   TYPE fbcon_s_hdb-subappl.
  STATICS st_ledger_users     TYPE hdb_t_range.
  STATICS st_yearper_users    TYPE hdb_t_range.
  statics sd_init_on_return   type abap_bool.
*---------------------------------------------------------------------*
  DATA ld_free_sel_text       TYPE string.
  DATA ls_sel_view            TYPE rsdsqcat.

  DATA lt_value               TYPE vrm_values.
  DATA ls_value               TYPE vrm_value.
  DATA lt_hdb_range           TYPE hdb_t_range.
  DATA ls_hdb_range           TYPE hdb_s_range.

  DATA lt_presel              TYPE rsds_trange.
  DATA lsx_table_field_ranges TYPE rsds_range.
  DATA lsx_field_ranges       TYPE rsds_frange.

  data ld_display_only        type abap_bool.
*---------------------------------------------------------------------*
* >> Transaction code
  REFRESH s_acctp.                                          "n2200302
  s_acctp-sign   = 'I'.
  s_acctp-option = 'EQ'.
  CASE p_appl.
    WHEN gc_hdb_subappl-s_newgl-gl_view.
      gd_title = 'G/L Account Line Item Browser (G/L View)'(024).
      s_acctp-low = gc_s_acctp-gl_account.
    WHEN gc_hdb_subappl-s_newgl-entry_view.
      gd_title = 'G/L Account Line Item Browser (Entry View)'(026).
      s_acctp-low = gc_s_acctp-gl_account.
    WHEN gc_hdb_subappl-s_classic_gl-line_item_browser.
      gd_title = 'G/L Account Line Item Browser'(025).
      s_acctp-low = gc_s_acctp-gl_account.
    WHEN gc_hdb_subappl-s_receivables-line_item_browser.
      gd_title = 'Customer Line Item Browser'(029).
      s_acctp-low = gc_s_acctp-customer.
    WHEN gc_hdb_subappl-s_payables-line_item_browser.
      gd_title = 'Vendor Line Item Browser'(032).
      s_acctp-low = gc_s_acctp-vendor.
    WHEN gc_hdb_subappl-s_pca-line_item_browser.
      gd_title = sy-title.
      s_acctp-low = 'P'.
    WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
      gd_title = sy-title.
    WHEN OTHERS.
      gd_title = 'G/L Account Line Item Browser (Entry View)'(026).
      s_acctp-low = gc_s_acctp-gl_account.
      APPEND s_acctp.
```

```
62        s_acctp-low = gc_s_acctp-vendor.
63        APPEND s_acctp.
64        s_acctp-low = gc_s_acctp-customer.
65        APPEND s_acctp.
66        gd_sel_view = gc_s_hdb_ddic-entry_view.
67      ENDCASE.
68      APPEND s_acctp.
69      SET TITLEBAR '010' WITH gd_title.
70
71      IF  gd_subapplication <> fbcon_hdb_subappl-s_new_gl-line_item_browser
72      AND gd_subapplication <> fbcon_hdb_subappl-s_special_ledger-line_item_
    browser.
73        CLEAR sscrfields-functxt_02.                          "n2124059
74        CLEAR sscrfields-functxt_03.                          "n2124059
75      ENDIF.
76
77      IF sd_subapplication <> gd_subapplication.
78        sd_subapplication = gd_subapplication.
79    * Get settings for ledger input
80        CALL FUNCTION 'HDB_RANGE_READ'
81          EXPORTING
82            i_application    = gc_hdb_appl-financials
83            i_subapplication = gd_subapplication
84            i_range_type     = gc_hdb_range_type-sel_screen_ledger
85          IMPORTING
86            et_range         = lt_hdb_range.
87
88        CLEAR sd_ledger_sel.
89        LOOP AT lt_hdb_range
90          INTO ls_hdb_range.
91          sd_ledger_sel = ls_hdb_range-low.
92        ENDLOOP.
93
94        IF sd_ledger_sel = gc_s_hdb_ledger_sel-some_users.
95    * Get users for ledger input
96          CALL FUNCTION 'HDB_RANGE_READ'
97            EXPORTING
98              i_application    = gc_hdb_appl-financials
99              i_subapplication = gd_subapplication
100             i_range_type     = gc_hdb_range_type-sel_screen_ledger
101             i_key_value      = gc_hdb_range_type-user
102           IMPORTING
103             et_range         = st_ledger_users.
104       ENDIF.
105
106   * Get settings for year & period input
107       CALL FUNCTION 'HDB_RANGE_READ'
108         EXPORTING
109           i_application    = gc_hdb_appl-financials
110           i_subapplication = gd_subapplication
111           i_range_type     = gc_hdb_range_type-sel_screen_yrper
112         IMPORTING
113           et_range         = lt_hdb_range.
114
115       CLEAR sd_yearper_sel.
116       LOOP AT lt_hdb_range
117         INTO ls_hdb_range.
118         sd_yearper_sel = ls_hdb_range-low.
119       ENDLOOP.
120
121       IF sd_yearper_sel = gc_s_hdb_yearper_sel-some_users.
```

```
122  * Get users for year & period input
123        CALL FUNCTION 'HDB_RANGE_READ'
124          EXPORTING
125            i_application    = gc_hdb_appl-financials
126            i_subapplication = gd_subapplication
127            i_range_type     = gc_hdb_range_type-sel_screen_yrper
128            i_key_value      = gc_hdb_range_type-user
129          IMPORTING
130            et_range         = st_yearper_users.
131      ENDIF.
132    ENDIF.
133
134    IF ( p_wlbuk IS NOT INITIAL                          "begin of "n2767139
135      OR p_wlrac IS NOT INITIAL
136      OR p_wlcus IS NOT INITIAL
137      OR p_wlven IS NOT INITIAL ).
138      gd_consider_worklists = abap_true.
139      gd_worklist_active = abap_true.
140      gd_consider_sets      = abap_false.                    "n2869685
141      gd_sets_active        = abap_false.                    "n2869685
142  **  Deactivate Worklist
143      sscrfields-functxt_05 = gs_text_wl-deactivate.
144    ENDIF.                                                  "end of "n2767139
145
146    IF ( p_setbuk IS NOT INITIAL                         "begin of "n2869685
147      OR p_setrac IS NOT INITIAL
148      OR p_setcus IS NOT INITIAL
149      OR p_setven IS NOT INITIAL ).
150      gd_consider_worklists = abap_false.
151      gd_consider_sets      = abap_true.
152      gd_worklist_active    = abap_false.
153      gd_sets_active        = abap_true.
154  **  Deactivate Worklist
155      sscrfields-functxt_05 = gs_text_set-deactivate.
156    ENDIF.
157
158    IF gs_reset_selection IS NOT INITIAL                 "begin of "n2869685
159      AND ( gd_worklist_active = abap_true
160          OR gd_sets_active = abap_true ).
161
162      IF gs_reset_selection-ccode = abap_true.
163        s_ccode[] = s_ccnowl[].
164        s_ccode   = s_ccnowl.
165      ENDIF.
166
167      IF s_vend[] IS NOT INITIAL AND gs_reset_selection-vendor = abap_true
    .
168        s_vend[] = s_acnowl[].
169        s_vend   = s_acnowl.
170      ELSEIF s_cust[] IS NOT INITIAL AND gs_reset_selection-customer = aba
    p_true.
171        s_cust[] = s_acnowl[].
172        s_cust   = s_acnowl.
173      ELSEIF s_racct[] IS NOT INITIAL AND gs_reset_selection-racct = abap_
    true.
174        s_racct[] = s_acnowl[].
175        s_racct   = s_acnowl.
176      ENDIF.
177
178      CLEAR gs_reset_selection.
179      REFRESH: s_ccnowl[], s_acnowl[].
```

```
180       CLEAR:   s_ccnowl, s_acnowl.
181     ELSE.
182       IF p_wlbuk IS NOT INITIAL OR p_setbuk IS NOT INITIAL.
183         REFRESH: s_ccode.
184       ENDIF.
185       IF p_wlrac IS NOT INITIAL OR p_setrac IS NOT INITIAL.
186         REFRESH: s_racct.
187       ENDIF.
188       IF p_wlven IS NOT INITIAL OR p_setven IS NOT INITIAL.
189         REFRESH: s_vend.
190       ENDIF.
191       IF p_wlcus IS NOT INITIAL OR p_setcus IS NOT INITIAL.
192         REFRESH: s_cust.
193       ENDIF.
194     ENDIF.                                              "end of "n2869685
195
196     IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_brows
    er.
197       sd_ledger_sel = gc_s_hdb_ledger_sel-dialog.
198     ENDIF.
199
200   * Disable KESS dynamic selection screen if desired  "begin of "n2636622
201     IF gd_disable_kess = abap_true.
202       CALL METHOD gr_screen->deselect_all_fields.
203     ENDIF.                                              "end of "n2636622
204
205     LOOP AT SCREEN.
206       CASE screen-group1.
207         WHEN 'RLD'.
208           if ge_appl_view = fi_entry.
209             screen-input     = 0.
210             screen-active    = 0.
211             screen-invisible = 1.
212           elseif sd_ledger_sel = gc_s_hdb_ledger_sel-dialog
213             or ( sd_ledger_sel = gc_s_hdb_ledger_sel-some_users and not sy
    -uname in st_ledger_users ).
214               screen-input = 0.
215           endif.
216         WHEN 'GLA'.
217           IF NOT gc_s_acctp-gl_account IN s_acctp.
218             screen-input     = 0.
219             screen-active    = 0.
220             screen-invisible = 1.
221           ENDIF.
222         WHEN 'GPC'.                                     "303117
223           CALL FUNCTION 'FAGL_GET_FAGL_SETTINGS'        "303117
224             EXPORTING                                   "303117
225               id_param_name = 'LIB_PRCTR_GRP_SELECT'    "303117
226             IMPORTING                                   "303117
227               ed_value      = gv_lib_prctr_grp_select."303117
228           IF NOT gc_s_acctp-gl_account IN s_acctp       "303117
229             OR gv_lib_prctr_grp_select = abap_false.    "303117
230             screen-input     = 0.                       "303117
231             screen-active    = 0.                       "303117
232             screen-invisible = 1.                       "303117
233           ENDIF.                                        "303117
234         WHEN 'ARA'.
235           IF NOT gc_s_acctp-customer IN s_acctp.
236             screen-input     = 0.
237             screen-active    = 0.
238             screen-invisible = 1.
```

```
239           ENDIF.
240         WHEN 'APA'.
241           IF NOT gc_s_acctp-vendor IN s_acctp.
242             screen-input     = 0.
243             screen-active    = 0.
244             screen-invisible = 1.
245           ENDIF.
246         WHEN 'WLB'.                                          "begin of "n2767139
247           IF gd_worklist_active = abap_true.
248             screen-input     = 1.
249             screen-active    = 1.
250             screen-invisible = 0.
251           ELSE.
252             screen-input     = 0.
253             screen-active    = 0.
254             screen-invisible = 1.
255           ENDIF.
256         WHEN 'WLG'.
257           IF NOT gc_s_acctp-gl_account IN s_acctp.
258             screen-input     = 0.
259             screen-active    = 0.
260             screen-invisible = 1.
261           ELSE.
262             IF gd_worklist_active = abap_true.
263               screen-input     = 1.
264               screen-active    = 1.
265               screen-invisible = 0.
266             ELSE.
267               screen-input     = 0.
268               screen-active    = 0.
269               screen-invisible = 1.
270             ENDIF.
271           ENDIF.
272         WHEN 'WLR'.
273           IF NOT gc_s_acctp-customer IN s_acctp.
274             screen-input     = 0.
275             screen-active    = 0.
276             screen-invisible = 1.
277           ELSE.
278             IF gd_worklist_active = abap_true.
279               screen-input     = 1.
280               screen-active    = 1.
281               screen-invisible = 0.
282             ELSE.
283               screen-input     = 0.
284               screen-active    = 0.
285               screen-invisible = 1.
286             ENDIF.
287           ENDIF.
288         WHEN 'WLP'.
289           IF NOT gc_s_acctp-vendor IN s_acctp.
290             screen-input     = 0.
291             screen-active    = 0.
292             screen-invisible = 1.
293           ELSE.
294             IF gd_worklist_active = abap_true.
295               screen-input     = 1.
296               screen-active    = 1.
297               screen-invisible = 0.
298             ELSE.
299               screen-input     = 0.
```

```
300             screen-active    = 0.
301             screen-invisible = 1.
302           ENDIF.
303         ENDIF.                                          "end of "n2767139
304       WHEN 'STB'.                                       "begin of "n2869685
305         IF gd_sets_active = abap_true.
306           screen-input     = 1.
307           screen-active    = 1.
308           screen-invisible = 0.
309         ELSE.
310           screen-input     = 0.
311           screen-active    = 0.
312           screen-invisible = 1.
313         ENDIF.
314       WHEN 'STG'.
315         IF NOT gc_s_acctp-gl_account IN s_acctp.
316           screen-input     = 0.
317           screen-active    = 0.
318           screen-invisible = 1.
319         ELSE.
320           IF gd_sets_active = abap_true.
321             screen-input     = 1.
322             screen-active    = 1.
323             screen-invisible = 0.
324           ELSE.
325             screen-input     = 0.
326             screen-active    = 0.
327             screen-invisible = 1.
328           ENDIF.
329         ENDIF.
330       WHEN 'STR'.
331         IF NOT gc_s_acctp-customer IN s_acctp.
332           screen-input     = 0.
333           screen-active    = 0.
334           screen-invisible = 1.
335         ELSE.
336           IF gd_sets_active = abap_true.
337             screen-input     = 1.
338             screen-active    = 1.
339             screen-invisible = 0.
340           ELSE.
341             screen-input     = 0.
342             screen-active    = 0.
343             screen-invisible = 1.
344           ENDIF.
345         ENDIF.
346       WHEN 'STP'.
347         IF NOT gc_s_acctp-vendor IN s_acctp.
348           screen-input     = 0.
349           screen-active    = 0.
350           screen-invisible = 1.
351         ELSE.
352           IF gd_sets_active = abap_true.
353             screen-input     = 1.
354             screen-active    = 1.
355             screen-invisible = 0.
356           ELSE.
357             screen-input     = 0.
358             screen-active    = 0.
359             screen-invisible = 1.
360           ENDIF.
```

```
361           ENDIF.                                                "end of "n2869685
362         WHEN 'ATP'.
363           screen-input     = 0.
364           screen-active    = 0.
365           screen-invisible = 1.
366         WHEN 'APP'.
367           IF gd_hide_appl = abap_true.
368             screen-input     = 0.
369             screen-active    = 0.
370             screen-invisible = 1.
371           ENDIF.
372         WHEN 'DWN'.
373           IF p_outfi = abap_true.
374             screen-input = 1.
375           ELSE.
376             screen-input = 0.
377           ENDIF.
378         WHEN 'XSP'.
379           IF  gd_subapplication <> gc_hdb_subappl-s_receivables-line_item_
    browser
380           AND gd_subapplication <> gc_hdb_subappl-s_payables-line_item_bro
    wser.
381             screen-input     = 0.
382             screen-active    = 0.
383             screen-invisible = 1.
384           ENDIF.
385         WHEN 'GLY'.                                    "begin "n2494719
386           IF gd_subapplication <> gc_hdb_subappl-s_newgl-line_item_browser
387           OR p_appl            =  gc_hdb_subappl-s_newgl-entry_view
388           OR cl_fagl_switch_check=>fagl_fin_gl_cp_rs( ) IS INITIAL.
389             screen-input     = 0.
390             screen-active    = 0.
391             screen-invisible = 1.
392           ENDIF.                                           "end "n2494719
393         WHEN 'EXT'.                                "begin of "n2816760
394           IF gd_subapplication = gc_hdb_subappl-s_newgl-line_item_browser
395             AND gd_modif_2818431 = abap_true.
396             SELECT SINGLE COUNT( * ) FROM finsc_ledger
397               WHERE rldnr = p_ledger AND ledger_type = 'A'.
398             IF sy-subrc <> 0.
399               screen-input     = 0.
400               screen-active    = 0.
401               screen-invisible = 1.
402             ENDIF.
403           ELSE.
404             screen-input     = 0.
405             screen-active    = 0.
406             screen-invisible = 1.
407           ENDIF.                                  "end of "n2816760
408         when 'DWE'.
409           if gv_ext_download_options = abap_true and not screen-name cs 'P
    _DMCMP'.
410             IF p_outfi = abap_false or p_dmraw = abap_false and screen-nam
    e cs 'P_DWHDR'.
411               screen-input = 0.
412             ELSE.
413               screen-input = 1.
414             ENDIF.
415             screen-active    = 1.
416             screen-invisible = 0.
417           else.
```

```
418           IF p_outfi = abap_true.
419             screen-input = 1.
420           ELSE.
421             screen-input = 0.
422           ENDIF.
423           screen-active    = 0.
424           screen-invisible = 1.
425         endif.
426       WHEN OTHERS.
427         CASE screen-group1.
428           WHEN 'XAI'.
429             CASE p_appl.
430               WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
431                 IF screen-name CS 'GD_YPCMT'.
432                   screen-input     = 0.
433                   screen-active    = 0.
434                   screen-invisible = 1.
435                 ENDIF.
436               WHEN OTHERS.
437                 IF screen-name CS 'S_RYEAR'
438           OR screen-name CS 'S_PERIOD'
439           OR screen-name CS 'GD_YPCMT'.
440             IF sd_yearper_sel = gc_s_hdb_yearper_sel-nobody
441             OR sd_yearper_sel = gc_s_hdb_yearper_sel-some_users
442                AND NOT sy-uname IN st_yearper_users.
443               screen-input     = 0.
444               screen-active    = 0.
445               screen-invisible = 1.
446             ENDIF.
447           ENDIF.
448             ENDCASE.
449           WHEN 'XOM'.
450             CASE p_appl.
451               WHEN gc_hdb_subappl-s_newgl-gl_view
452                 OR gc_hdb_subappl-s_newgl-entry_view
453                 OR gc_hdb_subappl-s_classic_gl-line_item_browser.
454               WHEN OTHERS.
455                 screen-input     = 0.
456                 screen-active    = 0.
457                 screen-invisible = 1.
458             ENDCASE.
459         ENDCASE.
460         CASE screen-group3.
461           WHEN 'PAR'
462             OR 'LOW'
463             OR 'HGH'.
464             CASE screen-group1.
465 * Open Items: Key Date
466               WHEN 'XOI'
467                 OR 'XOM'.
468                 IF p_oi IS INITIAL.
469                   screen-input = 0.
470                 ELSE.
471                   screen-input = 1.
472                 ENDIF.
473 * Cleared Items: Clearing / Key Date
474               WHEN 'XCL'.
475                 IF p_ci IS INITIAL.
476                   screen-input = 0.
477                 ELSE.
478                   screen-input = 1.
```

```
479                 ENDIF.
480   * All Items: Year, Period, Posting Date
481                 WHEN 'XAI'.
482                   IF screen-invisible = 0.
483                     IF p_ai IS INITIAL.
484                       screen-input = 0.
485                     ELSE.
486                       screen-input = 1.
487                     ENDIF.
488                   ENDIF.
489               ENDCASE.
490           ENDCASE.
491           CASE p_appl.                                          "n2275931
492             WHEN gc_hdb_subappl-s_newgl-gl_view.                "n2275931
493               IF screen-name CS 'P_TY_'.                        "n2275931
494                 screen-input     = 0.                           "n2275931
495                 screen-active    = 0.                           "n2275931
496                 screen-invisible = 1.                           "n2275931
497               ENDIF.                                            "n2275931
498           ENDCASE.                                              "n2275931
499
500       ENDCASE.
501       MODIFY SCREEN.
502     ENDLOOP.
503
504   * check authority groups and add to additonal restrictions
505     perform auth_groups.
506
507   * 3315130: project items->kess if psx_item is filled but psx_kess is emp
      ty.
508   *          e.g. loading an old variant which has only psx_item.
509   *          but not when only kess is filled.
510   *          e.g. loading a variant with only kess saved
511   *  if sd_init_on_return = abap_false.
512     if value #( psx_item-trange[ 1 ]-frange_t optional ) is not initial
513       and ss_gr_int->variant_name is not initial.               "n3340374
514       perform sync_items_to_selection_screen.
515     endif.
516   *    sd_init_on_return = abap_true.
517   *  endif.
518
519     perform sync_kess_to_items.
520
521     perform sync_selections_to_badi using if_fagl_lib=>event_id-sel_screen
      _output
522                                     changing ld_display_only.
523
524     perform sync_items_to_selection_screen.
525
526   * Set text for dynamic selections
527     CALL METHOD cl_fagl_freesel_selscreen=>selections_analyze
528       CHANGING
529         csx_01_sel = psx_item
530         cd_01_sel  = ld_free_sel_text.
531     item_sel = ld_free_sel_text.
532
533   * list of values
534     ls_value-text = text-024.
535     ls_value-key  = gc_hdb_subappl-s_newgl-gl_view.
536     APPEND ls_value TO lt_value.
537
```

```
538    ls_value-text = text-026.
539    ls_value-key  = gc_hdb_subappl-s_newgl-entry_view.
540    APPEND ls_value TO lt_value.
541
542    ls_value-text = text-025.
543    ls_value-key  = gc_hdb_subappl-classic_gl.
544    APPEND ls_value TO lt_value.
545
546    ls_value-text = text-029.
547    ls_value-key  = gc_hdb_subappl-s_receivables-line_item_browser.
548    APPEND ls_value TO lt_value.
549
550    ls_value-text = text-032.
551    ls_value-key  = gc_hdb_subappl-s_payables-line_item_browser.
552    APPEND ls_value TO lt_value.
553
554    CALL FUNCTION 'VRM_SET_VALUES'
555      EXPORTING
556        id     = lc_id
557        values = lt_value.
558
559  ENDFORM.                    " SELECTION_SCREEN_OUTPUT
560  *&---------------------------------------------------------------------*
561  *&      Form  AUTH_GROUPS
562  *&---------------------------------------------------------------------*
563  form auth_groups.
564    data auth_objects type standard table of xuobject.
565    data auth_tables type standard table of tabname.
566
567  * setup psx_item if not done yet
568    if psx_item-trange is initial.
569      append value #( tablename = gd_base_view ) to psx_item-trange.
570    endif.
571
572  * setup call
573    case p_appl.
574        when gc_hdb_subappl-s_payables-line_item_browser.
575          auth_objects = value #( ( 'F_LFA1_BEK' ) ).
576          auth_tables  = value #( ( 'LFA1' ) ( 'LFB1' ) ).
577        when gc_hdb_subappl-s_receivables-line_item_browser.
578          auth_objects = value #( ( 'F_KNA1_BED' ) ).
579          auth_tables  = value #( ( 'KNA1' ) ( 'KNB1' ) ).
580        when gc_hdb_subappl-s_pca-line_item_browser.                    "N
    3368898
581          auth_objects = value #( ( 'K_PCA' ) ).                        "N
    3368898
582        when others.
583          auth_objects = value #( ( 'F_BKPF_BES' ) ( 'F_SKA1_BES' ) ). "33
    75777 sequence of objects defines hierarchy
584          auth_tables  = value #( ( 'SKB1' ) ).
585    endcase.
586
587    cl_fagl_lib_authority=>get_instance( )->set_environment(
588      objects  = auth_objects
589      field    = value #( auth = 'BRGRU' field = 'BEGRU' )
590    ).
591
592    cl_fagl_lib_authority=>get_instance( )->project_to_selection( exportin
    g tables = auth_tables
593                                                                  changing
     selection = psx_item-trange ).
```

```
594
595  endform.
596
597  form sync_selections_to_badi using event_id
598                                changing display_only.
599
600    statics badi_is_initialized type abap_bool.
601
602    check go_badi_lib is not initial.
603
604  * first call goes to initialization
605    data(badi_event) = cond #( when badi_is_initialized = abap_false then
     if_fagl_lib=>event_id-initialization
606                                                                    else
      event_id ).
607
608    call badi go_badi_lib->create_default_restrictions
609            exporting
610              id_sel_view = gd_sel_view
611              event_id    = badi_event
612            changing
613              ct_table_range  = psx_item-trange
614              cd_display_only = display_only.
615
616    badi_is_initialized = abap_true.
617  endform.
618
619  form sync_kess_to_items.
620    data fld_on_kess             type sap_bool.
621
622    field-symbols <range_kess>  type rsds_range.
623    field-symbols <range_item>  type rsds_range.
624    field-symbols <frange_kess> type rsds_frange.
625    field-symbols <frange_item> type rsds_frange.
626
627    check gd_disable_kess <> abap_true.
628
629    perform sync_selection_screen_to_kess.
630
631    read table psx_kess-trange assigning <range_kess> index 1.
632    read table psx_item-trange assigning <range_item> index 1.
633
634    if <range_item> is not assigned.
635      append value #( tablename = gd_base_view ) to psx_item-trange assign
     ing <range_item>.
636    endif.
637
638    check <range_kess> is assigned and <range_item> is assigned.
639
640  * clear empty selections in psx_item
641    loop at <range_item>-frange_t assigning <frange_item>.
642      perform sync_check_fld_on_kess using <frange_item>-fieldname changin
     g fld_on_kess.
643
644      check fld_on_kess = abap_true and not line_exists( <range_kess>-fran
     ge_t[ fieldname = <frange_item>-fieldname ] ).
645
646      delete <range_item>-frange_t
647          where fieldname = <frange_item>-fieldname.
648    endloop.
649
```

```
650 * move populated selection to psx_item
651   loop at <range_kess>-frange_t assigning <frange_kess>.
652     read table <range_item>-frange_t
653     with key fieldname = <frange_kess>-fieldname
654     assigning <frange_item>.
655
656     if sy-subrc = 0.
657       <frange_item>-selopt_t = <frange_kess>-selopt_t.
658     else.
659       append <frange_kess> to <range_item>-frange_t.
660     endif.
661
662     clear <frange_kess>-selopt_t.
663   endloop.
664 endform.
665
666 form sync_check_fld_on_kess using fieldname
667                             changing fld_on_kess type abap_bool.
668   clear fld_on_kess.
669
670   field-symbols <par_fld> type any.
671
672 * Reset result from previous field
673   clear fld_on_kess.                                          "n3197820
674
675 *  data(conv_to_kess_name) = conv rsscr_dbfi( gd_sel_view && '-' && fiel
    dname ). "N3518816
676
677   do 3 times.
678     data(par_key_char) = switch #( sy-index when 1 then 'C'
679                                             when 2 then 'U'
680                                             else 'V' ).
681     do 25 times.
682       data(par_key) = par_key_char && conv num2( sy-index ).
683       data(par_name) = |PAR_{ par_key }|.
684       assign (par_name) to <par_fld>.
685
686       if sy-subrc <> 0 or <par_fld> is initial.
687         continue. " <- in rare cases KESS PAR_xyz are not in sequence
688       else.
689         split <par_fld> at '-' INTO data(kess_sel) data(kess_fld). "N351
    8816
690         check kess_fld = fieldname.                               "N351
    8816
691         fld_on_kess = abap_true.
692         return.
693       endif.
694     enddo.
695   enddo.
696 endform.
697
698 form sync_items_to_selection_screen.
699   field-symbols <so_tab> type standard table.
700   field-symbols <so_header> type any.
701   field-symbols <par_fld> type any.
702
703   check gd_disable_kess <> abap_true.
704
705   read table psx_item-trange index 1 assigning field-symbol(<trange>).
706
707   check sy-subrc = 0.
```

```
708
709     do 3 times.
710       data(par_key_char) = switch #( sy-index when 1 then 'C'
711                                                when 2 then 'U'
712                                                else 'V' ).
713       do 25 times.
714         data(par_key) = par_key_char && conv num2( sy-index ).
715         data(par_name) = |PAR_{ par_key }|.
716         assign (par_name) to <par_fld>.
717
718         if sy-subrc <> 0 or <par_fld> is initial.
719           continue. " <- in rare cases KESS PAR_xyz are not in sequence
720         endif.
721
722         data(so_key_header) = |SO_{ par_key }|.
723         assign (so_key_header) to <so_header>.
724
725         check sy-subrc = 0.
726
727         data(so_key_tab) = |SO_{ par_key }[]|.
728         assign (so_key_tab) to <so_tab>.
729
730         check sy-subrc = 0.
731
732         split <par_fld> at '-' into table data(par_fld_name).
733
734         clear <so_header>.
735         clear <so_tab>.
736
737         read table <trange>-frange_t
738           with key fieldname = par_fld_name[ 2 ]
739           assigning field-symbol(<frange_t>).
740
741         check sy-subrc = 0.
742
743         loop at <frange_t>-selopt_t assigning field-symbol(<selopt>).
744           if sy-tabix = 1.
745             <so_header> = corresponding #( <selopt> ).
746           endif.
747           append corresponding rsdsselopt( <selopt> ) to <so_tab>.
748         endloop.
749       enddo.
750     enddo.
751   endform.
752
753   form sync_selection_screen_to_kess.
754     data par_selopt type rsdsselopt_t.
755
756     field-symbols <so_tab> type standard table.
757     field-symbols <so_header> type any.
758     field-symbols <par_fld> type any.
759
760     check gd_disable_kess <> abap_true.
761
762     clear psx_kess.
763
764     append value #( tablename = gd_sel_view ) to psx_kess-trange assigning
      field-symbol(<trange>).
765
766     do 3 times.
767       data(par_key_char) = switch #( sy-index when 1 then 'C'
```

```
768                                                 when 2 then 'U'
769                                                 else 'V' ).
770       do 25 times.
771         data(par_key) = par_key_char && conv num2( sy-index ).
772         data(par_name) = |PAR_{ par_key }|.
773         assign (par_name) to <par_fld>.
774
775         check sy-subrc = 0.
776
777         if <par_fld> is initial.
778           continue. " <- in rare cases KESS PAR_xyz are not in sequence
779         endif.
780
781   *       data(so_key_header) = |SO_{ par_key }|.    "begin "n3197820
782   *       assign (so_key_header) to <so_header>.
783   *
784   *       check sy-subrc = 0 and <so_header> is not initial.
785
786         data(so_key_tab) = |SO_{ par_key }[]|.
787         assign (so_key_tab) to <so_tab>.
788
789         check sy-subrc = 0 and <so_tab> is not initial. "end "n3197820
790
791         split <par_fld> at '-' into table data(par_fld_name).
792
793         clear par_selopt.
794         loop at <so_tab> assigning field-symbol(<so>).
795           append corresponding #( <so> ) to par_selopt.
796         endloop.
797
798         append value rsds_frange( fieldname = par_fld_name[ 2 ]
799                                   selopt_t  = par_selopt ) to <trange>-fra
    nge_t.
800       enddo.
801     enddo.
802   endform.
```

```
*---------------------------------------------------------------------*
***INCLUDE FAGL_LINE_ITEM_BROWSER_F04 .
*---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  SELECTION_SCREEN
*&---------------------------------------------------------------------*
FORM selection_screen .
*---------------------------------------------------------------------*
  DATA ld_field               TYPE fieldname.
  DATA ld_repid               TYPE syrepid.
  DATA ls_range               TYPE rsds_range.              "n2871375
  DATA ls_frange              TYPE rsds_frange.             "n2871375
  DATA lt_default_restr       TYPE rsds_trange.             "n2871375
  DATA ld_display_only        TYPE boole_d.                 "n2871375
*---------------------------------------------------------------------*
  PERFORM rri_init.                                         "n1920358

  gd_subapplication = p_appl.
  IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
  OR gd_subapplication = gc_hdb_subappl-s_newgl-entry_view.
    gd_subapplication = fbcon_hdb_subappl-s_new_gl-line_item_browser.
  ENDIF.
  CASE sscrfields-ucomm.
    WHEN 'FC02'.
      CASE p_appl.
        WHEN gc_hdb_subappl-s_newgl-gl_view.
          ld_repid = 'FAGL_LINE_ITEM_BROWSER_EV'.
        WHEN gc_hdb_subappl-s_newgl-entry_view.
          ld_repid = 'FAGL_LINE_ITEM_BROWSER'.
      ENDCASE.
      PERFORM submit_restart
        USING
          ld_repid.
    WHEN 'FC03'.
      PERFORM ledger_value_request.
    WHEN 'FC04'.
      PERFORM call_hdbc_restricted
        USING
          gd_subapplication
          gd_hdb_is_primary.
      gd_reload_sview = abap_true.
    WHEN 'FC05'.                                  "begin of "n2767139
      IF gd_consider_worklists = abap_true.
        IF gd_worklist_active = abap_false
          OR gd_worklist_active = abap_undefined.
          gd_worklist_active = abap_true.
          "Deactivate Worklist
          sscrfields-functxt_05 = gs_text_wl-deactivate.
        ELSE.
          gd_worklist_active = abap_false.
          "Activate Worklist
          sscrfields-functxt_05 = gs_text_wl-activate.
          CLEAR: p_wlcus, p_wlven, p_wlrac, p_wlbuk.
        ENDIF.
      ENDIF.                                        "end of "n2767139
      IF gd_consider_sets = abap_true.              "begin of "n2869685
        IF ( gd_sets_active = abap_false
          OR gd_sets_active = abap_undefined ).
          gd_sets_active = abap_true.
          "Deactivate Sets
          sscrfields-functxt_05 = gs_text_set-deactivate.
```

```
62          ELSE.
63            gd_sets_active = abap_false.
64            "Activate Worklist
65            sscrfields-functxt_05 = gs_text_set-activate.
66            CLEAR: p_setcus, p_setven, p_setrac, p_setbuk.
67          ENDIF.
68        ENDIF.                                              "end of "n2869685
69      WHEN 'ITEM_SEL'.
70        CHECK sy-dynnr = '1000'.
71
72  *     begin of note 3140727
73  *       Before we call the BAdI or free selections,
74  *       get all selections into psx_item
75        perform sync_kess_to_items.
76
77  *     first call -> SEL_SCREEN_FREE_PRIOR
78        perform sync_selections_to_badi using if_fagl_lib=>event_id-sel_sc
    reen_free_prior
79                                        changing ld_display_only.
80
81  *     now, call free selections dialog
82        perform free_selections
83          using
84            ld_display_only
85          changing
86            psx_item
87            gd_free_sel_number
88            gd_item_sel_number.
89
90  *     second call -> SEL_SCREEN_FREE_PRIOR
91        perform sync_selections_to_badi using if_fagl_lib=>event_id-sel_sc
    reen_free_post
92                                        changing ld_display_only.
93
94  *     sync to screen
95        perform sync_items_to_selection_screen.
96
97  * end of note 3140727
98
99      WHEN 'ONLI'
100       OR 'PRIN'
101       OR 'SJOB'
102       OR 'UCOM1020'.
103
104 *   begin of note 3140727
105       perform sync_kess_to_items.
106
107       perform sync_selections_to_badi using if_fagl_lib=>event_id-sel_sc
    reen_process
108                                       changing ld_display_only.
109
110       perform sync_items_to_selection_screen.
111 *   end of note 3140727
112
113       PERFORM check_before_start
114         USING
115           psx_item
116           psx_kess                                          "n2571532
117           gd_subapplication
118           gd_hdb_is_primary
119         CHANGING
```

```
120             gd_sel_view
121             gd_dbcon_name
122             gd_exit.
123         CHECK gd_exit = abap_false.
124       WHEN 'APPL_CHANGE'.
125         CLEAR s_acctp[].
126       WHEN 'OPTI'.
127         GET CURSOR FIELD ld_field.
128         IF ld_field = 'GD_YPCMT'.
129           MESSAGE i001(fagl_reporting_en).
130         ENDIF.
131
132 *   begin of note 3140727
133       WHEN OTHERS.
134
135 *       Before we call the BAdI,
136 *       get all selections into psx_item
137         perform sync_kess_to_items.
138
139         perform sync_selections_to_badi using if_fagl_lib=>event_id-sel_sc
    reen
140                                           changing ld_display_only.
141
142 *       sync to screen
143         perform sync_items_to_selection_screen.
144
145 *   end of note 3140727
146     ENDCASE.
147     gd_create_file = p_outfi.
148
149   ENDFORM.                    " SELECTION_SCREEN
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F05 .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  DBCON_GET
6  *&---------------------------------------------------------------------*
7  FORM dbcon_get
8    USING
9      isx_item                TYPE rsds_type
10     isx_kess                TYPE rsds_type                  "n2571532
11     id_subapplication       TYPE fbcon_s_hdb-subappl
12     id_hdb_is_primary       TYPE boole_d
13   CHANGING
14     cd_sel_view             TYPE tabname
15     cd_dbcon_name           TYPE dbcon_name
16     cd_exit                 TYPE boole_d.
17 *---------------------------------------------------------------------*
18   DATA lt_table_list        TYPE fagl_strucnames.
19   DATA lsx_range            TYPE rsds_range.
20   DATA lsx_frange           TYPE rsds_frange.
21   DATA ls_selopt            TYPE rsdsselopt.
22   DATA lt_ledgers           TYPE fagl_rldnr_tab.
23   DATA ld_fagll03_ev_mode.                                  "n2171228
24 *---------------------------------------------------------------------*
25   FIELD-SYMBOLS <lt_ra_prctr> TYPE rsdsselopt_t.            "n2297003
26   FIELD-SYMBOLS <ls_ra_prctr> TYPE rsdsselopt.              "n2297003
27   FIELD-SYMBOLS <lsx_trange>  TYPE rsds_range.
28   FIELD-SYMBOLS <lsx_frange>  TYPE rsds_frange.
29 *---------------------------------------------------------------------*
30
31   CASE id_subapplication.
32     WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
33       APPEND cd_sel_view
34         TO lt_table_list.
35     WHEN OTHERS.
36       CASE cd_sel_view.
37         WHEN gc_s_hdb_ddic-gl_view                          "n2231737
38           OR gc_s_hdb_ddic-gl_view_ext.                     "n2231737
39           APPEND p_ledger
40             TO lt_ledgers.
41
42           CALL FUNCTION 'FAGL_HDB_CUST_BRW_TABLES_GET'
43             EXPORTING
44               id_appl                 = gc_hdb_appl-financials
45               id_subappl              = id_subapplication
46               id_include_other_objects = abap_true
47               it_ledgers              = lt_ledgers
48             IMPORTING
49               et_table_list           = lt_table_list.
50         WHEN OTHERS.
51           CALL FUNCTION 'FAGL_HDB_CUST_BRW_TABLES_GET'
52             EXPORTING
53               id_appl                 = gc_hdb_appl-financials
54               id_subappl              = id_subapplication
55               id_entry_view           = abap_true
56               id_include_other_objects = abap_true
57             IMPORTING
58               et_table_list           = lt_table_list.
59       ENDCASE.
60   ENDCASE.
61
```

```
  62    CALL FUNCTION 'FAGL_DBCON_GET_APPL'
  63      EXPORTING
  64        i_application     = gc_hdb_appl-financials
  65        i_subapplication  = id_subapplication
  66        it_required_table = lt_table_list
  67      IMPORTING
  68        e_dbcon_name      = cd_dbcon_name
  69      EXCEPTIONS
  70        OTHERS            = 1.
  71
  72    IF sy-subrc      <> 0
  73    OR (     cd_dbcon_name IS INITIAL
  74         AND id_hdb_is_primary =  abap_false ).
  75      MESSAGE ID sy-msgid TYPE 'E' NUMBER sy-msgno
  76        WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
  77      cd_exit = abap_true.
  78      EXIT.
  79    ENDIF.
  80
  81    IF sy-repid = 'FAGL_LINE_ITEM_BROWSER_EV'.                "n2171228
  82      ld_fagll03_ev_mode = abap_true.                         "n2171228
  83    ENDIF.                                                    "n2171228
  84
  85  * read selections from screen
  86    lsx_range-frange_t = value #(
  87      ( fieldname = 'RBUKRS' selopt_t = corresponding #( s_ccode[]  ) )
      "n3367337
  88      ( fieldname = 'RACCT'  selopt_t = corresponding #( s_racct[]  ) )
      "n3367337
  89      ( fieldname = 'KUNNR'  selopt_t = corresponding #( s_cust[]   ) )
      "n3367337
  90      ( fieldname = 'LIFNR'  selopt_t = corresponding #( s_vend[]   ) )
      "n3367337
  91      ( fieldname = 'RLDNR'  selopt_t = value #( sign = 'I' option = 'EQ'
     ( low = cond #( when p_ledger is initial then '00' else p_ledger ) ) ) )
  92      ( fieldname = 'KOKRS'  selopt_t = corresponding #( s_coarea[] ) )
      "n3367337
  93      ( fieldname = 'PRCTR'  selopt_t = corresponding #( s_rprctr[] ) )
      "n3367337
  94      ( fieldname = 'PRCTR'  selopt_t = corresponding #( gt_ra_prctr ) ) )
     . "n3367337
  95
  96  * read additional restrictions
  97    loop at isx_item-trange assigning <lsx_trange>.
  98      append lines of <lsx_trange>-frange_t to lsx_range-frange_t.
  99    endloop.
 100
 101    loop at isx_kess-trange assigning <lsx_trange>.
 102      append lines of <lsx_trange>-frange_t to lsx_range-frange_t.
 103    endloop.
 104
 105  * merge all ranges
 106    lsx_range-frange_t = go_util->summarize_frange_t( lsx_range-frange_t )
     .
 107
 108  * Note 3374823 BEG
 109    IF s_acctp-low = 'P'.
 110      LOOP AT lsx_range-frange_t ASSIGNING <lsx_frange> WHERE fieldname =
     'PRCTR'.
 111        <lsx_frange>-fieldname = 'RPRCTR'.
 112      ENDLOOP.
```

```
113     ENDIF.
114   * Note 3374823 END
115
116     CALL FUNCTION 'FAGL_CHECK_REP_AUTH_SEL_SCREEN'
117       EXPORTING
118         it_selections      = lsx_range-frange_t
119         id_koart           = s_acctp-low
120         id_totals_or_items = 'I'
121         id_fagll03_ev_mode = ld_fagll03_ev_mode              "n2171228
122       EXCEPTIONS
123         no_authority       = 1
124         wrong_call         = 2
125         OTHERS             = 3.
126
127     IF sy-subrc <> 0.
128       MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
129               WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
130       cd_exit = abap_true.
131       EXIT.
132     ENDIF.
133
134   ENDFORM.                    " DBCON_GET
```

```
*---------------------------------------------------------------------*
***INCLUDE FAGL_LINE_ITEM_BROWSER_F06 .
*---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  fill_fieldlist
*&---------------------------------------------------------------------*
*...fill gt_fieldlist with fields, which have to be ignored by.........*
*...function modul G_TABLE_SELECT_WITH_CURSOR during aggregation.......*
*---------------------------------------------------------------------*
FORM fill_fieldlist
  USING
    id_ledger                 TYPE rldnr
    id_sel_view               TYPE tabname
    id_use_variant            TYPE boole_d
    id_subapplication         TYPE hdb_subapplication
  CHANGING
    ct_fieldlist              TYPE tt_fields
    ct_fieldsel               TYPE tt_fields
    ct_group                  TYPE tt_fields
    ct_fieldcat               TYPE lvc_t_fcat
    ct_filter                 TYPE lvc_t_filt
    ct_sort                   TYPE lvc_t_sort
    ct_special_groups         TYPE lvc_t_sgrp
    cd_variant                TYPE slis_vari.
*---------------------------------------------------------------------*
  STATICS sth_flist           TYPE HASHED TABLE OF string
                              WITH UNIQUE DEFAULT KEY.
  STATICS st_fieldcat         TYPE lvc_t_fcat.
  STATICS st_excluded_fields  TYPE rsdsselopt_t.
*---------------------------------------------------------------------*
  DATA ld_field               TYPE sychar72.
  DATA ls_variant             TYPE disvariant.
  DATA ls_fieldcat            TYPE lvc_s_fcat.
  DATA ls_layout              TYPE lvc_s_layo.              "#EC NEEDED
  DATA ls_sort                TYPE lvc_s_sort.
  DATA ls_filter              TYPE lvc_s_filt.
  DATA ld_curtp               TYPE curtp.
  DATA lts_dfies              TYPE STANDARD TABLE OF dfies.
  DATA lt_fieldcat_reftab     TYPE lvc_t_fcat.

  DATA lr_data                TYPE REF TO data.
  DATA ls_sel_view TYPE rsdsqcat.

  DATA lt_func_groups         TYPE STANDARD TABLE OF rsdsqgx.
  DATA ls_func_groups         TYPE rsdsqgx.
  DATA lt_field_names         TYPE STANDARD TABLE OF rsdsqfn.
  DATA ls_field_names         TYPE rsdsqfn.
  DATA ls_special_groups      TYPE lvc_s_sgrp.

  DATA ld_tabname             TYPE tabname.
  DATA ld_string              TYPE string.

  DATA lt_dd26v               TYPE STANDARD TABLE OF dd26v.
  DATA ls_dd26v               TYPE dd26v.
  DATA ls_tab_info            TYPE t800a.
  DATA ls_ledger_info         TYPE t881.
  data ld_base_table          type tabname.

  CONSTANTS BEGIN OF lc_s_colpos.
  CONSTANTS   rldnr           TYPE i VALUE  10.
  CONSTANTS   ryear           TYPE i VALUE  20.
```

```
  62    CONSTANTS   gjahr           TYPE i VALUE  30.
  63    CONSTANTS   bukrs           TYPE i VALUE  40.
  64    CONSTANTS   rprctr          TYPE i VALUE  50.
  65    CONSTANTS   hkont           TYPE i VALUE  60.
  66    CONSTANTS   lifnr           TYPE i VALUE  70.
  67    CONSTANTS   kunnr           TYPE i VALUE  80.
  68    CONSTANTS   poper           TYPE i VALUE  90.
  69    CONSTANTS   monat           TYPE i VALUE 100.
  70    CONSTANTS   currkey_00      TYPE i VALUE 110.
  71    CONSTANTS   currval_00      TYPE i VALUE 120.
  72    CONSTANTS   currkey_10      TYPE i VALUE 130.
  73    CONSTANTS   currval_10      TYPE i VALUE 140.
  74    CONSTANTS   counter         TYPE i VALUE 150.
  75    CONSTANTS END OF lc_s_colpos.
  76  *---------------------------------------------------------------------*
  77    FIELD-SYMBOLS <ls_fieldcat> TYPE lvc_s_fcat.
  78    FIELD-SYMBOLS <ls_dfies>    TYPE dfies.
  79    FIELD-SYMBOLS <lt_data>     TYPE STANDARD TABLE.
  80  *---------------------------------------------------------------------*
  81    IF ct_fieldlist IS NOT INITIAL.
  82      CLEAR ct_fieldsel.
  83      CLEAR ct_group.
  84      IF id_use_variant IS NOT INITIAL.
  85        CLEAR ct_fieldlist.
  86        CLEAR ct_fieldcat.
  87        CLEAR ct_filter.
  88        CLEAR ct_sort.
  89      ENDIF.
  90    ENDIF.
  91
  92  * Get field list using information from layout
  93    IF id_use_variant IS NOT INITIAL.
  94      ls_variant-report    = sy-repid.
  95      ls_variant-handle    = gc_handle_main.
  96      IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_bro
     wser. "n2414462
  97        ls_variant-log_group = id_ledger.          "n2387297 "n2414462
  98      ENDIF.                                                "n2414462
  99      ls_variant-variant   = cd_variant.
 100
 101      IF st_fieldcat IS INITIAL.
 102        CALL FUNCTION 'DDIF_VIEW_GET'
 103          EXPORTING
 104            name      = id_sel_view
 105          TABLES
 106            dd26v_tab = lt_dd26v
 107          EXCEPTIONS
 108            OTHERS    = 1.
 109
 110        IF sy-subrc > 0
 111        OR lines( lt_dd26v ) > 1.
 112          ld_tabname = id_sel_view.
 113  * Implement suitable error handling here
 114        ELSE.
 115          READ TABLE lt_dd26v
 116            INTO ls_dd26v
 117            INDEX 1.
 118          ld_tabname = ls_dd26v-tabname.
 119        ENDIF.
 120
 121        IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_b
```

```
rowser.
        CALL FUNCTION 'G_GET_LEDGER_INFO'
          EXPORTING
            i_rldnr       = id_ledger
          IMPORTING
            e_ledger_info = ls_ledger_info
          EXCEPTIONS
            OTHERS        = 0.

        CALL FUNCTION 'G_GET_TABLE_INFO'
          EXPORTING
            i_tab      = ls_ledger_info-tab
          IMPORTING
            e_tab_info = ls_tab_info
          EXCEPTIONS
            OTHERS     = 0.
      ENDIF.

* Build default field catalog
      CALL FUNCTION 'LVC_FIELDCATALOG_MERGE'
        EXPORTING
          i_structure_name = ld_tabname
        CHANGING
          ct_fieldcat      = st_fieldcat.

      CASE id_sel_view.
        WHEN gc_s_hdb_ddic-pca_line_items
          OR gc_s_hdb_ddic-pca_line_items_ext.
          CALL FUNCTION 'LVC_FIELDCATALOG_MERGE'
            EXPORTING
              i_structure_name = 'GLPCA'
            CHANGING
              ct_fieldcat      = lt_fieldcat_reftab.
          SORT lt_fieldcat_reftab BY fieldname.
      ENDCASE.

      CALL FUNCTION 'DDIF_FIELDINFO_GET'
        EXPORTING
          tabname   = id_sel_view
        TABLES
          dfies_tab = lts_dfies.
      SORT lts_dfies
        BY fieldname.

      IF gts_curtp IS INITIAL.
        PERFORM get_curtp_info
          USING
            gd_sel_view
            p_ledger
            ls_tab_info-comptab
          CHANGING
            gts_curtp.
      ENDIF.

* Get information about selection view
      PERFORM sel_view_check_get
        USING
          id_sel_view
        CHANGING
          ls_sel_view
          ld_base_table.
```

```
182
183 * Get field groups from selection view
184       CALL FUNCTION 'RS_READ_SEL_OPTIONS'
185         EXPORTING
186           key         = ls_sel_view
187         TABLES
188           func_groups = lt_func_groups
189           field_names = lt_field_names
190         EXCEPTIONS
191           OTHERS      = 0.
192
193 * Prepare field list for assignment of field groups
194       SORT lt_field_names BY fname.
195
196       LOOP AT lt_func_groups
197         INTO  ls_func_groups.
198         ls_special_groups-sp_group = ls_func_groups-numb.
199         ls_special_groups-text     = ls_func_groups-gtext.
200         APPEND ls_special_groups
201           TO ct_special_groups.
202       ENDLOOP.
203       ls_special_groups-sp_group = 'ZZ'.
204       ls_special_groups-text     = text045.
205       IF ls_special_groups-text IS INITIAL.
206         ls_special_groups-text = ls_special_groups-sp_group.
207       ENDIF.
208       APPEND ls_special_groups
209         TO ct_special_groups.
210
211       LOOP AT st_fieldcat
212         ASSIGNING <ls_fieldcat>.
213         ld_string = <ls_fieldcat>-fieldname.
214         INSERT ld_string
215           INTO TABLE sth_flist.
216
217         CASE <ls_fieldcat>-fieldname.
218           WHEN 'ANFBJ'.
219             READ TABLE lts_dfies
220               ASSIGNING <ls_dfies>
221               WITH KEY
222                 fieldname = <ls_fieldcat>-fieldname
223               BINARY SEARCH.
224             <ls_fieldcat>-scrtext_m =
225             <ls_fieldcat>-scrtext_l = <ls_dfies>-fieldtext.
226             <ls_fieldcat>-col_pos = 999999.
227           WHEN 'BELNR'.
228             IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
229               CONCATENATE <ls_fieldcat>-scrtext_l '(' text-035 ')'
230                 INTO <ls_fieldcat>-scrtext_l
231                 SEPARATED BY space.
232             ENDIF.
233             <ls_fieldcat>-hotspot = abap_true.
234           WHEN 'BUKRS'
235             OR 'RBUKRS'.
236             <ls_fieldcat>-col_pos = lc_s_colpos-bukrs.
237             <ls_fieldcat>-key = abap_true.
238           WHEN 'BUZEI'.
239             IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
240               CONCATENATE <ls_fieldcat>-scrtext_l '(' text-035 ')'
241                 INTO <ls_fieldcat>-scrtext_l
242                 SEPARATED BY space.
```

```
243             ENDIF.
244             <ls_fieldcat>-col_pos = 999999.
245             <ls_fieldcat>-hotspot = abap_true.
246           WHEN 'COUNTER'.
247             <ls_fieldcat>-col_pos = lc_s_colpos-counter.
248             <ls_fieldcat>-do_sum = abap_true.
249           WHEN 'CURRKEY_00'.
250             <ls_fieldcat>-col_pos = lc_s_colpos-currkey_00.
251           WHEN 'CURRKEY_10'.
252             <ls_fieldcat>-col_pos = lc_s_colpos-currkey_10.
253           WHEN 'CURRVAL_00'.
254             <ls_fieldcat>-col_pos = lc_s_colpos-currval_00.
255             <ls_fieldcat>-do_sum = abap_true.
256           WHEN 'CURRVAL_10'.
257             <ls_fieldcat>-col_pos = lc_s_colpos-currval_10.
258             <ls_fieldcat>-do_sum = abap_true.
259           WHEN 'DOCLN'.
260             IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
261               CONCATENATE <ls_fieldcat>-scrtext_l '(' text-036 ')'
262                 INTO <ls_fieldcat>-scrtext_l
263                 SEPARATED BY space.
264             ENDIF.
265             <ls_fieldcat>-col_pos = 999999.
266             <ls_fieldcat>-hotspot = abap_true.
267           WHEN 'DOCNR'.
268             IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
269               CONCATENATE <ls_fieldcat>-scrtext_l '(' text-036 ')'
270                 INTO <ls_fieldcat>-scrtext_l
271                 SEPARATED BY space.
272             ENDIF.
273             <ls_fieldcat>-col_pos = 999999.
274             <ls_fieldcat>-hotspot = abap_true.
275           WHEN 'GJAHR'.
276             <ls_fieldcat>-col_pos = lc_s_colpos-gjahr.
277             <ls_fieldcat>-key = abap_true.
278             IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
279               CONCATENATE <ls_fieldcat>-scrtext_l '(' text-035 ')'
280                 INTO <ls_fieldcat>-scrtext_l
281                 SEPARATED BY space.
282             ENDIF.
283           WHEN 'HKONT'
284             OR 'RACCT'.
285             <ls_fieldcat>-col_pos = lc_s_colpos-hkont.
286             <ls_fieldcat>-key = abap_true.
287             <ls_fieldcat>-hotspot = abap_true.
288           WHEN 'LIFNR'.
289             <ls_fieldcat>-col_pos = lc_s_colpos-lifnr.
290             <ls_fieldcat>-key = abap_true.
291             <ls_fieldcat>-hotspot = abap_true.
292           WHEN 'KUNNR'.
293             <ls_fieldcat>-col_pos = lc_s_colpos-kunnr.
294             <ls_fieldcat>-key = abap_true.
295             <ls_fieldcat>-hotspot = abap_true.
296           WHEN 'MONAT'.
297             <ls_fieldcat>-col_pos = lc_s_colpos-monat.
298             <ls_fieldcat>-key = abap_true.
299           WHEN 'POPER'.
300             <ls_fieldcat>-col_pos = lc_s_colpos-poper.
301             <ls_fieldcat>-key = abap_true.
302           WHEN 'REBZJ'.
303             READ TABLE lts_dfies
```

```
304                ASSIGNING <ls_dfies>
305                WITH KEY
306                  fieldname = <ls_fieldcat>-fieldname
307                BINARY SEARCH.
308              <ls_fieldcat>-scrtext_m =
309              <ls_fieldcat>-scrtext_l = <ls_dfies>-fieldtext.
310              <ls_fieldcat>-col_pos = 999999.
311            WHEN 'RYEAR'.
312              <ls_fieldcat>-col_pos = lc_s_colpos-ryear.
313              <ls_fieldcat>-key = abap_true.
314              IF gd_subapplication = gc_hdb_subappl-s_newgl-gl_view.
315                CONCATENATE <ls_fieldcat>-scrtext_l '(' text-036 ')'
316                  INTO <ls_fieldcat>-scrtext_l
317                  SEPARATED BY space.
318              ENDIF.
319            WHEN 'RLDNR'.
320              <ls_fieldcat>-col_pos = lc_s_colpos-rldnr.
321              <ls_fieldcat>-key = abap_true.
322            WHEN 'RPRCTR'.
323              <ls_fieldcat>-col_pos = lc_s_colpos-rprctr.
324              <ls_fieldcat>-key = abap_true.
325              <ls_fieldcat>-hotspot = abap_true.
326            WHEN 'PRCTR'
327              OR 'PPRCTR'
328              OR 'SPRCTR'
329              OR 'EPRCTR'
330              OR 'MATNR'.
331              <ls_fieldcat>-hotspot = abap_true.
332            WHEN 'BALANCE'
333              OR 'CREDIT'
334              OR 'DEBIT'
335              OR 'CURTP'
336              OR 'CURRUNIT'
337              OR 'TURNOVER'.
338              <ls_fieldcat>-tech   = abap_true.
339              <ls_fieldcat>-no_out = abap_true.
340              <ls_fieldcat>-col_pos = 999999.
341              CONTINUE.
342            WHEN 'MWSKZ'
343              OR 'MWSK1'
344              OR 'MWSK2'
345              OR 'MWSK3'.
346              CONCATENATE <ls_fieldcat>-scrtext_l '(' <ls_fieldcat>-fieldn
    ame ')'
347                INTO <ls_fieldcat>-scrtext_l
348                SEPARATED BY space.
349              <ls_fieldcat>-col_pos = 999999.
350            WHEN 'X_CLEARED_ITEM'.
351              <ls_fieldcat>-checkbox = abap_true.
352            WHEN OTHERS.
353              <ls_fieldcat>-col_pos = 999999.
354          ENDCASE.
355          IF <ls_fieldcat>-fieldname CS 'CURRKEY_'
356          OR <ls_fieldcat>-fieldname CS 'CURRVAL_'.
357            ld_curtp = <ls_fieldcat>-fieldname+8(2).
358            READ TABLE gts_curtp
359              WITH TABLE KEY
360                table_line = ld_curtp
361              TRANSPORTING NO FIELDS.
362            IF sy-subrc <> 0.
363              <ls_fieldcat>-tech = abap_true.
```

```
364             <ls_fieldcat>-no_out = abap_true.
365           ELSE.
366             IF <ls_fieldcat>-fieldname CS 'CURRVAL_'.
367               <ls_fieldcat>-do_sum = abap_true.
368             ENDIF.
369           ENDIF.
370         ENDIF.
371         IF  <ls_fieldcat>-scrtext_l IS INITIAL
372         AND <ls_fieldcat>-scrtext_m IS INITIAL
373         AND <ls_fieldcat>-scrtext_s IS INITIAL.
374           IF <ls_fieldcat>-reptext IS INITIAL.
375             <ls_fieldcat>-scrtext_s =
376             <ls_fieldcat>-scrtext_m =
377             <ls_fieldcat>-scrtext_l = <ls_fieldcat>-fieldname.
378           ELSE.
379             <ls_fieldcat>-scrtext_s =
380             <ls_fieldcat>-scrtext_m =
381             <ls_fieldcat>-scrtext_l = <ls_fieldcat>-reptext.
382           ENDIF.
383         ENDIF.
384
385 * Find Group Assignment for ALV Grid Display
386         READ TABLE lt_field_names
387           INTO ls_field_names
388           WITH KEY
389             fname = <ls_fieldcat>-fieldname
390           BINARY SEARCH.
391         IF sy-subrc = 0.
392           <ls_fieldcat>-sp_group = ls_field_names-numb.
393         ELSE.
394           IF <ls_fieldcat>-fieldname(2) = 'ZZ'.
395             <ls_fieldcat>-sp_group = 'ZZ'.
396           ENDIF.
397         ENDIF.
398
399 * Get information from reference table
400         IF lt_fieldcat_reftab IS NOT INITIAL.
401           READ TABLE lt_fieldcat_reftab
402             INTO ls_fieldcat
403             WITH KEY
404               fieldname = <ls_fieldcat>-fieldname
405             BINARY SEARCH.
406           IF sy-subrc = 0.
407             <ls_fieldcat>-col_pos = ls_fieldcat-col_pos.
408             IF ls_fieldcat-col_pos <= 29.
409               <ls_fieldcat>-key = abap_true.
410             ENDIF.
411             CONTINUE.
412           ENDIF.
413         ENDIF.
414         IF <ls_fieldcat>-sp_group IS INITIAL.
415           <ls_fieldcat>-sp_group = '99'.
416         ENDIF.
417       ENDLOOP.
418
419       IF go_badi_lib IS NOT INITIAL.                          "n2273910
420         CALL BADI go_badi_lib->add_fields                     "n2273910
421           CHANGING                                            "n2273910
422             ct_fieldcat = st_fieldcat.                        "n2273910
423       ENDIF.                                                  "n2273910
424
```

```
425         SORT st_fieldcat BY col_pos.
426         LOOP AT st_fieldcat
427           ASSIGNING <ls_fieldcat>.
428           <ls_fieldcat>-col_pos = sy-tabix.
429         ENDLOOP.
430
431   * Determine Selection View
432         PERFORM sel_view_check_get
433           USING
434             gd_sel_view
435           CHANGING
436             ls_sel_view
437             ld_base_table.
438
439   * Get excluded fields
440         CALL FUNCTION 'FAGL_HDB_CUST_SVIEW_EXCL_FLDS'
441           EXPORTING
442             ed_appl            = gc_hdb_appl-financials
443             ed_subappl         = gd_subapplication
444             es_sel_view        = ls_sel_view
445           IMPORTING
446             it_excl_fields_alv = st_excluded_fields
447           EXCEPTIONS
448             OTHERS             = 0.
449
450       ENDIF.
451
452       IF ls_variant-variant(1) NA '/0123456789'.
453         ls_variant-username = sy-uname.
454       ENDIF.
455       CREATE DATA lr_data TYPE STANDARD TABLE OF (id_sel_view).
456       ASSIGN lr_data->* TO <lt_data>.
457   * Get field catalog using layout
458       CALL FUNCTION 'LVC_VARIANT_SELECT'
459         EXPORTING
460           i_dialog            = abap_false
461           i_user_specific     = 'A'
462           it_default_fieldcat = st_fieldcat
463         IMPORTING
464           et_fieldcat         = ct_fieldcat
465           et_sort             = ct_sort
466           et_filter           = ct_filter
467           es_layout           = ls_layout
468         TABLES
469           it_data             = <lt_data>
470         CHANGING
471           cs_variant          = ls_variant
472         EXCEPTIONS
473           OTHERS              = 1.
474       IF sy-subrc <> 0.
475         ct_fieldcat = st_fieldcat.
476         LOOP AT ct_fieldcat
477           ASSIGNING <ls_fieldcat>.
478           <ls_fieldcat>-no_out = abap_true.
479         ENDLOOP.
480         CLEAR ls_variant-variant.
481       ENDIF.
482       cd_variant = ls_variant-variant.
483     ENDIF.
484
485   * Check whether at least one field is set up to be displayed
```

```
486     READ TABLE ct_fieldcat
487       WITH KEY
488         no_out = space
489       TRANSPORTING NO FIELDS.
490
491   * Build list of fields to be selected from DB
492     IF sy-subrc = 0.
493       LOOP AT ct_fieldcat
494         ASSIGNING <ls_fieldcat>.
495   * If fields are hidden, they are also not relevant for totals
496         IF <ls_fieldcat>-no_out = abap_true.                  "n2436588
497           <ls_fieldcat>-do_sum = abap_false.                  "n2436588
498         ENDIF.                                                "n2436588
499
500         IF st_excluded_fields IS NOT INITIAL.
501           IF <ls_fieldcat>-fieldname IN st_excluded_fields.
502             <ls_fieldcat>-no_out = 'X'.
503             <ls_fieldcat>-tech   = 'X'.
504             CONTINUE.
505           ENDIF.
506         ENDIF.
507   * Handle special technical fields
508         CASE <ls_fieldcat>-fieldname.
509           WHEN 'TURNOVER'.
510             <ls_fieldcat>-tech   = abap_true.
511             <ls_fieldcat>-no_out = abap_true.
512             CONTINUE.
513           WHEN OTHERS.
514             IF  <ls_fieldcat>-no_out = abap_true.             "n2436588
515               CONTINUE.                                       "n2387297
516             ENDIF.                                            "n2387297
517
518             TRY.
519                 cl_abap_dyn_prg=>check_whitelist_tab( val = <ls_fieldcat>-
    fieldname
520                                                       whitelist = sth_flis
    t ).
521               CATCH cx_abap_not_in_whitelist.
522                 CONTINUE.
523             ENDTRY.
524
525             CASE <ls_fieldcat>-datatype.
526               WHEN 'CURR'
527                 OR 'QUAN'
528                 OR 'INT4'.
529   * For value fields make sure that corresponding currency key field
530   * is added as well (even if it is not shown)...
531                 IF <ls_fieldcat>-cfieldname IS NOT INITIAL
532                 OR <ls_fieldcat>-qfieldname IS NOT INITIAL.
533                   ld_field = <ls_fieldcat>-cfieldname.
534                   IF ld_field IS INITIAL.
535                     ld_field = <ls_fieldcat>-qfieldname.
536                   ENDIF.
537
538                   TRY.
539                       CALL METHOD cl_abap_dyn_prg=>check_whitelist_tab
540                         EXPORTING
541                           val       = ld_field  " Input that shall be chec
    ked
542                           whitelist = sth_flist " table of allowed values
543                         RECEIVING
```

```
544                         val_str   = ld_string.
545
546                   CATCH cx_abap_not_in_whitelist.
547                     CONTINUE.
548                 ENDTRY.
549
550                 ld_field = ld_string.
551                 IF  <ls_fieldcat>-no_out = abap_false.      "n2447572
552                   COLLECT ld_field
553                     INTO ct_fieldsel.
554                   COLLECT ld_field
555                     INTO ct_group.
556                 ENDIF.                                     "n2447572
557                 COLLECT ld_field
558                   INTO ct_fieldlist.
559               ENDIF.
560               CONCATENATE
561                 'SUM(' <ls_fieldcat>-fieldname ') as'       "#EC NOTEXT
562                 <ls_fieldcat>-fieldname
563             INTO ld_field
564             SEPARATED BY space.
565             WHEN OTHERS.
566               ld_field = <ls_fieldcat>-fieldname.
567               COLLECT ld_field INTO ct_group.
568           ENDCASE.
569       ENDCASE.
570       IF  <ls_fieldcat>-no_out = abap_false.               "n2447572
571         COLLECT ld_field
572           INTO ct_fieldsel.
573       ENDIF.                                               "n2447572
574       ld_field = <ls_fieldcat>-fieldname.
575       COLLECT ld_field
576         INTO ct_fieldlist.
577     ENDLOOP.
578     SORT ct_fieldcat BY fieldname.
579 * Add possibly hidden fields to be used for sorting
580     LOOP AT ct_sort
581       INTO  ls_sort
582       WHERE no_out = abap_true.
583       ld_field = ls_sort-fieldname.
584
585       TRY.
586           ld_field = cl_abap_dyn_prg=>check_column_name( ld_field ).
587         CATCH cx_abap_invalid_name.
588           CONTINUE.
589       ENDTRY.
590
591       READ TABLE ct_fieldcat
592         INTO ls_fieldcat
593         WITH KEY
594           fieldname = ld_field
595         BINARY SEARCH.
596       CHECK sy-subrc = 0.
597
598       CASE ls_fieldcat-datatype.                    "begin "n2387297
599         WHEN 'CURR'
600           OR 'QUAN'
601           OR 'INT4'.
602         WHEN OTHERS.
603           COLLECT ld_field
604             INTO ct_fieldsel.
```

```
605         ENDCASE.                                          "end "n2387297
606         COLLECT ld_field
607           INTO ct_fieldlist.
608         IF ls_fieldcat-inttype <> 'P'.
609             COLLECT ld_field
610               INTO ct_group.
611           ENDIF.
612       ENDLOOP.
613   * Add possibly hidden fields to be used for filtering
614       LOOP AT ct_filter
615         INTO  ls_filter.
616         ld_field = ls_filter-fieldname.
617
618         TRY.
619             ld_field = cl_abap_dyn_prg=>check_column_name( ld_field ).
620           CATCH cx_abap_invalid_name.
621             CONTINUE.
622         ENDTRY.
623
624         READ TABLE ct_fieldcat
625           INTO ls_fieldcat
626           WITH KEY fieldname = ld_field
627           BINARY SEARCH.
628         CHECK sy-subrc = 0
629         AND   ls_fieldcat-no_out = abap_true.
630         COLLECT ld_field
631           INTO ct_fieldsel.
632         COLLECT ld_field
633           INTO ct_fieldlist.
634         IF ls_fieldcat-inttype <> 'P'.
635           COLLECT ld_field
636             INTO ct_group.
637         ENDIF.
638       ENDLOOP.
639
640   * No useable layout found >> Default field list
641     ELSE.
642       IF id_sel_view = gc_s_hdb_ddic-gl_view                "n2231737
643       OR id_sel_view = gc_s_hdb_ddic-gl_view_ext.           "n2231737
644         ld_field = 'RLDNR'.
645         COLLECT ld_field INTO ct_fieldlist.
646       ENDIF.
647       CASE id_subapplication.
648         WHEN gc_hdb_subappl-s_pca-line_item_browser.
649           ld_field = 'RRCTY'.
650           COLLECT ld_field INTO ct_fieldlist.
651           ld_field = 'RLDNR'.
652           COLLECT ld_field INTO ct_fieldlist.
653           ld_field = 'KOKRS'.
654           COLLECT ld_field INTO ct_fieldlist.
655           ld_field = 'RPRCTR'.
656           COLLECT ld_field INTO ct_fieldlist.
657           ld_field = 'SPRCTR'.
658           COLLECT ld_field INTO ct_fieldlist.
659           ld_field = 'RBUKRS'.
660         WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
661           ld_field = 'RLDNR'.
662           COLLECT ld_field INTO ct_fieldlist.
663
664           IF ls_tab_info IS INITIAL.
665             READ TABLE lts_dfies
```

```
666             ASSIGNING <ls_dfies>
667             WITH KEY
668               fieldname = 'RBUKRS'
669             BINARY SEARCH.
670           IF sy-subrc <> 0.
671             READ TABLE lts_dfies
672               ASSIGNING <ls_dfies>
673               WITH KEY
674                 fieldname = 'BUKRS'
675               BINARY SEARCH.
676             IF sy-subrc <> 0.
677               READ TABLE lts_dfies
678                 ASSIGNING <ls_dfies>
679                 WITH KEY
680                   fieldname = 'RCOMP'
681                 BINARY SEARCH.
682             ENDIF.
683           ENDIF.
684           IF <ls_dfies> IS ASSIGNED.
685             ld_field = <ls_dfies>-fieldname.
686           ENDIF.
687         ELSE.
688           ld_field = ls_tab_info-dim_orgunit.
689         ENDIF.
690       WHEN OTHERS.
691         ld_field = 'BUKRS'.
692     ENDCASE.
693     IF ld_field IS NOT INITIAL.
694       COLLECT ld_field INTO ct_fieldlist.
695     ENDIF.
696     CASE id_sel_view.
697       WHEN gc_s_hdb_ddic-gl_view
698         OR gc_s_hdb_ddic-gl_view_ext                          "n2231737
699         OR gc_s_hdb_ddic-pca_line_items
700         OR gc_s_hdb_ddic-pca_line_items_ext.
701       WHEN OTHERS.
702         IF id_subapplication = gc_hdb_subappl-s_special_ledger-line_item
    _browser.
703           ld_field = 'RYEAR'.
704         COLLECT ld_field INTO ct_fieldlist.
705         ld_field = 'POPER'.
706         COLLECT ld_field INTO ct_fieldlist.
707         ELSE.
708         ld_field = 'GJAHR'.
709         COLLECT ld_field INTO ct_fieldlist.
710         ld_field = 'MONAT'.
711         COLLECT ld_field INTO ct_fieldlist.
712         ENDIF.
713     ENDCASE.
714     CASE p_appl.
715       WHEN gc_hdb_subappl-s_receivables-line_item_browser.
716         ld_field = 'KUNNR'.
717       WHEN gc_hdb_subappl-s_payables-line_item_browser.
718         ld_field = 'LIFNR'.
719       WHEN gc_hdb_subappl-s_pca-line_item_browser
720         OR gc_hdb_subappl-s_special_ledger-line_item_browser.
721         READ TABLE ct_fieldcat
722           INTO ls_fieldcat
723           WITH KEY
724             fieldname = ld_field
725           BINARY SEARCH.
```

```
726
727           IF sy-subrc = 0.
728             ld_field = 'RACCT'.
729           ENDIF.
730         WHEN OTHERS.
731           ld_field = 'HKONT'.
732       ENDCASE.
733       COLLECT ld_field INTO ct_fieldlist.
734       ld_field = 'CURRKEY_10'.
735       COLLECT ld_field INTO ct_fieldlist.
736
737       ct_group = ct_fieldlist.
738       ct_fieldsel = ct_fieldlist.
739
740       ld_field = 'CURRVAL_10'.
741       COLLECT ld_field INTO ct_fieldlist.
742
743       ld_field = 'COUNTER'.
744       COLLECT ld_field INTO ct_fieldlist.
745
746       ld_field = 'SUM( CURRVAL_10 ) as CURRVAL_10'.           "#EC NOTEXT
747       COLLECT ld_field INTO ct_fieldsel.
748
749       ld_field = 'SUM( COUNTER ) as COUNTER'.                 "#EC NOTEXT
750       COLLECT ld_field INTO ct_fieldsel.
751
752       LOOP AT ct_fieldcat
753         ASSIGNING <ls_fieldcat>.
754         IF st_excluded_fields IS NOT INITIAL.
755           IF <ls_fieldcat>-fieldname IN st_excluded_fields.
756             <ls_fieldcat>-no_out = 'X'.
757             <ls_fieldcat>-tech   = 'X'.
758             CONTINUE.
759           ENDIF.
760         ENDIF.
761         READ TABLE ct_fieldlist
762           WITH KEY
763             table_line = <ls_fieldcat>-fieldname
764           TRANSPORTING NO FIELDS.
765         IF sy-subrc = 0.
766           CASE id_subapplication.
767             WHEN gc_hdb_subappl-s_pca-line_item_browser
768               OR gc_hdb_subappl-s_special_ledger-line_item_browser.
769               CASE <ls_fieldcat>-fieldname.
770                 WHEN 'RRCTY'
771                   OR 'RLDNR'.
772                   <ls_fieldcat>-no_out = abap_true.
773                 WHEN OTHERS.
774                   <ls_fieldcat>-no_out = abap_false.
775               ENDCASE.
776             WHEN OTHERS.
777               <ls_fieldcat>-no_out = abap_false.
778           ENDCASE.
779         ENDIF.
780         IF  <ls_fieldcat>-no_out = abap_false
781         AND <ls_fieldcat>-do_sum = abap_false.
782           ls_sort-spos = <ls_fieldcat>-col_pos.
783           ls_sort-fieldname = <ls_fieldcat>-fieldname.
784           ls_sort-up = abap_true.
785           APPEND ls_sort
786             TO ct_sort.
```

```
787         ENDIF.
788         CASE <ls_fieldcat>-fieldname.                          "HW 1840118
789           WHEN 'HWMET'
790           OR   'ABPER'
791           OR   'SAMPLED'
792           OR   'SSBLK'
793           OR   'STEKZ'
794           OR   'XANET'
795           OR   'XFAKT'
796           OR   'XHRES'
797           OR   'XNCOP'
798           OR   'XUMAN'.
799             <ls_fieldcat>-no_out = 'X'.
800             <ls_fieldcat>-tech   = 'X'.
801         ENDCASE.                                               "HW 1840118
802       ENDLOOP.
803     ENDIF.
804
805   ENDFORM.                    " fill_fieldlist
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F08 .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  CHECK_BEFORE_START
6  *&---------------------------------------------------------------------*
7  FORM check_before_start
8    USING
9      isx_item                  TYPE rsds_type
10     isx_kess                  TYPE rsds_type "n2571532
11     id_subapplication         TYPE fbcon_s_hdb-subappl
12     id_hdb_is_primary         type boole_d
13   CHANGING
14     cd_sel_view               TYPE tabname
15     cd_dbcon_name             TYPE dbcon_name
16     cd_exit                   TYPE boole_d.
17 *---------------------------------------------------------------------*
18   DATA lt_ccode               TYPE STANDARD TABLE OF bukrs.
19   DATA ld_ccode               TYPE bukrs.
20   DATA ld_newgl_active.
21   DATA lt_fieldcat            TYPE lvc_t_fcat.
22   DATA ls_selopt              TYPE rsdsselopt.              "n2767139
23   DATA lt_tfavw               TYPE STANDARD TABLE OF tfavw. "n2767139
24   DATA ls_tfavw               TYPE tfavw.                   "n2767139
25   DATA ld_object              TYPE tfav-objct.              "n2767139
26   DATA ld_worklist            TYPE tfavw-ident.             "n2767139
27 *---------------------------------------------------------------------*
28   CHECK sy-dynnr = '1000'.
29   CLEAR cd_exit.
30
31 ** Get values from worklists                        "begin of "n2767139
32   IF gd_consider_worklists = abap_true
33     AND gd_worklist_active = abap_true
34     AND (   sy-repid <> 'FAGL_LINE_ITEM_BROWSER_SL'
35         AND sy-repid <> 'FAGL_LINE_ITEM_BROWSER_PCA' ).
36     IF p_wlbuk IS NOT INITIAL.
37       s_ccnowl[] = s_ccode[].
38       REFRESH s_ccode[].
39 ** Get company codes from worklist
40       REFRESH lt_tfavw.
41       ld_object = 'BUKRS'.
42       ld_worklist = p_wlbuk.
43
44       CALL FUNCTION 'RF_WORKLISTS_VALUES_GET'
45         EXPORTING
46           id_objct     = ld_object
47           id_ident     = ld_worklist
48         TABLES
49           et_tfavw     = lt_tfavw
50         EXCEPTIONS
51           not_existing = 1.
52       IF sy-subrc <> 0.
53         MESSAGE e040(msitem) WITH ld_worklist.
54       ENDIF.
55
56       CLEAR ls_selopt.
57       ls_selopt-sign    = 'I'.
58       ls_selopt-option  = 'EQ'.
59       LOOP AT lt_tfavw INTO ls_tfavw.
60         ls_selopt-low = ls_tfavw-value.
61         APPEND ls_selopt TO s_ccode[].
```

```
62        ENDLOOP.
63      ENDIF.
64
65      CLEAR ls_selopt.
66      ls_selopt-sign    = 'I'.
67      ls_selopt-option  = 'EQ'.
68
69      IF p_wlcus IS NOT INITIAL.
70        ld_object   = 'KUNNR'.
71        ld_worklist = p_wlcus.
72        s_acnowl[]  = s_cust[].
73        REFRESH s_cust[].
74      ELSEIF p_wlven IS NOT INITIAL.
75        ld_object   = 'LIFNR'.
76        ld_worklist = p_wlven.
77        s_acnowl[]  = s_vend[].
78        REFRESH s_vend[].
79      ELSEIF p_wlrac IS NOT INITIAL.
80        ld_object   = 'SAKNR'.
81        ld_worklist = p_wlrac.
82        s_acnowl[]  = s_racct[].
83        REFRESH s_racct[].
84      ENDIF.
85
86      IF p_wlven IS NOT INITIAL
87        OR p_wlcus IS NOT INITIAL
88        OR p_wlrac IS NOT INITIAL.
89        REFRESH lt_tfavw.
90        CALL FUNCTION 'RF_WORKLISTS_VALUES_GET'
91          EXPORTING
92            id_objct     = ld_object
93            id_ident     = ld_worklist
94          TABLES
95            et_tfavw     = lt_tfavw
96          EXCEPTIONS
97            not_existing = 1.
98        IF sy-subrc <> 0.
99          MESSAGE e040(msitem) WITH ld_worklist.
100       ENDIF.
101
102       CLEAR ls_selopt.
103       ls_selopt-sign    = 'I'.
104       ls_selopt-option  = 'EQ'.
105       LOOP AT lt_tfavw INTO ls_tfavw.
106         ls_selopt-low = ls_tfavw-value.
107         CASE ld_object.
108           WHEN 'SAKNR'.
109             APPEND ls_selopt TO s_racct[].
110           WHEN 'KUNNR'.
111             APPEND ls_selopt TO s_cust[].
112           WHEN 'LIFNR'.
113             APPEND ls_selopt TO s_vend[].
114         ENDCASE.
115       ENDLOOP.
116     ENDIF.
117   ENDIF.                                              "end of "n2767139
118
119 ** Get values from sets                               "begin of "n2869685
120   IF    gd_consider_sets = abap_true
121     AND gd_sets_active = abap_true
122     AND (   sy-repid <> 'FAGL_LINE_ITEM_BROWSER_SL'
```

```
123       AND     sy-repid <> 'FAGL_LINE_ITEM_BROWSER_PCA' ).
124       DATA lt_set_vals  TYPE TABLE OF rgsb4.
125       DATA ls_set_val   TYPE rgsb4.
126       DATA ld_set       TYPE rgsb4-setnr.
127       DATA ld_fieldname TYPE fieldname.
128
129       IF p_setbuk IS NOT INITIAL.
130         ld_set        = p_setidb.
131         ld_fieldname  = 'BUKRS'. "#EC NO_TEXT
132         CALL FUNCTION 'G_SET_GET_ID_FROM_NAME'
133           EXPORTING
134             shortname = p_setbuk
135           IMPORTING
136             new_setid = p_setidb.
137         IF p_setidb <> ld_set.
138           ld_set        = p_setidb.
139         ENDIF.
140         s_ccnowl      = s_ccode.
141         s_ccnowl[]    = s_ccode[].
142         REFRESH s_ccode[].
143
144         REFRESH lt_set_vals.
145         CALL FUNCTION 'G_SET_GET_ALL_VALUES'
146           EXPORTING
147             setnr                       = ld_set
148             fieldname                   = ld_fieldname
149           TABLES
150             set_values                  = lt_set_vals.
151
152         LOOP AT lt_set_vals INTO ls_set_val.
153           "No sets with a variable
154           CHECK ls_set_val-from(1) <> '&'.
155           CLEAR ls_selopt.
156           ls_selopt-low   = ls_set_val-from(4).
157           ls_selopt-high  = ls_set_val-to(4).
158           ls_selopt-sign  = 'I'.
159           IF ls_selopt-high IS INITIAL.
160             ls_selopt-option = 'EQ'.
161           ELSE.
162             ls_selopt-option = 'BT'.
163           ENDIF.
164           MOVE-CORRESPONDING ls_selopt TO s_ccode.
165           APPEND s_ccode.
166         ENDLOOP.
167       ENDIF.
168
169       IF p_setcus IS NOT INITIAL.
170         ld_fieldname  = 'KUNNR'.
171         ld_set = p_setidd.
172         CALL FUNCTION 'G_SET_GET_ID_FROM_NAME'
173           EXPORTING
174             shortname = p_setcus
175           IMPORTING
176             new_setid = p_setidd.
177         IF p_setidd <> ld_set.
178           ld_set        = p_setidd.
179         ENDIF.
180         s_acnowl[]    = s_cust[].
181         REFRESH s_cust[].
182       ELSEIF p_setven IS NOT INITIAL.
183         ld_fieldname  = 'LIFNR'.
```

```
184         ld_set        = p_setidk.
185         CALL FUNCTION 'G_SET_GET_ID_FROM_NAME'
186           EXPORTING
187             shortname = p_setven
188           IMPORTING
189             new_setid = p_setidk.
190         IF p_setidk <> ld_set.
191           ld_set        = p_setidk.
192         ENDIF.
193         s_acnowl[]    = s_vend[].
194         REFRESH s_vend[].
195       ELSEIF p_setrac IS NOT INITIAL.
196         ld_fieldname  = 'RACCT'.
197         ld_set        = p_setidr.
198         CALL FUNCTION 'G_SET_GET_ID_FROM_NAME'
199           EXPORTING
200             shortname = p_setrac
201           IMPORTING
202             new_setid = p_setidr.
203         IF p_setidr <> ld_set.
204           ld_set        = p_setidr.
205         ENDIF.
206         s_acnowl[]    = s_racct[].
207         REFRESH s_racct[].
208       ENDIF.
209
210       IF p_setcus IS NOT INITIAL
211         OR p_setven IS NOT INITIAL
212         OR p_setrac IS NOT INITIAL.
213
214         REFRESH lt_set_vals.
215         CALL FUNCTION 'G_SET_GET_ALL_VALUES'
216           EXPORTING
217             setnr                       = ld_set
218             fieldname                   = ld_fieldname
219           TABLES
220             set_values                  = lt_set_vals.
221
222         LOOP AT lt_set_vals INTO ls_set_val.
223           "No sets with a variable
224           CHECK ls_set_val-from(1) <> '&'.
225           CLEAR ls_selopt.
226           ls_selopt-low   = ls_set_val-from(10).
227           ls_selopt-high  = ls_set_val-to(10).
228           ls_selopt-sign  = 'I'.
229           IF ls_selopt-high IS INITIAL.
230             ls_selopt-option = 'EQ'.
231           ELSE.
232             ls_selopt-option = 'BT'.
233           ENDIF.
234           CASE ld_fieldname.
235             WHEN 'KUNNR'.
236               MOVE-CORRESPONDING ls_selopt TO s_cust.
237               APPEND s_cust.
238             WHEN 'LIFNR'.
239               MOVE-CORRESPONDING ls_selopt TO s_vend.
240               APPEND s_vend.
241             WHEN 'RACCT'.
242               MOVE-CORRESPONDING ls_selopt TO s_racct.
243               APPEND s_racct.
244           ENDCASE.
```

```
245         ENDLOOP.
246       ENDIF.
247     ENDIF.                                                "end of "n2869685
248
249     CASE cd_sel_view.
250   * In case of New GL make sure that New GL is active for all company code
    s
251       WHEN gc_s_hdb_ddic-gl_view
252         OR gc_s_hdb_ddic-gl_view_ext                        "n2104752
253         or if_fagl_lib_cds_util=>c_view_n_gl.
254         SELECT  bukrs
255           FROM  t001
256           INTO  TABLE lt_ccode
257           WHERE bukrs IN s_ccode.
258
259         LOOP AT lt_ccode
260           INTO  ld_ccode.
261   * check at PAI, if NewGL is active for the selected company codes.
262           CALL FUNCTION 'FAGL_CHECK_GLFLEX_ACTIVE'
263             EXPORTING
264               id_bukrs        = ld_ccode
265             IMPORTING
266               e_glflex_active = ld_newgl_active.
267           IF ld_newgl_active NE abap_true.
268             MESSAGE w026(fagl_account_balance) WITH ld_ccode.
269             AUTHORITY-CHECK OBJECT 'S_TCODE'
270               ID    'TCD'
271               FIELD gc_hdb_subappl-s_classic_gl-line_item_browser.
272             IF sy-subrc = 0.
273               LEAVE TO
274                 TRANSACTION gc_hdb_subappl-s_classic_gl-line_item_browser.
275             ENDIF.
276
277           ENDIF.
278         ENDLOOP.
279   * PCA Line item browsers always used fixed ledger 8A
280       WHEN gc_s_hdb_ddic-pca_line_items
281         OR gc_s_hdb_ddic-pca_line_items_ext.
282         p_ledger = '8A'.
283       WHEN OTHERS.
284   * Classic GL, New GL entry view >> Use ledger 00
285         IF gd_subapplication <> gc_hdb_subappl-s_special_ledger-line_item_
    browser.
286           p_ledger = '00'.
287   * FI-SL browser >> Derive view name from ledger
288         ELSE.
289           CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
290             EXPORTING
291               id_rldnr           = p_ledger
292             IMPORTING
293               ed_tabname         = gd_sel_view
294             EXCEPTIONS
295               ledger_not_allowed = 1
296               table_not_allowed  = 2
297               view_not_generated = 3
298               OTHERS             = 4.
299           IF sy-subrc <> 0.
300             MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
301                     WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
302             LEAVE PROGRAM.
303           ENDIF.
```

```
304
305         ENDIF.
306     ENDCASE.
307
308   * Get DB connection and check authorizations based on sel screen
309   * restrictions
310     PERFORM dbcon_get
311       USING
312         isx_item
313         isx_kess  "n2571532
314         id_subapplication
315         id_hdb_is_primary
316       CHANGING
317         cd_sel_view
318         cd_dbcon_name
319         cd_exit.
320
321   * In case file is supposed to be created, make sure file name is specifi
      ed
322     IF  p_outfi = abap_true
323     AND p_dfile IS INITIAL.
324       MESSAGE e006(fagl_reporting_en).
325     ENDIF.
326
327   * Download to presentation server only possible in dialog mode
328     IF  p_outfi = abap_true
329     AND p_dpres = abap_true.
330       IF sscrfields-ucomm = 'PRIN'
331       OR sscrfields-ucomm = 'SJOB'
332       OR sy-batch = abap_true.
333         MESSAGE e009(fagl_reporting_en).
334       ENDIF.
335     ENDIF.
336
337   * Make sure some type of document is supposed to be selected.
338     IF  p_ty_nor = abap_false
339     AND p_ty_spg = abap_false
340     AND p_ty_nit = abap_false
341     AND p_ty_pit = abap_false
342     AND p_ty_ar  = abap_false
343     AND p_ty_ap  = abap_false.
344       MESSAGE e020(msitem).
345     ENDIF.
346
347     IF go_badi_lib IS NOT INITIAL.
348       CALL BADI go_badi_lib->add_fields
349         CHANGING
350           ct_fieldcat = lt_fieldcat.
351       IF lt_fieldcat IS NOT INITIAL.
352         MESSAGE i022(fagl_reporting_en)
353           WITH gd_sel_view.
354       ENDIF.
355     ENDIF.
356   ENDFORM.                    " CHECK_BEFORE_START
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F09 .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  FREE_SELECTIONS
6  *&---------------------------------------------------------------------*
7  FORM free_selections
8    USING
9      id_display_only                          "3140727
10   CHANGING
11     csx_free_sel              TYPE rsds_type
12     cd_free_sel_number        TYPE sytfill
13     cd_free_sel_curr_number   TYPE sytfill.
14 *---------------------------------------------------------------------*
15   STATICS st_excluded_fields  TYPE rsdsselopt_t.
16   STATICS ss_sel_view         TYPE rsdsqcat.
17   STATICS sd_dyn_sel_mode.
18   STATICS st_selview_info     TYPE fagl_t_sel_view_fields_visible.
19   STATICS sd_base_table       TYPE tabname.
20 *---------------------------------------------------------------------*
21   DATA lt_tables              TYPE STANDARD TABLE OF rsdstabs.
22   DATA ls_tables              TYPE rsdstabs.
23   DATA lt_fields              TYPE STANDARD TABLE OF rsdsfields.
24   DATA lt_fields_not          TYPE STANDARD TABLE OF rsdsfields.
25
26   DATA ld_selection_id        TYPE dynselid.
27
28   DATA ls_field               TYPE rsdsfields.
29
30   DATA ld_free_sel_number     TYPE sytfill.
31   DATA ld_display_only.
32   DATA ld_sel_view_x.
33   DATA ld_sel_view_fm         TYPE rs38l_fnam.
34   DATA ls_range               TYPE rsdsselopt.
35   DATA lt_hdb_range           TYPE hdb_t_range.
36   DATA ls_hdb_range           TYPE hdb_s_range.
37   DATA lt_or_selfields        TYPE se16n_or_t.
38   DATA ls_seltab              TYPE se16n_seltab.
39   DATA ls_selfields           TYPE se16n_selfields.
40   DATA ld_functional_group(2).
41   DATA lsx_table_field_ranges TYPE rsds_range.
42   DATA lsx_field_ranges       TYPE rsds_frange.
43   DATA lt_table_range         TYPE rsds_trange.              "n2748811
44   DATA lsx_multi              TYPE se16n_selfields_s_in.
45   DATA lt_multi_or_all        TYPE se16n_selfields_t_out.
46   DATA lt_or_mul_all          TYPE se16n_selfields_t_out.
47   DATA lt_selfields           TYPE se16n_selfields_t_in.
48   DATA ld_lines               TYPE i.
49   DATA ld_curtp               TYPE curtp.
50   DATA ld_sel_view            LIKE gd_sel_view.              "n2833350
51   DATA lt_presel              TYPE rsds_trange.              "n2871375
52 *---------------------------------------------------------------------*
53   FIELD-SYMBOLS <lsx_table_expressions>  TYPE rsds_expr.
54   FIELD-SYMBOLS <ls_expression>          TYPE rsdsexpr.
55   FIELD-SYMBOLS <lsx_table_field_ranges> TYPE rsds_range.
56   FIELD-SYMBOLS <lsx_field_ranges>       TYPE rsds_frange.
57
58   FIELD-SYMBOLS <lt_table> TYPE STANDARD TABLE.
59   FIELD-SYMBOLS <ls_table> TYPE any.
60   FIELD-SYMBOLS <lt_fields> TYPE STANDARD TABLE.
61   FIELD-SYMBOLS <ls_fields> TYPE any.
```

```
62    FIELD-SYMBOLS <ld_field> TYPE any.
63    FIELD-SYMBOLS <ls_selview_info> TYPE fagl_s_sel_view_fields_visible.
64    FIELD-SYMBOLS <lsx_or_selfields> TYPE se16n_or_seltab.
65    FIELD-SYMBOLS <lsx_multi_1> TYPE se16n_selfields_s_in.
66    FIELD-SYMBOLS <lsx_multi_n> TYPE se16n_selfields_s_in.
67  *---------------------------------------------------------------------*
68  * Remember number of free selections at this point
69    ld_free_sel_number = cd_free_sel_curr_number.
70
71  * Determine Selection View
72    IF ss_sel_view IS INITIAL.
73      PERFORM sel_view_check_get
74        USING
75          gd_sel_view
76        CHANGING
77          ss_sel_view
78          sd_base_table.
79    ENDIF.
80
81  *                                                    "begin "n3536365
82  ** Special logic for FAGLL03H (Entry View) to read the  "begin "n2833350
83  ** same settings as for FAGLL03H (G/L View) and not FBL3H
84  *  IF sy-repid = 'FAGL_LINE_ITEM_BROWSER_EV'.
85  *    CLEAR: ss_sel_view, sd_base_table.
86  *    IF gd_hdb_is_primary = abap_true.
87  *      ld_sel_view = gc_s_hdb_ddic-gl_view_ext.
88  *    ELSE.
89  *      ld_sel_view = gc_s_hdb_ddic-gl_view.
90  *    ENDIF.
91  *
92  *    PERFORM sel_view_check_get
93  *      USING
94  *        ld_sel_view
95  *      CHANGING
96  *        ss_sel_view
97  *        sd_base_table.
98  *  ENDIF.                                                "end "n2833350
99  *                                                      "end "n3536365
100
101 * Determine field information depending on ledger group
102   IF st_excluded_fields IS INITIAL
103     or gd_reload_sview = abap_true.
104
105     gd_reload_sview = abap_false.
106
107     if gd_cds_on = abap_true.
108       data(lv_cds_view) = gd_sel_view.
109     endif.
110
111     CALL FUNCTION 'FAGL_HDB_CUST_SVIEW_EXCL_FLDS'
112       EXPORTING
113         ed_appl            = gc_hdb_appl-financials
114         ed_subappl         = gd_subapplication
115         es_sel_view        = ss_sel_view
116         ev_cds_view        = lv_cds_view
117         ed_subappl_cont    = p_appl                        "n3544236
118         ed_ledger          = p_ledger                      "n3544236
119       IMPORTING
120         it_excl_fields_sel = st_excluded_fields
121         it_sel_fields      = st_selview_info
122       EXCEPTIONS
```

```
123          OTHERS             = 1.                                  "n3544236
124        IF sy-subrc <> 0.                                           "n3544236
125          RETURN.                                                   "n3544236
126        ENDIF.                                                      "n3544236
127
128        IF gv_lib_prctr_grp_select = abap_true
              "3031177
129        AND ( gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
              "3031177
130           OR gd_subapplication = gc_hdb_subappl-s_newgl-entry_view
              "3031177
131           OR gd_subapplication = gc_hdb_subappl-s_newgl-line_item_browser
              "3031177
132           OR gd_subapplication = gc_hdb_subappl-s_classic_gl-line_item_brow
    ser ). "3031177
133          DELETE st_selview_info WHERE fname = 'PRCTR'.
              "3031177
134        ENDIF.
              "3031177
135
136        IF gts_curtp IS INITIAL.
137          PERFORM get_curtp_info
138            USING
139              gd_sel_view
140              p_ledger
141              space
142            CHANGING
143              gts_curtp.
144        ENDIF.
145
146    * Reduce field list to relevant currency keys
147        LOOP AT st_selview_info
148          ASSIGNING <ls_selview_info>.
149          IF <ls_selview_info>-fname CS 'CURRKEY_'
150          OR <ls_selview_info>-fname CS 'CURRVAL_'.
151            ld_curtp = <ls_selview_info>-fname+8(2).
152            READ TABLE gts_curtp
153              WITH TABLE KEY
154                table_line = ld_curtp
155              TRANSPORTING NO FIELDS.
156            IF sy-subrc <> 0.
157              ls_range-sign   = 'I'.
158              ls_range-option = 'EQ'.
159              ls_range-low    = <ls_selview_info>-fname.
160              COLLECT ls_range
161                INTO st_excluded_fields.
162              <ls_selview_info>-visible_sel = abap_false.
163            ENDIF.
164          ENDIF.
165        ENDLOOP.
166
167    * Get settings for dynamic selections dialog
168        CALL FUNCTION 'HDB_RANGE_READ'
169          EXPORTING
170            i_application    = gc_hdb_appl-financials
171            i_subapplication = gd_subapplication
172            i_range_type     = gc_hdb_range_type-sel_screen_dynsel
173          IMPORTING
174            et_range         = lt_hdb_range.
175
176        LOOP AT lt_hdb_range
```

```
177         INTO ls_hdb_range.
178         sd_dyn_sel_mode = ls_hdb_range-low.
179       ENDLOOP.
180
181   * if selection is switched to CDS -> 'traditional' free selections canno
      t be used
182       if sd_dyn_sel_mode is not initial and gd_cds_on = abap_true.
183         clear sd_dyn_sel_mode.
184         loop at lt_hdb_range reference into data(lr_hdb_range).
185           clear lr_hdb_range->low.
186         endloop.
187         call function 'HDB_RANGE_SAVE'
188           exporting
189             i_application     = gc_hdb_appl-financials
190             i_subapplication  = gd_subapplication
191             i_range_type      = gc_hdb_range_type-sel_screen_dynsel
192             it_range          = lt_hdb_range.
193       endif.
194     ENDIF.
195
196     IF sd_dyn_sel_mode IS INITIAL.
197   * fill fields from previous free selections in case they were saved
198   * as part of the variant
199       LOOP AT csx_free_sel-trange
200         ASSIGNING <lsx_table_field_ranges>.
201         ls_field-tablename = <lsx_table_field_ranges>-tablename.
202         LOOP AT <lsx_table_field_ranges>-frange_t
203           ASSIGNING <lsx_field_ranges>.
204           ls_field-fieldname = <lsx_field_ranges>-fieldname.
205           COLLECT ls_field INTO lt_fields.
206         ENDLOOP.
207       ENDLOOP.
208
209       DELETE st_selview_info
210         WHERE visible_sel = space.
211
212       lsx_multi-pos = 1.
213       APPEND lsx_multi
214         TO lt_multi_or_all.
215       READ TABLE lt_multi_or_all
216         ASSIGNING <lsx_multi_1>
217         INDEX 1.
218
219       APPEND lsx_multi
220         TO lt_or_mul_all.
221       READ TABLE lt_or_mul_all
222         ASSIGNING <lsx_multi_n>
223         INDEX 1.
224
225       SORT st_selview_info BY numb scrtext_l.
226       LOOP AT st_selview_info
227         ASSIGNING <ls_selview_info>.
228         IF <ls_selview_info>-numb <> ld_functional_group.
229           ld_functional_group = <ls_selview_info>-numb.
230           CLEAR ls_selfields.
231           ls_selfields-scrtext_l = <ls_selview_info>-gtext.
232           ls_selfields-key = abap_true.
233           ls_selfields-input = 0.
234   *        APPEND ls_selfields
235   *          TO lt_selfields.
236           APPEND ls_selfields
```

```
237           TO <lsx_multi_1>-selfields.
238         CLEAR ls_selfields.
239       ENDIF.
240       MOVE-CORRESPONDING <ls_selview_info> TO ls_selfields.
241       ls_selfields-tabname   = sd_base_table.
242       ls_selfields-fieldname = <ls_selview_info>-fname.
243 *      APPEND ls_selfields
244 *        TO lt_selfields.
245       IF <lsx_table_field_ranges> IS ASSIGNED.
246         READ TABLE <lsx_table_field_ranges>-frange_t
247           ASSIGNING <lsx_field_ranges>
248           WITH KEY
249             fieldname = ls_selfields-fieldname.
250         IF sy-subrc = 0.
251           ld_lines = lines( <lsx_field_ranges>-selopt_t ).
252           LOOP AT <lsx_field_ranges>-selopt_t
253             INTO ls_range.
254             MOVE-CORRESPONDING ls_range
255               TO ls_selfields.
256             CASE sy-tabix.
257               WHEN 1.
258                 IF ld_lines > 1.
259                   ls_selfields-push = abap_true.
260                 ENDIF.
261                 APPEND ls_selfields
262                   TO <lsx_multi_1>-selfields.
263               WHEN OTHERS.
264                 APPEND ls_selfields
265                   TO <lsx_multi_n>-selfields.
266             ENDCASE.
267           ENDLOOP.
268         ELSE.
269           APPEND ls_selfields
270             TO <lsx_multi_1>-selfields.
271         ENDIF.
272       ELSE.
273         APPEND ls_selfields
274           TO <lsx_multi_1>-selfields.
275       ENDIF.
276       CLEAR ls_selfields.
277     ENDLOOP.
278
279     ls_tables-prim_tab = sd_base_table.
280
281     CALL FUNCTION 'SE16N_UT_GET_SELECT_CRITERIA'
282       EXPORTING
283         i_tab                = ls_tables-prim_tab
284         i_title_text         = text-001
285         i_key_field_by_caller = 'X'
286         i_display            = id_display_only "n2748811
287       CHANGING
288         et_or_selfields      = lt_or_selfields
289         et_multi_or_all      = lt_multi_or_all
290         et_or_mul_all        = lt_or_mul_all
291         it_selfields         = lt_selfields.
292
293     CLEAR csx_free_sel-trange.
294     lsx_table_field_ranges-tablename = ls_tables-prim_tab.
295     cd_free_sel_number = 0.
296     LOOP AT lt_or_selfields
297       ASSIGNING <lsx_or_selfields>.
```

```
298         SORT <lsx_or_selfields>-seltab BY field.
299         LOOP AT <lsx_or_selfields>-seltab
300           INTO ls_seltab.
301           AT NEW field.
302             lsx_field_ranges-fieldname = ls_seltab-field.
303             cd_free_sel_number = cd_free_sel_number + 1.
304           ENDAT.
305           MOVE-CORRESPONDING ls_seltab
306             TO ls_range.
307           APPEND ls_range
308             TO lsx_field_ranges-selopt_t.
309           AT END OF field.
310             APPEND lsx_field_ranges
311               TO lsx_table_field_ranges-frange_t.
312             CLEAR lsx_field_ranges.
313           ENDAT.
314         ENDLOOP.
315       ENDLOOP.
316       APPEND lsx_table_field_ranges
317         TO csx_free_sel-trange.
318
319       CALL FUNCTION 'FREE_SELECTIONS_RANGE_2_EX'
320         EXPORTING
321           field_ranges = csx_free_sel-trange
322         IMPORTING
323           expressions  = csx_free_sel-texpr.
324
325       CALL FUNCTION 'FREE_SELECTIONS_RANGE_2_WHERE'
326         EXPORTING
327           field_ranges  = csx_free_sel-trange
328         IMPORTING
329           where_clauses = csx_free_sel-clauses.
330
331     ELSE.
332
333       ls_tables-prim_tab = sd_base_table.
334       APPEND ls_tables TO lt_tables.
335
336   * fill fields from previous free selections in case they were saved
337   * as part of the variant
338       LOOP AT csx_free_sel-texpr                    "begin "n2124059
339         ASSIGNING <lsx_table_expressions>.
340         ls_field-tablename = <lsx_table_expressions>-tablename.
341         LOOP AT <lsx_table_expressions>-expr_tab
342           ASSIGNING <ls_expression>
343           WHERE fieldname <> space.
344           ls_field-fieldname = <ls_expression>-fieldname.
345           COLLECT ls_field INTO lt_fields.
346         ENDLOOP.
347       ENDLOOP.
348
349       LOOP AT csx_free_sel-trange
350         ASSIGNING <lsx_table_field_ranges>.
351         ls_field-tablename = <lsx_table_field_ranges>-tablename.
352         LOOP AT <lsx_table_field_ranges>-frange_t
353           ASSIGNING <lsx_field_ranges>.
354           ls_field-fieldname = <lsx_field_ranges>-fieldname.
355           COLLECT ls_field INTO lt_fields.
356         ENDLOOP.
357       ENDLOOP.                                      "end "n2124059
358
```

```
359      CALL FUNCTION 'FREE_SELECTIONS_INIT'
360        EXPORTING
361          kind                     = 'G'
362          field_ranges_int         = csx_free_sel-trange
363          field_groups_key         = ss_sel_view
364          alv                      = abap_true
365        IMPORTING
366          selection_id             = ld_selection_id
367          where_clauses            = csx_free_sel-clauses
368          expressions              = csx_free_sel-texpr
369          field_ranges             = csx_free_sel-trange
370          number_of_active_fields = cd_free_sel_curr_number
371        TABLES
372          tables_tab               = lt_tables
373          fields_tab               = lt_fields
374          fields_not_selected      = lt_fields_not
375  *       tabfields_not_display    = st_excluded_fields
376        EXCEPTIONS
377          OTHERS                   = 1.
378
379      IF sy-subrc <> 0.
380        MESSAGE e005(fagl_reporting_en) WITH space space space space.
381      ENDIF.
382
383      ASSIGN ('(SAPLSSEL)QUFIELDS[]') TO <lt_table>.
384      LOOP AT <lt_table>
385        ASSIGNING <ls_table>.
386        ASSIGN COMPONENT 'FIELDS'
387          OF STRUCTURE <ls_table>
388          TO  <lt_fields>.
389        LOOP AT <lt_fields>
390          ASSIGNING <ls_fields>.
391          ASSIGN COMPONENT 'FNAME'
392            OF STRUCTURE <ls_fields>
393            TO <ld_field>.
394          IF <ld_field> IN st_excluded_fields.
395            DELETE <lt_fields>.
396            CONTINUE.
397          ENDIF.
398        ENDLOOP.
399      ENDLOOP.
400
401      CALL FUNCTION 'FREE_SELECTIONS_DIALOG'
402        EXPORTING
403          selection_id             = ld_selection_id
404          title                    = text-001 "Dynamic Selections
405          just_display             = id_display_only
406          alv                      = abap_true
407        IMPORTING
408          where_clauses            = csx_free_sel-clauses
409          expressions              = csx_free_sel-texpr
410          field_ranges             = csx_free_sel-trange
411          number_of_active_fields = cd_free_sel_curr_number
412        TABLES
413          fields_tab               = lt_fields
414          fields_not_selected      = lt_fields_not
415        EXCEPTIONS
416          OTHERS                   = 0.
417    ENDIF.
418
419  * New total number of free selections is the previous number of free
```

```
420  * selections plus the new number of sels for current table minus
421  * previous number of sels for current table
422    cd_free_sel_number
423    = cd_free_sel_number
424    + cd_free_sel_curr_number
425    - ld_free_sel_number.
426
427  ENDFORM.                    " FREE_SELECTIONS
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F13 .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  REPORT_ASSIGN
6  *&---------------------------------------------------------------------*
7  FORM report_assign .
8  *---------------------------------------------------------------------*
9    DATA ls_rstirec             TYPE rstirec.
10 *---------------------------------------------------------------------*
11   ls_rstirec-rtool = 'RT'.
12   ls_rstirec-ronam = sy-repid.
13
14   CALL FUNCTION 'RSTI_REPORT_ADD'
15     EXPORTING
16       e_fccls  = '9'
17       e_tool   = 'RT'
18       e_report = ls_rstirec.
19
20 ENDFORM.                    " REPORT_ASSIGN
21 *&---------------------------------------------------------------------*
22 *&      Form  GET_TEXT
23 *&---------------------------------------------------------------------*
24 FORM get_text                                        "new since "n2318460
25   USING
26     id_acctp                  TYPE bseg-koart
27     id_account                TYPE bseg-hkont
28   CHANGING
29     cs_text                   TYPE ts_text.
30 *---------------------------------------------------------------------*
31   STATICS sth_text            TYPE tth_text.
32 *---------------------------------------------------------------------*
33   CLEAR cs_text.
34   READ TABLE sth_text
35     INTO cs_text
36     WITH TABLE KEY
37       acctp = id_acctp
38       account = id_account.
39   IF sy-subrc <> 0.
40     cs_text-acctp = id_acctp.
41     cs_text-account = id_account.
42     CASE id_acctp.
43       WHEN 'D'.
44         SELECT SINGLE name1 name2
45           FROM kna1
46           INTO (cs_text-txt_s, cs_text-txt_l)
47           WHERE kunnr = id_account.
48       WHEN 'K'.
49         SELECT SINGLE name1 name2
50           FROM lfa1
51           INTO (cs_text-txt_s, cs_text-txt_l)
52           WHERE lifnr = id_account.
53     ENDCASE.
54     INSERT cs_text
55       INTO TABLE sth_text.
56   ENDIF.
57 ENDFORM.
```

```
*---------------------------------------------------------------------*
***INCLUDE FAGL_LINE_ITEM_BROWSER_F20 .
*---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  LEDGER_VALUE_REQUEST
*&---------------------------------------------------------------------*
FORM ledger_value_request .
*---------------------------------------------------------------------*
  DATA lt_chosen_values       TYPE STANDARD TABLE OF sval.
*---------------------------------------------------------------------*
  CASE p_appl.
    WHEN gc_hdb_subappl-s_special_ledger-line_item_browser.
      PERFORM f4_ledger_browser
        CHANGING
          p_ledger.
    WHEN OTHERS.
      PERFORM choose_ledger
    TABLES
      lt_chosen_values
    USING
      p_ledger
    CHANGING
      p_ledger.
  SUPPRESS DIALOG.
  ENDCASE.

ENDFORM.                    "ledger_value_request
*&---------------------------------------------------------------------*
*&      Form  SUBMIT_RESTART
*&---------------------------------------------------------------------*
FORM submit_restart
  USING
    id_repid                  TYPE syrepid.
*---------------------------------------------------------------------*
  DATA ld_guid                TYPE sychar22.
  DATA lt_params              TYPE STANDARD TABLE OF rsparams.
  DATA ls_params              TYPE rsparams.
  DATA ld_no_ledger.                                        "n2184083
*---------------------------------------------------------------------*
  LOOP AT gt_guid_stack
    INTO ld_guid.
    DELETE FROM SHARED BUFFER rfdt(li)
    ID ld_guid.
  ENDLOOP.

  IF  sy-tcode          <> gd_subapplication                "n1920358
  AND sy-tcode          <> 'FAGLL03H'                       "n1920358
  AND gd_subapplication <> 'FAGL_BROWSE'.                   "n1920358
    LEAVE PROGRAM.                                          "n1920358
  ENDIF.                                                    "n1920358

  CALL FUNCTION 'RS_REFRESH_FROM_SELECTOPTIONS'
    EXPORTING
      curr_report     = sy-repid                            "n2184083
    TABLES
      selection_table = lt_params
    EXCEPTIONS
      OTHERS          = 1.

  IF sy-subrc <> 0.
    LEAVE PROGRAM.
```

```
62    ENDIF.
63
64    READ TABLE lt_params INTO ls_params                          "n2104752
65      WITH KEY selname = 'P_APPL'.                               "n2104752
66    ls_params-SIGN = 'I'.                                        "n2104752
67    ls_params-option = 'EQ'.                                     "n2104752
68    CASE id_repid.                                               "n2104752
69    WHEN 'FAGL_LINE_ITEM_BROWSER'.                               "n2104752
70      ls_params-low = gc_hdb_subappl-s_newgl-gl_view.            "n2104752
71        ld_no_ledger = abap_true.                                "n2184083
72      WHEN 'FAGL_LINE_ITEM_BROWSER_EV'.                          "n2104752
73        ls_params-low = gc_hdb_subappl-s_newgl-entry_view.       "n2104752
74        ld_no_ledger = abap_true.                                "n2184083
75    ENDCASE.                                                     "n2104752
76
77    MODIFY lt_params FROM ls_params INDEX sy-tabix.              "n2104752
78
79    IF ld_no_ledger = abap_true.                                 "n2184083
80      DELETE lt_params WHERE selname = 'P_LEDGER'.               "n2184083
81    ENDIF.                                                       "n2184083
82
83    SUBMIT (id_repid)
84      VIA SELECTION-SCREEN
85      WITH SELECTION-TABLE lt_params
86      WITH psx_item = psx_item
87      WITH psx_kess = psx_kess.
88
89  ENDFORM.                    " SUBMIT_RESTART
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F23.
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  CALL_HDBC_RESTRICTED
6  *&---------------------------------------------------------------------*
7  FORM call_hdbc_restricted
8    USING
9      id_subapplication         TYPE fbcon_s_hdb-subappl
10     id_hdb_is_primary         TYPE boole_d.
11 *---------------------------------------------------------------------*
12   DATA lt_ra_application      TYPE hdb_t_range.
13   DATA lt_ra_subapplication   TYPE hdb_t_range.
14   DATA ls_range               TYPE hdb_s_range.
15   DATA lt_exclude_ucomm       TYPE salv_dynpro_t_fcode.
16   DATA ld_cross_application   VALUE abap_true.
17   DATA ld_subapplication      TYPE fbcon_s_hdb-subappl.     "n3536365
18 *---------------------------------------------------------------------*
19   ls_range-sign   = 'I'.
20   ls_range-option = 'EQ'.
21   ls_range-low    = gc_hdb_appl-financials.
22   APPEND ls_range TO lt_ra_application.
23   CASE sy-cprog.                                          "begin "n3536365
24     WHEN 'FAGL_LINE_ITEM_BROWSER_EV'.
25       ld_subapplication = gc_hdb_subappl-s_classic_gl-line_item_browser.
26     WHEN OTHERS.
27       ld_subapplication = id_subapplication.
28   ENDCASE.
29   ls_range-low = ld_subapplication.                       "end "n3536365
30   APPEND ls_range TO lt_ra_subapplication.
31   IF id_hdb_is_primary = abap_true.
32     APPEND 'HDBC_TREE' TO lt_exclude_ucomm.
33     ld_cross_application = abap_false.
34   ENDIF.
35
36   CALL FUNCTION 'HDB_SETT_MAINTAIN'
37     EXPORTING
38       it_ra_application       = lt_ra_application
39       it_ra_subapplication    = lt_ra_subapplication
40       id_cross_application    = ld_cross_application
41       id_start_application    = gc_hdb_appl-financials
42       id_start_subapplication = ld_subapplication          "n3536365
43       id_tree_show            = abap_false
44       it_exclude_ucomm        = lt_exclude_ucomm.
45
46 ENDFORM.                    " CALL_HDBC_RESTRICTED
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FAGL_LINE_ITEM_BROWSER_F24.
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  MESSAGES_SHOW
6  *&---------------------------------------------------------------------*
7  FORM messages_show
8    USING
9      id_no_data.
10 *---------------------------------------------------------------------*
11   DATA ls_log                 TYPE bal_s_log.
12   DATA ld_log_handle          TYPE balloghndl.
13   DATA lt_log_handle          TYPE bal_t_logh.
14   DATA ls_message             TYPE bapiret2.
15   DATA ls_log_message         TYPE bal_s_msg.
16   DATA ls_profile             TYPE bal_s_prof.
17 *---------------------------------------------------------------------*
18   IF gt_message IS NOT INITIAL.
19     ls_log-object = 'HDB'.
20     ls_log-subobject = 'HDBS'.
21     ls_log-aldate    = sy-datum.
22     ls_log-altime    = sy-uzeit.
23     ls_log-aluser    = sy-uname.
24     ls_log-altcode   = sy-tcode.
25     ls_log-alprog    = sy-repid.
26
27     CALL FUNCTION 'BAL_LOG_CREATE'
28       EXPORTING
29         i_s_log      = ls_log
30       IMPORTING
31         e_log_handle = ld_log_handle.
32
33
34     LOOP AT gt_message
35       INTO  ls_message.
36       ls_log_message-msgty = ls_message-type.
37       ls_log_message-msgid = ls_message-id.
38       ls_log_message-msgno = ls_message-number.
39       ls_log_message-msgv1 = ls_message-message_v1.
40       ls_log_message-msgv2 = ls_message-message_v2.
41       ls_log_message-msgv3 = ls_message-message_v3.
42       ls_log_message-msgv4 = ls_message-message_v4.
43       CALL FUNCTION 'BAL_LOG_MSG_ADD'
44         EXPORTING
45           i_log_handle = ld_log_handle
46           i_s_msg      = ls_log_message.
47     ENDLOOP.
48
49     APPEND ld_log_handle
50       TO lt_log_handle.
51
52 * Prepare log
53     CALL FUNCTION 'BAL_DSP_PROFILE_NO_TREE_GET'
54       IMPORTING
55         e_s_display_profile = ls_profile.
56
57     ls_profile-title = sy-title.
58     IF sy-batch IS INITIAL.
59       ls_profile-use_grid   = abap_true.
60     ENDIF.
61
```

```
62      ls_profile-disvariant-report = sy-repid.
63      ls_profile-disvariant-handle = 'ERR'.
64
65      IF id_no_data = abap_false.
66
67        IF go_contain_msg IS INITIAL.
68          CREATE OBJECT go_contain_msg
69            EXPORTING
70              parent    = go_main_container
71              repid     = sy-repid
72              dynnr     = sy-dynnr
73              extension = 100
74              side      = cl_gui_docking_container=>dock_at_bottom.
75        ENDIF.
76        CALL FUNCTION 'BAL_CNTL_CREATE'
77          EXPORTING
78            i_container         = go_contain_msg
79            i_s_display_profile = ls_profile
80            i_t_log_handle      = lt_log_handle.
81      ELSE.
82        CALL FUNCTION 'BAL_DSP_LOG_DISPLAY'
83          EXPORTING
84            i_s_display_profile = ls_profile
85            i_t_log_handle      = lt_log_handle
86          EXCEPTIONS
87            OTHERS              = 0.
88
89      ENDIF.
90    ENDIF.
91
92
93  ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F25
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  FILENAME_VALUE_REQUEST
6  *&---------------------------------------------------------------------*
7  FORM filename_value_request
8    CHANGING
9      cd_filename               TYPE fagl_download_filename.
10 *---------------------------------------------------------------------*
11   DATA ld_filename            TYPE string.
12   DATA ld_path                TYPE string.
13   DATA ld_fullpath            TYPE string.
14   DATA ld_dpath               TYPE dxlpath.
15   DATA ld_ipath               TYPE dxlpath.
16 *---------------------------------------------------------------------*
17   if gv_ext_download_options = abap_true.
18     if p_dmxml = abap_true.
19       data(lv_default_extension) = |.xml|.
20       data(lv_default_filename) = |*.xml|.
21     else.
22       lv_default_extension = |.dat|.
23       lv_default_filename = |*.dat|.
24     endif.
25   endif.
26
27   CASE p_dpres.
28 * Presentation Server
29     WHEN abap_true.
30 * Get File Name
31       cl_gui_frontend_services=>file_save_dialog(
32         exporting
33           default_extension = lv_default_extension
34           default_file_name = lv_default_filename
35         CHANGING
36           filename = ld_filename
37           path     = ld_path
38           fullpath = ld_fullpath ).
39       IF ld_fullpath IS NOT INITIAL.
40         cd_filename = ld_fullpath.
41       ENDIF.
42 * Application Server
43     WHEN OTHERS.
44 * Get directory from validation file name
45       CALL FUNCTION 'FILE_GET_NAME'
46         EXPORTING
47           logical_filename = gc_check_file
48           parameter_1      = sy-repid
49           including_dir    = abap_true
50         IMPORTING
51           file_name        = ld_dpath
52         EXCEPTIONS
53           OTHERS           = 0.
54
55 * Let user choose file name
56       CALL FUNCTION 'F4_DXFILENAME_TOPRECURSION'
57         EXPORTING
58           i_location_flag = 'A'
59           i_path          = ld_dpath
60         IMPORTING
61           o_path          = ld_ipath.
```

```
62        IF ld_ipath IS NOT INITIAL.
63          cd_filename = ld_ipath.
64        ENDIF.
65
66    ENDCASE.
67  ENDFORM.                    " FILENAME_VALUE_REQUEST
68
69  FORM set_value_request                                  "begin of "n2869685
70    USING
71      id_field                  TYPE rgsbs-field
72    CHANGING
73      cd_set                    TYPE rgsbm-shortname.
74  *---------------------------------------------------------------------*
75    DATA ld_set                 TYPE rgsb4-setnr.
76    DATA ld_name                TYPE rgsbm-shortname.
77  *---------------------------------------------------------------------*
78
79    CALL FUNCTION 'G_RW_SET_SELECT'
80     EXPORTING
81       field_name                 = id_field
82       no_dynamic_sets            = 'X'
83       typelist                   = 'S'
84     IMPORTING
85       setid                      = ld_set
86       set_name                   = ld_name
87     EXCEPTIONS
88       error_message              = 1
89       OTHERS                     = 2.
90    IF SY-SUBRC <> 0.
91  * Implement suitable error handling here
92    ENDIF.
93
94    cd_set = ld_name.
95
96    CASE id_field.
97      WHEN 'BUKRS'.
98        p_setidb = ld_set.
99      WHEN 'RACCT'.
100       p_setidr = ld_set.
101     WHEN 'KUNNR'.
102       p_setidd = ld_set.
103     WHEN 'LIFNR'.
104       p_setidk = ld_set.
105   ENDCASE.
106
107 ENDFORM.                                                "end of "n2869685
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_F27
*&---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  ALV_LIST_DISPLAY
*&---------------------------------------------------------------------*
FORM alv_list_display .
*----------------------------------------------------------------------*
  DATA lt_fieldcat            TYPE slis_t_fieldcat_alv.
  DATA ls_fieldcat            TYPE slis_fieldcat_alv.
  DATA ls_fieldcat_grid       TYPE lvc_s_fcat.
*----------------------------------------------------------------------*

  LOOP AT gt_fieldcat
    INTO ls_fieldcat_grid
    WHERE no_out = space.
    MOVE-CORRESPONDING ls_fieldcat_grid
      TO ls_fieldcat.
    ls_fieldcat-seltext_l = ls_fieldcat_grid-scrtext_l.
    ls_fieldcat-seltext_m = ls_fieldcat_grid-scrtext_m.
    ls_fieldcat-seltext_s = ls_fieldcat_grid-scrtext_s.
    APPEND ls_fieldcat
      TO lt_fieldcat.
  ENDLOOP.


  CALL FUNCTION 'REUSE_ALV_LIST_DISPLAY'
    EXPORTING
      it_fieldcat = lt_fieldcat
    TABLES
      t_outtab    = <gt_table>
    EXCEPTIONS
      OTHERS      = 1.

  IF  sy-subrc NE 0
  AND sy-msgid IS NOT INITIAL.
    MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
            WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
  ENDIF.
ENDFORM.                    " ALV_LIST_DISPLAY
*&---------------------------------------------------------------------*
*&      Form  RRI_INIT
*&---------------------------------------------------------------------*
FORM rri_init .                                     "new since "n1920358
*----------------------------------------------------------------------*
  DATA ls_sel                 TYPE rstisel.
  DATA ls_sel_help            TYPE rstisel.                 "n3026074
  DATA lt_sel                 TYPE TABLE OF rstisel.
  DATA lt_field_s             TYPE STANDARD TABLE OF rstifields.
  DATA ls_field_s             LIKE rstifields.
  DATA lt_field_r             TYPE STANDARD TABLE OF rstifields.
  DATA ls_field_r             LIKE rstifields.
  DATA ls_a_rec               LIKE rstirec.
  DATA ld_rri_subrc           LIKE sy-subrc.
  DATA lt_field_info          TYPE STANDARD TABLE OF rsel_info.
  DATA ls_field_info          TYPE rsel_info.
  DATA ld_fdpos               TYPE syfdpos.
  DATA ld_table               TYPE tabname.
  DATA ld_field               TYPE fieldname.
  DATA lt_dfies               TYPE STANDARD TABLE OF dfies.
  DATA ls_dfies               TYPE dfies.
```

```
  DATA ld_range_name          TYPE fieldname.
  DATA ls_range               TYPE rsdsselopt.
  DATA lsx_trange             TYPE rsds_range.
  DATA lsx_frange             TYPE rsds_frange.
  DATA ld_keydo               TYPE budat.
  DATA ld_keydc               TYPE budat.
  DATA lt_ra_cdate            TYPE RANGE OF budat.
  DATA ld_subrc               TYPE sy-subrc.
  DATA ld_fs_version          TYPE versn_011.
  DATA ld_fs_item             TYPE ergsl.
  DATA lt_accounts            TYPE rfaccinf
                              OCCURS 0 WITH HEADER LINE.
  DATA lt_ra_racct            TYPE rsdsselopt_t.
  DATA ld_coa                 TYPE ktopl.
  DATA ld_xbilk_acc.
  DATA ld_xbilk_cnt           TYPE i.
  DATA ld_cumulated_value.
  DATA ls_a_sen               LIKE rstirec.                  "n2387729
  DATA ld_dspovr              TYPE boole_d                   "n2778804
                              VALUE abap_undefined.          "n2778804
  DATA lv_dspovr_settings_id    TYPE fagl_settings-param_name.  "3031504
  DATA lv_dspovr_settings_value TYPE fagl_settings-param_value. "3031504
*---------------------------------------------------------------------*
  FIELD-SYMBOLS <ls_range>    TYPE any.
  FIELD-SYMBOLS <lt_range>    TYPE STANDARD TABLE.
  FIELD-SYMBOLS <ld_value>    TYPE any.
*---------------------------------------------------------------------*
  FIELD-SYMBOLS <lsx_trange>  TYPE rsds_range.
  FIELD-SYMBOLS <lsx_frange>  TYPE rsds_frange.
*---------------------------------------------------------------------*

  CALL FUNCTION 'RSTI_APPL_STACK_POP'
    IMPORTING
      i_rec                     = ls_a_rec
      i_sen                     = ls_a_sen                   "n2387729
    EXCEPTIONS
      appl_stack_not_initialized = 1.

  "3031504: default display style in RRI is space
  IF sy-subrc = 0 AND ls_a_sen-ronam IS NOT INITIAL
    AND ls_a_sen-ronam <> 'FAGL_LINE_ITEM_BROWSER_AP'
    AND ls_a_sen-ronam <> 'FAGL_LINE_ITEM_BROWSER_AR'
    AND ls_a_sen-ronam <> 'FAGL_ACCOUNT_BALANCE'.
    CONCATENATE 'LIB_RRI_' ls_a_sen-ronam INTO lv_dspovr_settings_id.
    lv_dspovr_settings_value = abap_true.
    CALL FUNCTION 'FAGL_GET_FAGL_SETTINGS'
        EXPORTING
          id_param_name = lv_dspovr_settings_id
          id_defau      = lv_dspovr_settings_value
        IMPORTING
          ed_value      = lv_dspovr_settings_value.
    p_dspovr = lv_dspovr_settings_value.
  ENDIF.

  ld_rri_subrc = sy-subrc.
  IF ld_rri_subrc = 0.
* Receiver is this report
    IF NOT ( ( ls_a_rec-rtool = 'RT'
               AND ls_a_rec-ronam = sy-repid )
* Receiver is transaction code
          OR (     ls_a_rec-rtool = 'TR'
```

```
123  * Usually transaction code = sub-application
124                 AND (    ls_a_rec-ronam = gd_subapplication
125  * Exception: FAGLL03H - check tcode against program name
126                       OR ls_a_rec-ronam = 'FAGLL03H'
127                          AND sy-repid = 'FAGL_LINE_ITEM_BROWSER' ) ) ) .
128        ld_rri_subrc = 2.
129      ENDIF.
130    ENDIF.
131    IF ld_rri_subrc = 0.
132      CALL FUNCTION 'RSTI_SELECTION_IMPORT'
133        TABLES
134          it_sel            = lt_sel
135          it_fields         = lt_field_s
136        EXCEPTIONS
137          no_selection_data = 1
138          OTHERS            = 2.
139      IF sy-subrc <> 0.
140        CALL FUNCTION 'RSTI_APPL_STACK_INITIALIZE'
141          EXPORTING
142            e_tool = ls_a_rec-rtool
143            e_onam = ls_a_rec-ronam.
144        EXIT.
145      ENDIF.
146
147      LOOP AT lt_sel INTO ls_sel
148        WHERE sign   IS INITIAL
149          AND option IS INITIAL
150          AND low    IS INITIAL.
151        DELETE lt_sel.
152      ENDLOOP.
153
154  * deleted restrictions to USEDB, USEAR and USEAS
155      LOOP AT lt_sel INTO ls_sel
156        WHERE field = 'USEDB'
157           OR field = 'USEAR'
158           OR field = 'USEAS'.
159        DELETE lt_sel.
160      ENDLOOP.
161
162      CALL FUNCTION 'RS_REPORTSELECTIONS_INFO'
163        EXPORTING
164          report     = sy-repid
165        TABLES
166          field_info = lt_field_info.
167
168      LOOP AT lt_field_info
169        INTO  ls_field_info.
170  *   empty dbfield -> useless for RRI
171        CHECK NOT ls_field_info-dbfield IS INITIAL.
172        IF ls_field_info-dbfield CA '-'.
173  *   -> field is defined via table and fieldname
174          ld_fdpos = sy-fdpos + 1.
175          ld_table = ls_field_info-dbfield(sy-fdpos).
176          ld_field = ls_field_info-dbfield+ld_fdpos(*).
177          IF ld_table = 'SY'.
178            ld_table = 'SYST'.
179          ENDIF.
180  *     get field info for table + field
181          CALL FUNCTION 'DDIF_FIELDINFO_GET'
182            EXPORTING
183              tabname   = ld_table
```

```
184             fieldname = ld_field
185           TABLES
186             dfies_tab = lt_dfies
187           EXCEPTIONS
188             OTHERS    = 1.
189         IF sy-subrc <> 0.
190           CONTINUE. "don't append export tables
191         ENDIF.
192       ENDIF.
193 *   if major information missing -> skip field
194       LOOP AT lt_dfies
195         INTO  ls_dfies.
196         IF ls_dfies-domname   IS INITIAL
197         OR ls_dfies-rollname  IS INITIAL
198         OR ls_dfies-leng      IS INITIAL
199         OR ls_dfies-intlen    IS INITIAL
200         OR ls_dfies-inttype   IS INITIAL.
201           CONTINUE. "don't append export tables
202         ENDIF.
203 *   fill some missing fields
204         CLEAR ls_field_r.
205         ls_field_r-rfield   = ls_field_info-name.
206         ls_field_r-rollname = ls_dfies-rollname.
207         ls_field_r-domname  = ls_dfies-domname.
208         ls_field_r-kind     = ls_field_info-kind.
209         IF  ls_field_r-kind        = 'S'
210         AND ls_field_info-noselset = 'N'.
211           ls_field_r-kind = 'I'.
212         ENDIF.
213         IF NOT ls_field_info-obligatory IS INITIAL.
214           ls_field_r-oblig = 'X'.
215         ELSE.
216           CLEAR: ls_field_r-oblig.
217         ENDIF.
218 *   finally append export tables
219         APPEND ls_field_r TO lt_field_r.
220       ENDLOOP.
221     ENDLOOP.
222
223 * adjust available selscreen fields based on called LIB"begin "n2937701
224 * these fields are then handled as dynamic selections
225     CASE gd_sel_view.
226       WHEN gc_s_hdb_ddic-gl_view
227         OR gc_s_hdb_ddic-gl_view_ext
228         OR gc_s_hdb_ddic-entry_view
229         OR gc_s_hdb_ddic-gl_line_items.
230         "For FBL3H and FAGLL03H, S_CUST and S_VEND are not available
231         DELETE lt_field_r WHERE ( field = 'S_VEND' OR field = 'S_CUST' )
    .
232       WHEN gc_s_hdb_ddic-ap_line_items.
233         "For FBL1H, S_CUST and S_RACCT are not available (hidden)
234         DELETE lt_field_r WHERE ( field = 'S_CUST' OR field = 'S_RACCT'
    ).
235       WHEN gc_s_hdb_ddic-ar_line_items.
236         "For FBL5H, S_VEND and S_RACCT are not available (hidden)
237         DELETE lt_field_r WHERE ( field = 'S_VEND' OR field = 'S_RACCT'
    ).
238     ENDCASE.                                              "end "n2937701
239
240 * get field info for selection view
241     CALL FUNCTION 'DDIF_FIELDINFO_GET'
```

```
242         EXPORTING
243           tabname   = gd_sel_view
244         TABLES
245           dfies_tab = lt_dfies
246         EXCEPTIONS
247           OTHERS    = 0.
248
249       IF go_badi_lib IS NOT INITIAL.                "begin "n2387729
250         CALL BADI go_badi_lib->modify_rri_restrictions
251           EXPORTING
252             is_receiver          = ls_a_rec
253             is_sender            = ls_a_sen
254             it_fields_sender     = lt_field_s
255             it_fields_receiver   = lt_field_r
256             it_view_fields       = lt_dfies
257           CHANGING
258             ct_selections_sender = lt_sel
259             ctx_table_range      = psx_item-trange
260             cd_dspovr            = ld_dspovr.          "n2778804
261                                                        "n2778804
262         IF ld_dspovr <> abap_undefined.                "n2778804
263           p_dspovr = ld_dspovr.                        "n2778804
264         ENDIF.                                         "n2778804
265       ENDIF.
266       SORT lt_dfies BY rollname position.           "end "n2387729
267
268       SORT lt_field_s BY field.                              "b3008490
269       SORT lt_field_r BY rollname rfield DESCENDING.
270
271       ld_keydo    = p_keydo.
272       lt_ra_cdate = s_cdate[].
273       ld_keydc    = p_keydc.
274
275       LOOP AT lt_sel INTO ls_sel.
276   * Determine Comp Code
277         CASE ls_sel-field.
278           WHEN 'RLDNR'.
279   *         IF p_ledger IS INITIAL.                  "n2714238
280             IF ls_sel-low IS NOT INITIAL.            "n2714238
281               p_ledger = ls_sel-low.                 "n2714238
282             ENDIF.                                   "n2714238
283   *         ENDIF.                                   "n2714238
284           WHEN 'BUKRS'
285             OR 'RBUKRS'.
286             MOVE-CORRESPONDING ls_sel TO s_ccode.
287             COLLECT s_ccode.
288           WHEN 'KTOPL'
289             OR 'RKTPL'
290             OR 'VERSN'.
291             IF ld_coa IS INITIAL.
292               ld_coa = ls_sel-low.
293             ENDIF.
294   * Determine GL Accounts
295           WHEN 'RACCT'
296             OR 'SAKNR'
297             OR 'HKONT'.
298             MOVE-CORRESPONDING ls_sel TO s_racct.
299             COLLECT s_racct.
300   * Determine Posting Date
301   *       WHEN 'BUDAT'.
302   *         MOVE-CORRESPONDING ls_sel TO sd_budat.
```

```
303 *          APPEND sd_budat.
304 ** Determine Business Areas
305 *         WHEN 'GSBER'
306 *           OR 'BUSA'
307 *           OR 'RBUSA'.
308 *           MOVE-CORRESPONDING ls_sel TO so_gsber.
309 *           APPEND so_gsber.
310           WHEN 'P_OI'.                                    "begin "n2799848
311             IF ls_sel-low IS NOT INITIAL.
312               p_oi = abap_true.
313               p_ci = abap_false.
314               p_ai = abap_false.
315             ENDIF.
316           WHEN 'P_CI'.
317             IF ls_sel-low IS NOT INITIAL.
318               p_oi = abap_false.
319               p_ci = abap_true.
320               p_ai = abap_false.
321             ENDIF.
322           WHEN 'P_KEYDO'.
323             p_keydo = ls_sel-low.
324           WHEN 'P_KEYDC'.
325             p_keydc = ls_sel-low.                          "end "n2799848
326           WHEN 'SAK_PLUMI'
327           OR   'ERGSL'
328           OR   'SAKFB_LONG'.
329             IF ld_fs_version IS INITIAL.
330               ld_fs_version = ls_sel-hienm.
331             ENDIF.
332             IF NOT ld_fs_version IS INITIAL.
333               ld_fs_item = ls_sel-low.
334               CALL FUNCTION 'RGRE_ERGSL_TO_RACCT_CONVERT'
335                 EXPORTING
336                   i_bs_version         = ld_fs_version
337                   i_bs_item            = ld_fs_item
338                 TABLES
339                   t_accounts           = lt_accounts
340                 EXCEPTIONS
341                   bs_version_not_exist = 1
342                   OTHERS               = 2.
343               IF sy-subrc <> 0.
344 *               MESSAGE ID SY-MSGID TYPE SY-MSGTY NUMBER SY-MSGNO
345 *               WITH SY-MSGV1 SY-MSGV2 SY-MSGV3 SY-MSGV4.
346               ENDIF.
347
348               ls_range-sign   = 'I'.
349               ls_range-option = 'EQ'.
350               LOOP AT lt_accounts.
351                 ls_range-low = lt_accounts-acct_from.
352                 COLLECT ls_range
353                   INTO lt_ra_racct.
354               ENDLOOP.
355             ENDIF.
356 * Free selections or other fields
357           WHEN OTHERS.
358         READ TABLE lt_field_s
359           INTO ls_field_s
360           WITH KEY
361             field = ls_sel-field
362           BINARY SEARCH.
363
```

```
364         CHECK sy-subrc = 0.
365
366             CASE ls_field_s-rollname.
367               WHEN 'RPMAX'.
368                 ls_field_s-rollname = 'POPER'.
369               WHEN 'KDAUF'.                                        "n2937701
370                 "KDAUF is remapped to VBEL2 in generated views     "n2937701
371                 ls_field_s-rollname = 'VBELN_VA'.                  "n2937701
372             ENDCASE.
373
374             READ TABLE lt_field_r
375           INTO ls_field_r
376           WITH KEY
377             rollname = ls_field_s-rollname
378           BINARY SEARCH.
379             ld_subrc = sy-subrc.
380
381             CASE ls_field_s-rollname.
382               WHEN 'PRCTR'.
383                 CASE sy-repid.
384                   WHEN 'FAGL_LINE_ITEM_BROWSER_PCA'.
385                   WHEN OTHERS.
386                     ld_subrc = 4.
387                 ENDCASE.
388             ENDCASE.
389
390             CASE ld_subrc.
391           WHEN 0.
392             IF ls_field_r-kind = 'S'.
393               CONCATENATE ls_field_r-rfield '[]'
394                 INTO ld_range_name.
395               ASSIGN (ld_range_name)     TO <lt_range>.
396               CHECK sy-subrc = 0.
397   * If the field is not initial, the values have been supplied by the
398   * standard RRI functionality
399               IF <lt_range> IS INITIAL.                  "begin of "n2937701
400                 ASSIGN (ls_field_r-rfield) TO <ls_range>.
401                 IF sy-subrc = 0.
402                   MOVE-CORRESPONDING ls_sel TO <ls_range>.
403                   APPEND <ls_range>  TO <lt_range>.
404                 ELSE.
405   * Some fields are hidden on the selection screen ot the LIB
406   * but RRI shows them as available --> assign fails, dyn sel must be used
407                   "Append field to dynamic selection
408                   IF <lsx_frange> IS NOT ASSIGNED.
409                     IF psx_item-trange IS INITIAL.
410                       lsx_trange-tablename = gd_sel_view.
411                       APPEND lsx_trange TO psx_item-trange.
412                     ENDIF.
413                     READ TABLE psx_item-trange
414                       ASSIGNING <lsx_trange>
415                       INDEX 1.
416                     ASSIGN lsx_frange TO <lsx_frange>.
417                   ENDIF.
418
419                   IF <lsx_frange>-fieldname <> ls_dfies-fieldname.
420                     READ TABLE <lsx_trange>-frange_t
421                       ASSIGNING <lsx_frange>
422                       WITH KEY fieldname = ls_dfies-fieldname.
423                     IF sy-subrc <> 0.
424                       CLEAR lsx_frange.
```

```
425                     lsx_frange-fieldname = ls_dfies-fieldname.
426                     APPEND lsx_frange TO <lsx_trange>-frange_t.
427                     READ TABLE <lsx_trange>-frange_t
428                       ASSIGNING <lsx_frange>
429                       INDEX sy-tabix.
430                   ENDIF.
431                 ENDIF.
432                 MOVE-CORRESPONDING ls_sel TO ls_range.
433                 COLLECT ls_range  INTO <lsx_frange>-selopt_t.
434               ENDIF.
435             ELSE.
436               "Parameters have already been passed
437               "Merge everything together
438               ASSIGN (ls_field_r-rfield) TO <ls_range>.
439               IF sy-subrc = 0.
440                 MOVE-CORRESPONDING ls_sel TO <ls_range>.
441                 APPEND <ls_range> TO <lt_range>.
442               ENDIF.
443             ENDIF.                                          "end of "n2937701
444           ELSE.
445             ASSIGN (ls_field_r-rfield) TO <ld_value>.
446             CHECK sy-subrc = 0.
447 * If the field is not initial, the values have been supplied by the
448 * standard RRI functionality
449             IF <ld_value> IS INITIAL.
450               <ld_value> = ls_sel-low.
451             ENDIF.
452           ENDIF.
453         WHEN OTHERS.
454           READ TABLE lt_dfies
455             INTO ls_dfies
456             WITH KEY
457               rollname = ls_field_s-rollname
458             BINARY SEARCH.
459           IF sy-subrc = 0.
460 * Do not apply any restrictions based on currency keys unless the
461 * currency type is 00 or 0D. The different Currency Types can be
462 * displayed in additional columns. If the user adds the necessary
463 * column, they will see the correct value - even if it is zero.
464 * When calling from FAGLB03, the field name will be SO_WAERS - field
465 * name WAERS indicates that this is a generic call via RRI
466               IF ls_sel-field = 'WAERS'.                    "begin "n3026074
467                 READ TABLE lt_sel
468                   INTO ls_sel_help
469                   WITH KEY
470                     field = 'CURTP'.
471                 CHECK sy-subrc = 0.
472
473                 IF ls_sel_help-low = '00'
474                 OR ls_sel_help-low = '0D'.
475                 ELSE.
476                   CONTINUE.
477                 ENDIF.
478               ENDIF.                                        "end "n3026074
479
480             IF <lsx_frange> IS NOT ASSIGNED.
481               IF psx_item-trange IS INITIAL.
482                     lsx_trange-tablename = gd_sel_view.
483                     APPEND lsx_trange
484                       TO psx_item-trange.
485                 ENDIF.
```

```
486                 READ TABLE psx_item-trange
487                   ASSIGNING <lsx_trange>
488                   INDEX 1.
489                   ASSIGN lsx_frange TO <lsx_frange>.
490               ENDIF.
491               IF <lsx_frange>-fieldname <> ls_dfies-fieldname.
492                 READ TABLE <lsx_trange>-frange_t
493                   ASSIGNING <lsx_frange>
494                   WITH KEY
495                     fieldname = ls_dfies-fieldname.
496                 IF sy-subrc <> 0.
497                   CLEAR lsx_frange.
498                   lsx_frange-fieldname = ls_dfies-fieldname.
499                   APPEND lsx_frange TO <lsx_trange>-frange_t.
500                   READ TABLE <lsx_trange>-frange_t
501                     ASSIGNING <lsx_frange>
502                     INDEX sy-tabix.
503                 ENDIF.
504               ENDIF.
505               MOVE-CORRESPONDING ls_sel TO ls_range.
506               COLLECT ls_range
507                 INTO <lsx_frange>-selopt_t.
508             ENDIF.
509         ENDCASE.
510         ENDCASE.
511       ENDLOOP.
512
513   * If there are not account restrictions, use restrictions from
514   * Financial Statement Version (if there are any)
515       IF s_racct[] IS INITIAL.
516         SELECT SINGLE COUNT(*)
517           FROM ska1                                          "#EC CI_GENBUFF
518           INTO ld_xbilk_cnt
519           WHERE ktopl =  ld_coa
520           AND   saknr IN lt_ra_racct
521           AND   xbilk =  abap_true.
522         IF sy-subrc = 0.
523           ld_xbilk_acc = abap_true.
524         ENDIF.
525
526   * Rewritten: Determine if a cumulated display is needed
527   * determine kumsl for drilldown reporting
528         CLEAR ld_cumulated_value.
529         LOOP AT lt_sel
530           INTO ls_sel
531           WHERE field = 'KUMSL'.
532           DELETE lt_sel.
533         ENDLOOP.
534         IF sy-subrc NE 0.
535           LOOP AT lt_sel
536             INTO ls_sel
537             WHERE field = '&KKENNZAHL'.
538             IF   ls_sel-low = 'KUMSL'
539               OR ( ls_sel-low = 'BILWERT'
540                       AND ld_xbilk_acc = abap_true )
541               OR ls_sel-low = 'KUMSOLL'
542               OR ls_sel-low = 'KUMHABEN'.
543               ld_cumulated_value = abap_true.
544             ENDIF.
545           ENDLOOP.
546         ELSE.
```

```
547           ld_cumulated_value = abap_true.
548         ENDIF.
549
550         LOOP AT lt_ra_racct
551           INTO ls_range.
552           MOVE-CORRESPONDING ls_range
553             TO s_racct.
554           COLLECT s_racct.
555         ENDLOOP.
556       ENDIF.
557
558       IF  ld_keydo <> p_keydo
559       AND p_keydo IS NOT INITIAL.
560         p_oi = abap_true.
561         p_ci = abap_false.
562         p_ai = abap_false.
563       ELSEIF      lt_ra_cdate <> s_cdate[]
564             AND  s_cdate[]   IS NOT INITIAL
565       OR          ld_keydc    <> p_keydc
566             AND  p_keydc     IS NOT INITIAL.
567         p_oi = abap_false.
568         p_ci = abap_true.
569         p_ai = abap_false.
570       ELSE.
571         p_oi = abap_false.
572         p_ci = abap_false.
573         p_ai = abap_true.
574         IF s_pdate[] IS INITIAL.
575           IF ld_cumulated_value = abap_true.
576             LOOP AT s_ryear.
577               s_ryear-option = 'BT'.
578               s_ryear-high   = s_ryear-low.
579               s_ryear-low    = '1950'.
580               MODIFY s_ryear.
581             ENDLOOP.
582             LOOP AT s_period.
583               s_period-option = 'BT'.
584               IF s_period-high IS INITIAL.
585                 s_period-high = s_period-low.
586               ENDIF.
587               s_period-low = '001'.
588               MODIFY s_period.
589             ENDLOOP.
590           ENDIF.
591         ENDIF.
592       ENDIF.
593
594       PERFORM sync_items_to_selection_screen. "N3380814
595       PERFORM sync_selection_screen_to_kess.  "N3380814
596
597     ENDIF.
598   ENDFORM.                    " RRI_INIT
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_F28
*&---------------------------------------------------------------------*
*&---------------------------------------------------------------------*
*&      Form  SEL_VIEW_CHECK_GET
*&---------------------------------------------------------------------*
*----------------------------------------------------------------------*
FORM sel_view_check_get
  USING
    id_sel_view               TYPE tabname
  CHANGING
    cs_sel_view               TYPE rsdsqcat
    cd_base_table             type tabname.
*----------------------------------------------------------------------*
  DATA ls_tables              TYPE rsdstabs.
  DATA lt_tables              TYPE STANDARD TABLE OF rsdstabs.
  DATA ld_sel_view_x.
  DATA ld_sel_view_fm         TYPE rs38l_fnam.
  DATA ls_sel_view            TYPE rsdsqcat.

  DATA lt_dd26v               TYPE STANDARD TABLE OF dd26v.
  DATA ls_dd26v               TYPE dd26v.
  DATA lt_fields              TYPE STANDARD TABLE OF rsdsqfn.
  DATA ls_fields              TYPE rsdsqfn.
  DATA lt_groups              TYPE STANDARD TABLE OF rsdsqgx.
*----------------------------------------------------------------------*

  CASE id_sel_view.
    when if_fagl_lib_cds_util=>c_view_n_gl
      or if_fagl_lib_cds_util=>c_view_c_gl
      or if_fagl_lib_cds_util=>c_view_c_ar
      or if_fagl_lib_cds_util=>c_view_c_ap.
*     no selection views for CDS
      cs_sel_view-origin = 'SAP'.
      cs_sel_view-name = id_sel_view.
      cd_base_table = id_sel_view && '_PROXY'.
      return.
    WHEN gc_s_hdb_ddic-gl_view.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-gl_view.
    WHEN gc_s_hdb_ddic-entry_view.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-entry_view
.
    WHEN gc_s_hdb_ddic-gl_view_ext.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-gl_view_ex
t.
    WHEN gc_s_hdb_ddic-gl_line_items.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-gl_line_it
ems.
    WHEN gc_s_hdb_ddic-ar_line_items.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-ar_line_it
ems.
    WHEN gc_s_hdb_ddic-ap_line_items.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-ap_line_it
ems.
    WHEN gc_s_hdb_ddic-pca_line_items.
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-pca_line_i
tems.
    WHEN gc_s_hdb_ddic-pca_line_items_ext.                  "n2250571
      ls_sel_view-name = cs_sel_view-name = gc_s_hdb_ddic_sel-pca_line_i
tems_ext. "n2250571
    WHEN OTHERS.
```

```
55        CALL FUNCTION 'DDIF_VIEW_GET'
56          EXPORTING
57            name      = id_sel_view
58          TABLES
59            dd26v_tab = lt_dd26v
60          EXCEPTIONS
61            OTHERS    = 1.
62
63        IF sy-subrc > 0
64        OR lines( lt_dd26v ) > 1.
65          ls_sel_view-name = cs_sel_view-name = id_sel_view.
66  * Implement suitable error handling here
67        ELSE.
68          READ TABLE lt_dd26v
69            INTO ls_dd26v
70            INDEX 1.
71          ls_sel_view-name = cs_sel_view-name = ls_dd26v-tabname.
72        ENDIF.
73
74    ENDCASE.
75  * Get settings from HDBC
76    CALL FUNCTION 'FAGL_HDB_CUST_BRW_SELVIEW_GET'
77      EXPORTING
78        id_appl         = gc_hdb_appl-financials
79        id_subappl      = gd_subapplication
80        id_default_view = cs_sel_view-name
81      IMPORTING
82        ed_sel_view     = cs_sel_view-name
83        ed_sel_view_x   = ld_sel_view_x
84        ed_sel_view_fm  = ld_sel_view_fm.
85    IF ld_sel_view_x = abap_false.
86  * Check whether FM can be used
87      CALL FUNCTION 'FAGL_HDB_CUST_BRW_SELVIEW_CHCK'
88        EXPORTING
89          id_appl        = gc_hdb_appl-financials
90          id_subappl     = gd_subapplication
91          id_sel_view_fm = ld_sel_view_fm
92        EXCEPTIONS
93          OTHERS         = 1.
94      IF sy-subrc = 0.
95  * Get Selection View from FM
96        CALL FUNCTION ld_sel_view_fm
97          EXPORTING
98            id_appl     = gc_hdb_appl-financials
99            id_subappl  = gd_subapplication
100         IMPORTING
101           ed_sel_view = cs_sel_view-name.
102     ENDIF.
103   ENDIF.
104 * Selection View could not be determined >> use standard Selection View
105   IF cs_sel_view-name IS INITIAL
106 * In case HDB is primary and there is no customer defined SelView:
107 * use default.
108   OR (     gd_hdb_is_primary = abap_true
109        AND cs_sel_view-name(1) NA 'YZ' ).
110     CASE id_sel_view.
111       WHEN gc_s_hdb_ddic-gl_view.
112         cs_sel_view-name = ls_sel_view-name.
113       WHEN gc_s_hdb_ddic-entry_view.
114         cs_sel_view-name = ls_sel_view-name.
115       WHEN gc_s_hdb_ddic-gl_view_ext.
```

```
116           cs_sel_view-name = ls_sel_view-name.
117         WHEN gc_s_hdb_ddic-gl_line_items.
118           cs_sel_view-name = ls_sel_view-name.
119         WHEN gc_s_hdb_ddic-ar_line_items.
120           cs_sel_view-name = ls_sel_view-name.
121         WHEN gc_s_hdb_ddic-ap_line_items.
122           cs_sel_view-name = ls_sel_view-name.
123         WHEN gc_s_hdb_ddic-pca_line_items.
124           cs_sel_view-name = ls_sel_view-name.
125         WHEN OTHERS.
126           cs_sel_view-name = ls_sel_view-name.
127       ENDCASE.
128     ENDIF.
129
130   * Determine whether SAP or Customer Selection View
131     IF cs_sel_view-name(1) CA 'YZ'.
132       cs_sel_view-origin = 'CUS'.
133     ELSE.
134       cs_sel_view-origin = 'SAP'.
135     ENDIF.
136
137     CALL FUNCTION 'RS_READ_SEL_OPTIONS'
138       EXPORTING
139         key         = cs_sel_view
140       TABLES
141         field_names = lt_fields
142         func_groups = lt_groups
143       EXCEPTIONS
144         OTHERS      = 1.
145
146     CASE sy-subrc.
147       WHEN 0.
148         READ TABLE lt_fields
149           INTO ls_fields
150           INDEX 1.
151
152         ls_tables-prim_tab = ls_fields-tab.
153         cd_base_table = ls_fields-tab.
154     APPEND ls_tables TO lt_tables.
155
156     CALL FUNCTION 'FREE_SELECTIONS_INIT'
157       EXPORTING
158         kind             = 'G'
159         field_groups_key = cs_sel_view
160       TABLES
161         tables_tab       = lt_tables
162       EXCEPTIONS
163         OTHERS           = 1.
164
165
166       WHEN OTHERS.
167     ENDCASE.
168     CASE sy-subrc.
169       WHEN 0.
170         RETURN.
171       WHEN OTHERS.
172         cs_sel_view-origin = 'SAP'.
173         CASE id_sel_view.
174           WHEN gc_s_hdb_ddic-gl_view.
175             cs_sel_view-name = gc_s_hdb_ddic_sel-gl_view.
176           WHEN gc_s_hdb_ddic-entry_view.
```

```
177           cs_sel_view-name = gc_s_hdb_ddic_sel-entry_view.
178         WHEN gc_s_hdb_ddic-gl_view_ext.
179           cs_sel_view-name = gc_s_hdb_ddic_sel-gl_view_ext.
180         WHEN gc_s_hdb_ddic-gl_line_items.
181           cs_sel_view-name = gc_s_hdb_ddic_sel-gl_line_items.
182         WHEN gc_s_hdb_ddic-ar_line_items.
183           cs_sel_view-name = gc_s_hdb_ddic_sel-ar_line_items.
184         WHEN gc_s_hdb_ddic-ap_line_items.
185           cs_sel_view-name = gc_s_hdb_ddic_sel-ap_line_items.
186         WHEN gc_s_hdb_ddic-pca_line_items.
187           cs_sel_view-name = gc_s_hdb_ddic_sel-pca_line_items.
188         WHEN gc_s_hdb_ddic-pca_line_items_ext.
189           cs_sel_view-name = gc_s_hdb_ddic_sel-pca_line_items_ext.
190         WHEN OTHERS.
191           cs_sel_view-name = ls_sel_view-name.
192       ENDCASE.
193   ENDCASE.
194
195 ENDFORM.                    " SEL_VIEW_CHECK_GET
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F34
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  GET_CURTP_INFO
6  *&---------------------------------------------------------------------*
7  FORM get_curtp_info
8    USING
9      id_sel_view               TYPE tabname
10     id_ledger                 TYPE rfbila_sel-ledger
11     id_global_ledger          TYPE rcomp_tab
12   CHANGING
13     cts_curtp                 TYPE tts_curtp.
14 *---------------------------------------------------------------------*
15   DATA ls_fagl_org_info       TYPE fagl_org_info.
16   DATA lt_fagl_org_info       TYPE STANDARD TABLE OF fagl_org_info.
17 *---------------------------------------------------------------------*
18
19 * Determine relevant currency fields
20   CASE id_sel_view.
21     WHEN gc_s_hdb_ddic-entry_view
22       OR gc_s_hdb_ddic-gl_line_items
23       OR gc_s_hdb_ddic-ar_line_items
24       OR gc_s_hdb_ddic-ap_line_items
25       or if_fagl_lib_cds_util=>c_view_c_gl
26       or if_fagl_lib_cds_util=>c_view_c_ar
27       or if_fagl_lib_cds_util=>c_view_c_ap.
28 * GL View: NewGL Entry View or Classic GL
29 * Customer / Vendor View
30 * >> Information is contained in FAGL_ORG_INFO_CT
31       SELECT DISTINCT curtp
32         FROM fagl_org_infc_ct                              "#EC CI_BYPASS
33         INTO TABLE cts_curtp.
34     WHEN OTHERS.
35       IF id_global_ledger = abap_true.
36         SELECT DISTINCT curtp
37           FROM fagl_org_infg_ct                            "#EC CI_BYPASS
38           INTO TABLE cts_curtp
39           WHERE rldnr = id_ledger.
40       ELSE.
41 * All others
42 * >> Information is contained in FAGL_ORG_INFO_CT
43       SELECT DISTINCT curtp
44         FROM fagl_org_info_ct                              "#EC CI_BYPASS
45         INTO TABLE cts_curtp
46         WHERE rldnr = id_ledger.
47       ENDIF.
48   ENDCASE.
49
50 ENDFORM.
51 *&---------------------------------------------------------------------*
52 *&      Form  GET_EXTENDED_SEL
53 *&---------------------------------------------------------------------*
54 FORM get_context
55   CHANGING
56     cd_subapplication         TYPE hdb_subapplication
57     ctx_item                  TYPE rsds_trange
58     ctx_kess                  TYPE rsds_trange
59     co_badi_lib               TYPE REF TO fagl_lib.
60 *---------------------------------------------------------------------*
61   ctx_item = psx_item-trange.
```

```
62    ctx_kess = psx_kess-trange.
63    cd_subapplication = gd_subapplication.
64    co_badi_lib = go_badi_lib.
65  ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F36
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  GROUP_VALUE_REQUEST
6  *&---------------------------------------------------------------------*
7  FORM group_value_request
8    using
9      id_setclass               type setclass
10     id_fieldname              type fieldname
11   CHANGING
12     cd_group                  TYPE grpname.
13 *---------------------------------------------------------------------*
14   DATA ld_field               LIKE rgsbs-field.
15   DATA ld_table               LIKE rgsbs-table.
16   DATA lt_dynpfields          TYPE STANDARD TABLE OF dynpread.
17   DATA ls_dynpfields          TYPE dynpread.
18
19   DATA ld_coarea              LIKE tka01-kokrs.
20 *---------------------------------------------------------------------*
21   PERFORM get_table_field_from_class(saplgsac)
22     USING
23       id_setclass
24     CHANGING
25       ld_table
26       ld_field.
27
28   ls_dynpfields-fieldname = 'S_COAREA-LOW'.
29   APPEND ls_dynpfields
30     TO lt_dynpfields.
31   ls_dynpfields-fieldname = id_fieldname.
32   APPEND ls_dynpfields
33     TO lt_dynpfields.
34
35   CALL FUNCTION 'DYNP_VALUES_READ'
36     EXPORTING
37       dyname     = sy-repid
38       dynumb     = sy-dynnr
39     TABLES
40       dynpfields = lt_dynpfields
41     EXCEPTIONS
42       OTHERS     = 1.
43   IF sy-subrc > 0.
44     CHECK sy-msgno IS NOT INITIAL.
45     MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
46             WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
47     RETURN.
48   ENDIF.
49
50   LOOP AT lt_dynpfields
51     INTO  ls_dynpfields.
52     CASE ls_dynpfields-fieldname.
53       WHEN 'S_COAREA-LOW'.
54         ld_coarea = ls_dynpfields-fieldvalue.
55       WHEN id_fieldname.
56         cd_group = ls_dynpfields-fieldvalue.
57     ENDCASE.
58
59   ENDLOOP.
60
61   CALL FUNCTION 'K_GROUP_SELECT'
```

```
62      EXPORTING
63        class              = id_setclass
64        field_name         = ld_field
65        searchfld_required = ' '
66        set                = cd_group
67        table              = ld_table
68        kokrs              = ld_coarea
69      IMPORTING
70        set_name           = cd_group
71      EXCEPTIONS
72        OTHERS             = 1.
73
74    IF sy-subrc <> 0.
75      MESSAGE s016(fagl_reporting_en).
76    ENDIF.
77
78  ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F37
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  SETVAL_FROM_GROUP
6  *&---------------------------------------------------------------------*
7  FORM setval_from_group
8    USING
9      id_setclass               TYPE setclass
10     id_parameter              TYPE fieldname
11     id_msgty                  type symsgty
12   CHANGING
13     ct_ra_range               TYPE rsds_selopt_t.
14 *---------------------------------------------------------------------*
15   STATICS st_frange           TYPE rsds_frange_t.
16 *---------------------------------------------------------------------*
17   DATA lt_coarea              TYPE STANDARD TABLE OF kokrs.
18   DATA ld_coarea              TYPE kokrs.
19   DATA ls_info                TYPE grphinfo.
20   DATA ld_overwrite.
21   DATA lt_nodes               TYPE gseth_node_tab.
22   DATA ls_nodes               TYPE gseth_node_line.
23   DATA lt_values              TYPE gseth_val_tab.
24   DATA ls_values              TYPE gseth_val_line.
25   DATA ld_lines               TYPE i.
26   DATA ld_setid               LIKE sethier-setid.
27   DATA ls_range               TYPE rsdsselopt.
28   DATA lsx_frange             TYPE rsds_frange.
29   DATA ld_fieldname           TYPE fieldname.
30 *---------------------------------------------------------------------*
31   FIELD-SYMBOLS <ld_group>    TYPE grpname.
32   FIELD-SYMBOLS <lsx_frange>  TYPE rsds_frange.
33 *---------------------------------------------------------------------*
34 * Check whether parameter exists in this context
35   ASSIGN (id_parameter) TO <ld_group>.
36   IF sy-subrc <> 0.
37     RETURN.
38   ENDIF.
39
40 * Derive set values only if group value is specified
41   CHECK <ld_group> IS NOT INITIAL.
42
43 * Check whether set has been read already
44   CONCATENATE id_setclass <ld_group>
45     INTO ld_fieldname
46     SEPARATED BY '-'.
47   READ TABLE st_frange
48     ASSIGNING <lsx_frange>
49     WITH KEY
50     fieldname = ld_fieldname.
51
52 * Set has been read already >> use available information
53   IF sy-subrc = 0.
54     ct_ra_range = <lsx_frange>-selopt_t.
55 * This is the first time this set is accessed
56 * >> Derive set values
57   ELSE.
58     CLEAR ct_ra_range.
59     SELECT kokrs
60       FROM tka01
61       INTO TABLE lt_coarea
```

```
62        WHERE kokrs IN s_coarea.
63
64    * Make sure CO Area information is unique
65        ld_lines = lines( lt_coarea ).
66        IF ld_lines <> 1.
67          MESSAGE s017(fagl_reporting_en)
68            DISPLAY LIKE 'E'.
69          RETURN.
70        ENDIF.
71
72        READ TABLE lt_coarea
73          INTO ld_coarea
74          INDEX 1.
75
76    * Get technical set key
77        CALL FUNCTION 'G_SET_ENCRYPT_SETID'
78          EXPORTING
79            setclass  = id_setclass
80            shortname = <ld_group>
81            kokrs     = ld_coarea
82          IMPORTING
83            setid     = ld_setid
84          EXCEPTIONS
85            OTHERS    = 1.
86
87        IF sy-subrc <> 0.
88          CHECK sy-msgno IS NOT INITIAL.
89          MESSAGE ID sy-msgid TYPE id_msgty NUMBER sy-msgno
90            WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4
91            DISPLAY LIKE 'E'.
92          lsx_frange-fieldname = ld_fieldname.
93          lsx_frange-selopt_t = ct_ra_range.
94          INSERT lsx_frange
95            INTO TABLE st_frange.
96          RETURN.
97        ENDIF.
98
99    * Read set values
100       CALL FUNCTION 'K_HIERARCHY_TABLES_READ'
101         EXPORTING
102           e_class     = id_setclass
103           e_setid     = ld_setid
104           e_kokrs     = ld_coarea
105         TABLES
106           t_nodes     = lt_nodes
107           t_values    = lt_values
108         CHANGING
109           c_info      = ls_info
110           c_overwrite = ld_overwrite
111         EXCEPTIONS
112           OTHERS      = 1.
113
114       IF sy-subrc <> 0.
115         CHECK sy-msgno IS NOT INITIAL.
116         MESSAGE ID sy-msgid TYPE id_msgty NUMBER sy-msgno
117           WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4
118           DISPLAY LIKE 'E'.
119         lsx_frange-fieldname = ld_fieldname.
120         lsx_frange-selopt_t = ct_ra_range.
121         INSERT lsx_frange
122           INTO TABLE st_frange.
```

```
123         RETURN.
124       ENDIF.
125
126   * Transfer set values to selection table
127       ls_range-sign   = 'I'.
128       LOOP AT lt_values
129         INTO  ls_values.
130         IF ls_values-vto IS NOT INITIAL.     "3039680
131           ls_range-option = 'BT'.            "3039680
132         ELSE.                                "3039680
133           ls_range-option = 'EQ'.            "3039680
134         ENDIF.                               "3039680
135         ls_range-low = ls_values-vfrom.      "3039680
136         ls_range-high = ls_values-vto.       "3039680
137         COLLECT ls_range
138           INTO ct_ra_range.
139       ENDLOOP.
140
141   * Add information to stack
142       lsx_frange-fieldname = ld_fieldname.
143       lsx_frange-selopt_t = ct_ra_range.
144       INSERT lsx_frange
145         INTO TABLE st_frange.
146
147     ENDIF.
148
149   ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F44
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  F4_LEDGER_BROWSER
6  *&---------------------------------------------------------------------*
7  FORM f4_ledger_browser
8    CHANGING
9      cd_ledger                TYPE rldnr.
10 *---------------------------------------------------------------------*
11   DATA lt_allowed_tables      TYPE STANDARD TABLE OF rgall_tab.
12   DATA ls_allowed_tables      TYPE rgall_tab.
13   DATA ld_appl                LIKE t800a-appl.
14   DATA ld_subappl             LIKE t800a-subappl.
15   DATA ld_only_fixed_ledgers  LIKE t881-fix.
16   DATA ld_wdependent_ledgers  LIKE t881-depld.
17   DATA ld_only_free_ledgers   LIKE t881-fix.
18   DATA ld_help_text_t881t     LIKE t881t-name.
19   DATA ld_ledger_tab          TYPE gltab.
20   DATA ls_ledger_info         TYPE t881.
21   DATA ld_old_table           TYPE gltab.
22   DATA ls_tab_info            TYPE t800a.
23   DATA ld_ledger              TYPE rldnr.
24
25   DATA lt_excluded_fields     TYPE rsdsselopt_t.
26   DATA ls_range               TYPE rsdsselopt.
27   DATA ls_sel_view            TYPE rsdsqcat.
28
29   DATA lt_field               TYPE rsfsfieldst.
30   DATA ld_field               TYPE fieldname.
31   DATA lt_dfies               TYPE STANDARD TABLE OF dfies.
32   DATA ls_dfies               TYPE dfies.
33   DATA ld_curtp               TYPE curtp.
34   DATA ld_base_table          TYPE tabname.
35 *---------------------------------------------------------------------*
36
37   IF gd_ledger IS NOT INITIAL.
38     CALL FUNCTION 'G_GET_LEDGER_INFO'
39       EXPORTING
40         i_rldnr       = gd_ledger
41       IMPORTING
42         e_ledger_info = ls_ledger_info.
43
44     CALL FUNCTION 'G_GET_TABLE_INFO'
45       EXPORTING
46         i_tab     = ls_ledger_info-tab
47       IMPORTING
48         e_si_info = ls_tab_info.
49
50     ld_old_table = ls_tab_info-tab.
51   ENDIF.
52
53   CALL FUNCTION 'G_SUMTABLE_AND_MODE_GIVE'
54     EXPORTING
55       i_tcode                  = 'GD20'
56     IMPORTING
57       e_appl                   = ld_appl
58       e_subappl                = ld_subappl
59       e_only_fixed_ledgers     = ld_only_fixed_ledgers
60       e_with_dependent_ledgers = ld_wdependent_ledgers
61       e_only_free_ledgers      = ld_only_free_ledgers
```

```
62      TABLES
63        t_allowed_tables         = lt_allowed_tables.
64
65    CALL FUNCTION 'G_DISPLAY_LEDGERS_FOR_TABLE'
66      EXPORTING
67        gappl                  = ld_appl
68        gsubappl               = ld_subappl
69        only_fixed_ledgers     = ld_only_fixed_ledgers
70        with_dependent_ledgers = ld_wdependent_ledgers
71        only_free_ledgers      = ld_only_free_ledgers
72      IMPORTING
73        picked_ledger          = ld_ledger
74        picked_ledger_tab      = ld_ledger_tab
75        picked_ledger_name     = ld_help_text_t881t
76      TABLES
77        allowed_tables         = lt_allowed_tables
78      EXCEPTIONS
79        no_ledger_found        = 1
80        OTHERS                 = 2.
81    IF sy-subrc <> 0.
82      MESSAGE ID sy-msgid TYPE sy-msgty NUMBER sy-msgno
83              WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
84    ENDIF.
85    CHECK ld_ledger_tab IS NOT INITIAL.
86    cd_ledger = ld_ledger.
87
88    CALL FUNCTION 'G_GET_TABLE_INFO'
89      EXPORTING
90        i_tab     = ld_ledger_tab
91      IMPORTING
92        e_si_info = ls_tab_info.
93
94    IF ls_tab_info-tab <> ld_old_table.
95      CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
96        EXPORTING
97          id_rldnr           = cd_ledger
98        IMPORTING
99          ed_tabname         = gd_sel_view
100       EXCEPTIONS
101         ledger_not_allowed = 1
102         table_not_allowed  = 2
103         view_not_generated = 3
104         OTHERS             = 4.
105     IF sy-subrc <> 0.
106       MESSAGE ID sy-msgid TYPE 'I' NUMBER sy-msgno
107               WITH sy-msgv1 sy-msgv2 sy-msgv3 sy-msgv4.
108       LEAVE PROGRAM.
109     ENDIF.
110
111     gr_screen->set_table( i_tablename = gd_sel_view ) .
112
113 * Determine Selection View
114     PERFORM sel_view_check_get
115       USING
116         gd_sel_view
117       CHANGING
118         ls_sel_view
119         ld_base_table.
120
121 * Determine field information depending on ledger group
122     CALL FUNCTION 'FAGL_HDB_CUST_SVIEW_EXCL_FLDS'
```

```
123         EXPORTING
124           ed_appl            = gc_hdb_appl-financials
125           ed_subappl         = gd_subapplication
126           es_sel_view        = ls_sel_view
127         IMPORTING
128           it_excl_fields_sel = lt_excluded_fields
129         EXCEPTIONS
130           OTHERS             = 0.
131
132       LOOP AT lt_excluded_fields
133         INTO ls_range.
134         ld_field = ls_range-low.
135         COLLECT ld_field
136           INTO  lt_field.
137       ENDLOOP.
138
139       IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_bro
      wser.
140         CALL FUNCTION 'G_GET_LEDGER_INFO'
141           EXPORTING
142             i_rldnr       = p_ledger
143           IMPORTING
144             e_ledger_info = ls_ledger_info
145           EXCEPTIONS
146             OTHERS        = 0.
147
148         CALL FUNCTION 'G_GET_TABLE_INFO'
149           EXPORTING
150             i_tab      = ls_ledger_info-tab
151           IMPORTING
152             e_tab_info = ls_tab_info
153           EXCEPTIONS
154             OTHERS     = 0.
155       ENDIF.
156
157       PERFORM get_curtp_info
158         USING
159           gd_sel_view
160           p_ledger
161           ls_tab_info-comptab
162         CHANGING
163           gts_curtp.
164
165       CALL FUNCTION 'DDIF_NAMETAB_GET'
166         EXPORTING
167           tabname   = 'FISL_S_CURRENCY_VALUE'
168         TABLES
169           dfies_tab = lt_dfies.
170
171       LOOP AT lt_dfies
172         INTO  ls_dfies.
173         ld_curtp = ls_dfies-fieldname+8(2).
174         READ TABLE gts_curtp
175           WITH TABLE KEY
176             table_line = ld_curtp
177           TRANSPORTING NO FIELDS.
178         IF sy-subrc <> 0.
179           COLLECT ls_dfies-fieldname
180             INTO lt_field.
181         ENDIF.
182       ENDLOOP.
```

```
183
184       gr_screen->set_excluded_so( i_tablename  = gd_sel_view
185                                   it_fieldname = lt_field    ).
186
187     ENDIF.
188
189
190   ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_F45
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  LEDGER_FROM_SELSCREEN
6  *&---------------------------------------------------------------------*
7  FORM ledger_from_selscreen
8    CHANGING
9      cd_ledger                TYPE rldnr.
10 *---------------------------------------------------------------------*
11   DATA lt_fields             TYPE STANDARD TABLE OF dynpread.
12   DATA ls_fields             TYPE dynpread.
13 *---------------------------------------------------------------------*
14   ls_fields-fieldname = 'P_LEDGER'.
15   APPEND ls_fields
16     TO lt_fields.
17   CALL FUNCTION 'DYNP_VALUES_READ'
18     EXPORTING
19       dyname     = sy-repid
20       dynumb     = sy-dynnr
21     TABLES
22       dynpfields = lt_fields.
23
24   READ TABLE lt_fields
25     INTO ls_fields
26     WITH KEY
27       fieldname = 'P_LEDGER'.
28   IF  sy-subrc = 0
29   AND ls_fields-fieldvalue IS NOT INITIAL.
30     cd_ledger = ls_fields-fieldvalue.
31   ELSE.
32     MESSAGE s503(fr).
33     EXIT.
34   ENDIF.
35
36 ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *& Include          FAGL_LINE_ITEM_BROWSER_F50
3  *&---------------------------------------------------------------------*
4  FORM apar_branch_extension.
5    DATA:
6      " user setting
7      lv_fit_branch(2)   TYPE c,
8      lv_branch_active   TYPE boole_d,
9
10     " address selection
11     ls_select_addr     LIKE addr1_sel,
12     ls_branch          LIKE addr1_val,
13     ls_head_office     LIKE addr1_val,
14
15     " master data
16     ls_lfa1            LIKE lfa1,
17     ls_kna1            LIKE kna1,
18
19     lt_lfb1            TYPE STANDARD TABLE OF lfb1,
20     lt_knb1            TYPE STANDARD TABLE OF knb1,
21
22     " additional selection
23     ls_head_office_add TYPE rsdsselopt.
24
25   FIELD-SYMBOLS: <lfb> LIKE lfb1,
26                  <knb> LIKE knb1.
27
28   " check application
29   CHECK gd_subapplication = gc_hdb_subappl-s_receivables-line_item_brows
   er
30       OR gd_subapplication = gc_hdb_subappl-s_payables-line_item_browser.
31
32   " check FIT_BRANCH [space,X] condition
33   GET PARAMETER ID 'FIT_BRANCH' FIELD lv_fit_branch.
34   CHECK NOT ( lv_fit_branch+1(1) = 'X' AND lv_fit_branch(1) <> 'X' ).
35
36   " prepare additional selection
37   ls_head_office_add-sign   = 'I'.
38   ls_head_office_add-option = 'EQ'.
39
40   " extend vendor selection
41   IF s_vend[] IS NOT INITIAL.
42     SELECT lifnr bukrs lnrze
43       FROM lfb1
44       INTO CORRESPONDING FIELDS OF TABLE lt_lfb1
45       WHERE lifnr IN s_vend[]
46         AND lnrze NE ''
47         AND lnrze NOT IN s_vend[]
48         AND bukrs IN s_ccode[].
49
50     LOOP AT lt_lfb1 ASSIGNING <lfb>.
51       " check additions -> only I|EQ|low
52       READ TABLE s_vend[]
53         WITH KEY sign = 'I' option = 'EQ' low = <lfb>-lnrze
54         TRANSPORTING NO FIELDS.
55       CHECK sy-subrc <> 0.
56
57       " check user setting
58       IF lv_fit_branch+1(1) = 'X'.
59         lv_branch_active = lv_fit_branch(1).
60       ELSE.
```

```
61
62          " parse branch
63          SELECT SINGLE name1 adrnr
64            FROM lfa1
65            INTO CORRESPONDING FIELDS OF ls_lfa1
66            WHERE lifnr = <lfb>-lifnr.
67
68          IF sy-subrc = 0.
69            ls_select_addr-addrnumber = ls_lfa1-adrnr.
70            CALL FUNCTION 'ADDR_GET'
71              EXPORTING
72                address_selection = ls_select_addr
73              IMPORTING
74                address_value     = ls_branch
75              EXCEPTIONS
76                parameter_error   = 1
77                OTHERS            = 2.
78          ENDIF.
79
80          " parse head office
81          SELECT SINGLE name1 adrnr
82            FROM lfa1
83            INTO CORRESPONDING FIELDS OF ls_lfa1
84            WHERE lifnr = <lfb>-lnrze.
85
86          IF sy-subrc = 0.
87            ls_select_addr-addrnumber = ls_lfa1-adrnr.
88            CALL FUNCTION 'ADDR_GET'
89              EXPORTING
90                address_selection = ls_select_addr
91              IMPORTING
92                address_value     = ls_head_office
93              EXCEPTIONS
94                parameter_error   = 1
95                OTHERS            = 2.
96          ENDIF.
97
98          " show pop-up
99          CALL FUNCTION 'FI_ITEMS_BRANCH_CENTRAL'
100           EXPORTING
101             id_branch_acct   = <lfb>-lifnr
102             id_branch_name1  = ls_branch-name1
103             id_central_acct  = <lfb>-lnrze
104             id_central_name1 = ls_head_office-name1
105             id_bukrs         = <lfb>-bukrs
106           IMPORTING
107             eb_central_items = lv_branch_active.
108       ENDIF.
109
110       " add head office to selection
111       IF lv_branch_active = 'X'.
112         ls_head_office_add-low    = <lfb>-lnrze.
113         APPEND ls_head_office_add TO s_vend[].
114       ENDIF.
115     ENDLOOP.
116   ENDIF.
117
118   " extend customer selection
119   IF s_cust[] IS NOT INITIAL.
120     SELECT kunnr knrze bukrs
121       FROM knb1
```

```
122         INTO CORRESPONDING FIELDS OF TABLE lt_knb1
123         WHERE kunnr IN s_cust[]
124           AND knrze NE ''
125           AND knrze NOT IN s_cust[]
126           AND bukrs IN s_ccode[].
127
128       LOOP AT lt_knb1 ASSIGNING <knb>.
129         " check additions -> only I|EQ|low
130         READ TABLE s_cust[]
131           WITH KEY sign = 'I' option = 'EQ' low = <knb>-knrze
132           TRANSPORTING NO FIELDS.
133         CHECK sy-subrc <> 0.
134
135         " check user setting
136         IF lv_fit_branch+1(1) = 'X'.
137           lv_branch_active = lv_fit_branch(1).
138         ELSE.
139           " parse branch
140           SELECT SINGLE name1 adrnr
141             FROM kna1
142             INTO CORRESPONDING FIELDS OF ls_kna1
143             WHERE kunnr = <knb>-kunnr.
144
145           IF sy-subrc = 0.
146             ls_select_addr-addrnumber = ls_kna1-adrnr.
147             CALL FUNCTION 'ADDR_GET'
148               EXPORTING
149                 address_selection = ls_select_addr
150               IMPORTING
151                 address_value     = ls_branch
152               EXCEPTIONS
153                 parameter_error   = 1
154                 OTHERS            = 2.
155           ENDIF.
156
157           " parse head office
158           SELECT SINGLE name1 adrnr
159             FROM kna1
160             INTO CORRESPONDING FIELDS OF ls_kna1
161             WHERE kunnr = <knb>-knrze.
162
163           IF sy-subrc = 0.
164             ls_select_addr-addrnumber = ls_kna1-adrnr.
165             CALL FUNCTION 'ADDR_GET'
166               EXPORTING
167                 address_selection = ls_select_addr
168               IMPORTING
169                 address_value     = ls_head_office
170               EXCEPTIONS
171                 parameter_error   = 1
172                 OTHERS            = 2.
173           ENDIF.
174
175           " show pop-up
176           CALL FUNCTION 'FI_ITEMS_BRANCH_CENTRAL'
177             EXPORTING
178               id_branch_acct   = <knb>-kunnr
179               id_branch_name1  = ls_branch-name1
180               id_central_acct  = <knb>-knrze
181               id_central_name1 = ls_head_office-name1
182               id_bukrs         = <knb>-bukrs
```

```
183            IMPORTING
184              eb_central_items = lv_branch_active.
185        ENDIF.
186
187        IF lv_branch_active = 'X'.
188          ls_head_office_add-low    = <knb>-knrze.
189          APPEND ls_head_office_add TO s_cust[].
190        ENDIF.
191      ENDLOOP.
192    ENDIF.
193
194  ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *& Include          FAGL_LINE_ITEM_BROWSER_GPC
3  *&---------------------------------------------------------------------*
4  *** Note 3031177: Profit Center Group Selection
5  *   - activation via FAGL_SETTINGS -> LIB_PRCTR_GRP_SELECT
6
7  *** Check & convert profit center group input
8  form selection_screen_prctr.
9    check p_pcgrp is not initial.
10
11 * Check alternatives
12   if  p_pcgrp is not initial
13   and s_rprctr is not initial.
14     message e016(kb).
15   endif.
16
17   perform check_coarea.
18
19 * Get profit centers for group
20   perform setval_from_group
21     using
22       gc_s_setclass-pc_group
23       'P_PCGRP'
24       'S'
25     changing
26       gt_ra_prctr[].
27 endform.
28
29 form selection_screen_racct.
30   check p_acgrp is not initial.
31
32 * Check alternatives
33   if p_acgrp  is not initial
34   and s_racct is not initial.
35     message e016(kb).
36   endif.
37
38   perform check_coarea.
39
40 * get accounts for group
41   perform setval_from_group
42     using
43       gc_s_setclass-acct_group
44       'P_ACGRP'
45       'S'
46     changing
47       gt_ra_racct[].
48 endform.
49
50 form check_coarea.
51   data lt_coarea type standard table of kokrs.
52
53   select kokrs
54     from tka01
55     into table lt_coarea
56     where kokrs in s_coarea.
57
58   if sy-subrc <> 0.
59     message e019(kb).
60   elseif lines( lt_coarea ) > 1.
61     select kokrs from tka02 into table lt_coarea where kokrs in s_coarea
```

```
     and bukrs in s_ccode.
62      if sy-subrc = 0 and lines( lt_coarea ) = 1.
63        clear s_coarea.
64        append value #( sign = 'I' option = 'EQ' low = lt_coarea[ 1 ] ) to
     s_coarea.
65      else.
66        message e017(fagl_reporting_en).
67      endif.
68    endif.
69  endform.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_P01
3  *&---------------------------------------------------------------------*
4  form main.
5  * set up new call
6    check p_ty_spg is not initial
7       or p_ty_nit is not initial
8       or p_ty_pit is not initial
9       or p_ty_nor is not initial
10      or p_ty_ap  is not initial
11      or p_ty_ar  is not initial.
12
13   clear gt_pivb_param.
14
15 * Get all selection criteria (collected in psx_item at this point)
16   if psx_item is not initial.
17     loop at psx_item-trange assigning field-symbol(<trange>).
18       append lines of <trange>-frange_t to gt_seltab.
19     endloop.
20   endif.
21
22 * Set up layout
23   perform get_layout.
24
25 * Selection and display of data
26   perform display_data.
27
28 endform.
29
30
31 *&---------------------------------------------------------------------*
32 *&  GET_LAYOUT
33 *&    -> set layout from selection screen
34 *&     -> if not available, load default layout
35 *&      -> if default cannot be loaded, create default
36 *&     -> or use ad-hoc layout
37 *&      -> if ad-hoc is not defined or does no contain any visible field
38 *&       -> default layout
39 *&---------------------------------------------------------------------*
40 form get_layout.
41 * Choose the default layout if no layout is specified
42   if p_layout is not initial.
43     gd_variant = p_layout.
44     return.
45   else.
46     data(ls_variant) = value disvariant(
47       report = sy-repid
48       handle = gc_handle_main
49       log_group = cond #( when gd_subapplication = gc_hdb_subappl-s_spec
   ial_ledger-line_item_browser then p_ledger ) ).
50
51     call function 'REUSE_ALV_VARIANT_DEFAULT_GET'
52       exporting
53         i_save     = 'A'
54       changing
55         cs_variant = ls_variant
56       exceptions
57         others     = 1.
58
59     if sy-subrc <> 0.
60       message s000(pivb)
```

```
 61          with 'Error loading default layout' 'generating new layout'. "#E
    C NOTEXT
 62      else.
 63        gd_variant = ls_variant-variant.
 64        return.
 65      endif.
 66    endif.
 67
 68  * create default?
 69    if  ( gd_variant is initial and gt_column is initial )
 70     or ( gd_variant = 'AD-HOC' and gt_column is initial )
 71     or ( gd_variant = 'AD-HOC' and not line_exists( gt_column[ is_visible
     = abap_true ] ) ).
 72
 73      ls_variant-variant = '/DEFAULT'.
 74
 75      call function 'LVC_VARIANT_EXISTENCE_CHECK'
 76        changing
 77          cs_variant = ls_variant
 78        exceptions
 79          others     = 4.
 80
 81      if sy-subrc = 0.
 82        gd_variant = ls_variant-variant.
 83        return.
 84      endif.
 85
 86      types: begin of ts_field_pos,
 87               field type fieldname,
 88               pos   type i,
 89             end of ts_field_pos,
 90             tt_field_pos type standard table of ts_field_pos with empty k
    ey.
 91
 92      data lt_default_fields type tt_field_pos.
 93      data lt_fieldcat type lvc_t_fcat.
 94      data lt_sort type lvc_t_sort.
 95      data lt_filter type lvc_t_filt.
 96
 97      case p_appl.
 98        when gc_hdb_subappl-s_newgl-gl_view
 99          or gc_hdb_subappl-s_newgl-line_item_browser.
100          lt_default_fields = value #( ( field = 'RLDNR' pos = 1 ) ( field
     = 'BUKRS' pos = 2 ) ( field = 'HKONT' pos = 3 ) ).
101        when gc_hdb_subappl-s_newgl-entry_view
102          or gc_hdb_subappl-s_classic_gl-line_item_browser.
103          lt_default_fields = value #( ( field = 'BUKRS' pos = 1 ) ( field
     = 'HKONT' pos = 2 ) ).
104        when gc_hdb_subappl-s_receivables-line_item_browser.
105          lt_default_fields = value #( ( field = 'BUKRS' pos = 1 ) ( field
     = 'KUNNR' pos = 2 ) ).
106        when gc_hdb_subappl-s_payables-line_item_browser.
107          lt_default_fields = value #( ( field = 'BUKRS' pos = 1 ) ( field
     = 'LIFNR' pos = 2 ) ).
108        when gc_hdb_subappl-s_special_ledger-line_item_browser.
109          lt_default_fields = value #( ( field = 'RBUKRS' pos = 1 ) ( fiel
    d = 'RACCT' pos = 2 ) ).
110        when gc_hdb_subappl-s_pca-line_item_browser.
111          lt_default_fields = value #( ( field = 'KOKRS' pos = 1 ) ( field
     = 'RPRCTR' pos = 2 ) ).
112        when others.
```

```
113     endcase.
114
115     loop at lt_default_fields reference into data(lr_field).
116       append value #( spos = lr_field->pos fieldname = lr_field->field u
    p = abap_true  ) to lt_sort.
117     endloop.
118     append lines of value tt_field_pos( ( field = 'CURRKEY_10' pos = 4 )
     ( field = 'CURRVAL_10' pos = 5 ) ( field = 'COUNTER' pos = 6 ) ) to lt_
    default_fields.
119
120     call function 'LVC_FIELDCATALOG_MERGE'
121       exporting
122         i_structure_name = gd_sel_view
123       changing
124         ct_fieldcat      = lt_fieldcat.
125
126     loop at lt_fieldcat assigning field-symbol(<fcat>).
127       read table lt_default_fields with key field = <fcat>-fieldname ref
    erence into lr_field.
128       if sy-subrc = 0.
129         <fcat>-no_out = abap_false.
130         <fcat>-col_pos = lr_field->pos.
131       else.
132         <fcat>-no_out = abap_true.
133       endif.
134       if <fcat>-fieldname = 'CURRVAL_10' or <fcat>-fieldname = 'COUNTER'
    .
135         <fcat>-do_sum = abap_true.
136         <fcat>-no_sum = abap_false.
137       endif.
138     endloop.
139
140     data(ls_layout) = value lvc_s_layo( sel_mode = 'A' zebra = abap_true
     cwidth_opt = abap_true totals_bef = abap_true ).
141
142     call function 'LVC_VARIANT_SAVE'
143       exporting
144         it_fieldcat           = lt_fieldcat
145         it_sort               = lt_sort
146         it_filter             = lt_filter
147         is_layout             = ls_layout
148         i_dialog              = ' '
149         i_overwrite           = ' '
150         i_customer_name_check = ' '
151       changing
152         cs_variant            = ls_variant
153       exceptions
154         variant_exists        = 1
155         others                = 2.
156
157     if ( sy-subrc = 2 ).
158       data(pivb_param) = value pivb_param( paramname = 'GEN_LAYOUT' ).
159
160       loop at lt_default_fields reference into lr_field.
161         append value #( fieldname = lr_field->field
162                         is_visible = abap_true
163                         fieldposition = lr_field->pos
164                         do_sum = cond #( when lr_field->field cs 'CURRVA
    L' then abap_true ) )
165           to gt_column.
166
```

```
167           append value #( fieldname = lr_field->field seqnr = lr_field->po
      s )
168             to pivb_param-content.
169         endloop.
170
171         append pivb_param to gt_pivb_param.
172       else.
173         gd_variant = ls_variant-variant.
174       endif.
175
176     endif.
177   endform.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_P02
3  *&---------------------------------------------------------------------*
4  * Taken from the PIVB SFLIGHT example
5  FORM convert_to_seltab
6    USING
7      id_fname                      TYPE rsdstabs-prim_fname
8      it_table                      TYPE ANY TABLE
9    CHANGING
10     ct_seltab                     TYPE rsds_frange_t.
11 *---------------------------------------------------------------------*
12   CALL FUNCTION 'PIVB_CONV_RANGE_TO_SELTAB'
13     EXPORTING
14       i_fname   = id_fname
15       it_table  = it_table
16     CHANGING
17       ct_seltab = ct_seltab.
18
19 ENDFORM.
20 *---------------------------------------------------------------------*
21
22 *---------------------------------------------------------------------*
23 * Dynamic field addition (e.g. for KE5ZH)
24 *---------------------------------------------------------------------*
25 FORM convert_to_seltab_dyn
26   USING
27     id_fname                      TYPE rsdstabs-prim_fname
28     id_tabname                    TYPE string
29   CHANGING
30     ct_seltab                     TYPE rsds_frange_t.
31 *---------------------------------------------------------------------*
32   FIELD-SYMBOLS <lt_table>        TYPE STANDARD TABLE.
33 *---------------------------------------------------------------------*
34   ASSIGN (id_tabname) TO <lt_table>.
35   IF sy-subrc = 0.
36     PERFORM convert_to_seltab
37       USING
38         id_fname
39         <lt_table>
40       CHANGING
41         ct_seltab.
42   ENDIF.
43 ENDFORM.
44 *---------------------------------------------------------------------*
45
46 *---------------------------------------------------------------------*
47 FORM disvar_value_request
48   USING
49     id_repid                      TYPE syrepid
50     id_handle                     TYPE slis_handl
51   CHANGING
52     cd_variant                    TYPE slis_vari.
53 *---------------------------------------------------------------------*
54   DATA lt_fields                  TYPE TABLE OF fieldname.
55   DATA ls_ledger_info             TYPE t881.
56   DATA ls_tab_info                TYPE t800a.
57   DATA ld_fieldname               TYPE fieldname.
58   DATA ls_start_par               TYPE gdx3_s_pers_start.
59   DATA ld_view                    TYPE viewname.
60
61   DATA lt_excluded_fields         TYPE rsdsselopt_t.
```

```
  62    DATA ls_range                   TYPE rsdsselopt.
  63    DATA ls_sel_view                TYPE rsdsqcat.
  64
  65    DATA lt_dfies                   TYPE STANDARD TABLE OF dfies.
  66    DATA ls_dfies                   TYPE dfies.
  67    DATA ld_curtp                   TYPE curtp.
  68
  69    DATA lt_repid                   TYPE pivb_selopt_t.
  70    DATA lt_handle                  TYPE pivb_selopt_t.
  71    DATA lt_log_group               TYPE pivb_selopt_t.
  72    DATA ls_handle                  LIKE LINE OF lt_handle.
  73    DATA ld_sel_view                TYPE pivb_report_catalog.
  74
  75    DATA lt_param                   TYPE pivb_param_t.
  76    DATA ls_param                   TYPE pivb_param.
  77    DATA lt_filter                  TYPE pivb_tfilter_t.
  78    DATA ls_tfilter                 TYPE pivb_tfilter.
  79    DATA ls_ffilter                 TYPE pivb_ffilter.
  80    DATA ls_selopt                  TYPE rsdsselopt.
  81    DATA ld_tabname                 TYPE tabname.
  82    DATA ld_num                     TYPE n LENGTH 2.
  83    DATA lt_func_groups             TYPE TABLE OF rsdsqgx.
  84    DATA lt_field_names             TYPE TABLE OF  rsdsqfn.
  85    DATA lt_diff_columns            TYPE pivb_column_t.
  86    DATA ls_column                  TYPE pivb_column.
  87    DATA ld_result_status           TYPE char6.
  88    DATA ld_layout_name             TYPE slis_varbz.
  89    data ld_txt                     TYPE camsg.
  90  *---------------------------------------------------------------------*
  91    FIELD-SYMBOLS <ls_func_group>      TYPE rsdsqgx.
  92    FIELD-SYMBOLS <ls_field_name>      TYPE rsdsqfn.
  93  *---------------------------------------------------------------------*
  94    IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_brows
      er.
  95      IF p_ledger IS INITIAL.
  96        GET PARAMETER ID 'GLN'
  97          FIELD p_ledger.
  98      ENDIF.
  99
 100      IF p_ledger IS INITIAL.
 101        CALL METHOD cl_pers_admin=>get_data
 102          EXPORTING
 103            p_pers_key  = 'FI_SL_SEARCH_IT_START'
 104            p_uname     = sy-uname
 105          IMPORTING
 106            p_pers_data = ls_start_par
 107          EXCEPTIONS
 108            OTHERS      = 0.
 109        p_ledger = ls_start_par-ledger.
 110      ENDIF.
 111
 112      IF p_ledger IS NOT INITIAL.
 113        CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
 114          EXPORTING
 115            id_rldnr = p_ledger
 116          EXCEPTIONS
 117            OTHERS   = 1.
 118
 119        IF sy-subrc <> 0.
 120          CLEAR p_ledger.
 121        ENDIF.
```

```
122       ENDIF.
123
124       IF p_ledger IS INITIAL.
125         PERFORM f4_ledger_browser
126           CHANGING
127             p_ledger.
128       ENDIF.
129
130       IF p_ledger IS NOT INITIAL.
131         SET PARAMETER ID 'GLN'
132           FIELD p_ledger.
133       ENDIF.
134
135       IF p_ledger IS INITIAL.
136         LEAVE PROGRAM.
137       ENDIF.
138
139       CALL FUNCTION 'G_GET_LEDGER_INFO'
140         EXPORTING
141           i_rldnr       = p_ledger
142         IMPORTING
143           e_ledger_info = ls_ledger_info.
144
145       CALL FUNCTION 'G_GET_TABLE_INFO'
146         EXPORTING
147           i_tab     = ls_ledger_info-tab
148         IMPORTING
149           e_si_info = ls_tab_info.
150
151       CALL FUNCTION 'FAGL_VIEWS_GET_VIEWNAME_FISL'
152         EXPORTING
153           i_tabname  = ls_tab_info-tab
154         IMPORTING
155           e_viewname = ld_view.
156
157       IF p_ledger <> gd_ledger.
158         gd_ledger = p_ledger.
159       ENDIF.
160
161       gd_sel_view = ld_view.
162     ENDIF.
163
164     CALL METHOD fagl_lib_pivb=>sel_view_check_get
165       EXPORTING
166         id_sel_view   = gd_sel_view
167       CHANGING
168         cs_sel_view   = ls_sel_view
169         cd_base_table = ld_tabname.
170
171   * Determine field information depending on ledger group
172     CALL FUNCTION 'FAGL_HDB_CUST_SVIEW_EXCL_FLDS'
173       EXPORTING
174         ed_appl            = gc_hdb_appl-financials
175         ed_subappl         = gd_subapplication
176         es_sel_view        = ls_sel_view
177       IMPORTING
178         it_excl_fields_sel = lt_excluded_fields
179       EXCEPTIONS
180         OTHERS             = 0.
181
182     LOOP AT lt_excluded_fields
```

```
183       INTO ls_range.
184       ld_fieldname = ls_range-low.
185       COLLECT ld_fieldname
186         INTO  lt_fields.
187     ENDLOOP.
188
189     IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_brows
    er.
190       CALL FUNCTION 'G_GET_LEDGER_INFO'
191         EXPORTING
192           i_rldnr       = p_ledger
193         IMPORTING
194           e_ledger_info = ls_ledger_info
195         EXCEPTIONS
196           OTHERS        = 0.
197
198       CALL FUNCTION 'G_GET_TABLE_INFO'
199         EXPORTING
200           i_tab      = ls_ledger_info-tab
201         IMPORTING
202           e_tab_info = ls_tab_info
203         EXCEPTIONS
204           OTHERS     = 0.
205     ENDIF.
206
207     PERFORM get_curtp_info
208       USING
209         ld_view
210         p_ledger
211         ls_tab_info-comptab
212       CHANGING
213         gts_curtp.
214
215     CALL FUNCTION 'DDIF_NAMETAB_GET'
216       EXPORTING
217         tabname   = 'FISL_S_CURRENCY_VALUE'
218       TABLES
219         dfies_tab = lt_dfies.
220
221     LOOP AT lt_dfies
222       INTO  ls_dfies.
223       ld_curtp = ls_dfies-fieldname+8(2).
224       READ TABLE gts_curtp
225         WITH TABLE KEY
226           table_line = ld_curtp
227         TRANSPORTING NO FIELDS.
228       IF sy-subrc <> 0.
229         COLLECT ls_dfies-fieldname
230           INTO lt_fields.
231       ENDIF.
232     ENDLOOP.
233
234     ls_handle-option = 'EQ'.
235     ls_handle-sign = 'I'.
236
237   * Fill report name for layout selection
238     ls_handle-low = id_repid.
239     APPEND ls_handle TO lt_repid.
240
241   * Fill handle parameter for layout selection
242     ls_handle-low = id_handle.
```

```
243   APPEND ls_handle TO lt_handle.
244
245 * If we have GD20H, we need to add the ledger for per-ledger layouts
246   IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_brows
    er.
247     ls_handle-low = p_ledger.
248     APPEND ls_handle TO lt_log_group.
249   ENDIF.
250
251 * Call this FM to provide user dialogs for selection from existing layou
    ts and
252 * for creating ad hoc layout based on free selection from available colu
    mns.
253   ld_sel_view = id_repid.
254
255   CLEAR ls_selopt.
256   CLEAR ls_ffilter.
257   CLEAR ls_tfilter.
258
259 * Get field groups from selection view
260   CALL FUNCTION 'RS_READ_SEL_OPTIONS'
261     EXPORTING
262       key         = ls_sel_view
263     TABLES
264       func_groups = lt_func_groups
265       field_names = lt_field_names
266     EXCEPTIONS
267       OTHERS      = 0.
268
269   IF lt_field_names IS NOT INITIAL.
270 * Prepare field list for assignment of field groups
271     SORT lt_field_names BY fname.
272
273     ls_ffilter-fieldname = 'FIELDNAME'.
274     ls_selopt-sign       = 'I'.
275     ls_selopt-option     = 'EQ'.
276
277     LOOP AT lt_func_groups
278       ASSIGNING <ls_func_group>.
279       ls_tfilter-text = <ls_func_group>-gtext.
280       LOOP AT lt_field_names
281         ASSIGNING <ls_field_name>
282         WHERE numb = <ls_func_group>-numb.
283         ls_selopt-low = <ls_field_name>-fname.
284         APPEND ls_selopt TO ls_ffilter-selopt_t.
285       ENDLOOP.
286
287       ls_tfilter-filter = ls_ffilter.
288       ld_num = sy-tabix.
289       CONCATENATE 'GROUP' ld_num
290         INTO ls_tfilter-tech_name.
291       APPEND ls_tfilter TO lt_filter.
292       CLEAR ls_tfilter.
293       CLEAR ls_ffilter-selopt_t.
294     ENDLOOP.
295   ENDIF.
296
297   ls_param-paramname = 'SUBAPP'.
298   ls_param-custom = p_appl.
299   APPEND ls_param TO lt_param.
300
```

```
301     LOOP AT lt_excluded_fields INTO ls_range.
302       ls_column-fieldname = ls_range-low.
303       APPEND ls_column TO lt_diff_columns.
304     ENDLOOP.
305
306     CALL FUNCTION 'PIVB_F4'
307       EXPORTING
308         i_report_catalog  = gd_sel_view
309         i_report_scenario = gc_scenario
310         i_report_name     = id_repid
311         i_handle          = lt_handle
312         i_log_group       = lt_log_group
313         i_start           = 'LAYOUT'
314 *       it_diff_columns   = lt_diff_columns
315         it_custom_filter  = lt_filter
316       IMPORTING
317         e_layout          = cd_variant
318         e_result_status   = ld_result_status
319         e_layout_name     = ld_layout_name
320       CHANGING
321         ct_field          = gt_column
322       EXCEPTIONS
323         error_message     = 4.
324
325     IF sy-subrc = 4.
326   * Do nothing, same error will be also raised during execution
327   * (and is not possible raise messages in F4 Help event)
328     ENDIF.
329
330   * update screen with description of the selected layout
331     CASE ld_result_status.
332       WHEN if_pivb_c_f4=>result_field.
333
334         MESSAGE i014(pivb) INTO ld_txt.
335         ld_layout_name = ld_txt.
336         MESSAGE i013(pivb) INTO ld_txt.
337
338         PERFORM update_screen.
339
340       WHEN if_pivb_c_f4=>result_layout.
341
342         MESSAGE i012(pivb) INTO ld_txt.
343         PERFORM update_screen.
344
345     ENDCASE.
346
347   ENDFORM.
348   *---------------------------------------------------------------------*
349
350   *---------------------------------------------------------------------*
351   FORM update_screen.
352   *---------------------------------------------------------------------*
353     DATA ls_dynpfield               TYPE dynpread.
354     DATA lt_dynpfield               TYPE TABLE OF dynpread.
355     DATA ld_layout_name             TYPE slis_varbz.
356   *---------------------------------------------------------------------*
357     ls_dynpfield-fieldname = 'P_LAYOUT'.
358     ls_dynpfield-fieldvalue = p_layout.
359     APPEND ls_dynpfield TO lt_dynpfield.
360
361     ls_dynpfield-fieldname = 'COMM01'.
```

```
362    ls_dynpfield-fieldvalue = ld_layout_name.
363    APPEND ls_dynpfield TO lt_dynpfield.
364
365    CALL FUNCTION 'DYNP_VALUES_UPDATE'
366      EXPORTING
367        dyname     = sy-repid
368        dynumb     = sy-dynnr
369      TABLES
370        dynpfields = lt_dynpfield.
371
372  ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_P03
3  *&---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  DISPLAY_DATA
6  *&---------------------------------------------------------------------*
7  form display_data.
8  * add ledger selection
9    case gd_sel_view.
10     when gc_s_hdb_ddic-gl_view
11       or gc_s_hdb_ddic-pca_line_items                    "n2436588
12       or gc_s_hdb_ddic-pca_line_items_ext                "n2436588
13       or gc_s_hdb_ddic-gl_view_ext                       "n2104752
14       or if_fagl_lib_cds_util=>c_view_n_gl.
15
16       go_util->add_ledger( ledger = p_ledger no_extension = p_exonly ).
17   endcase.
18
19 * add pofit center groups (note 3031177)
20   perform add_prctr_groups.
21
22 * add account groups
23   perform add_racct_groups.
24
25 * add PCA browser specifics
26   perform add_pca_selections.
27
28 * add SL browser specifics
29   data pivb_log_group type pivb_selopt_t.
30   perform add_sl_selections changing pivb_log_group.
31
32 * now get all selections
33   append lines of go_util->get_selection( ) to gt_seltab.
34
35 * set general parameters for PIVB call
36   append value #( paramname = 'REPT_NAME' custom =  sy-repid ) to gt_piv
   b_param.
37   data(pivb_handle) =  value pivb_selopt_t( ( sign = 'I' option = 'EQ' l
   ow = gc_handle_main ) ).
38   append value #( paramname = 'VAR_HANDLE' custom = gc_handle_main ) to
   gt_pivb_param.
39
40 * set proxy source for CDS
41   data(lv_sel_view) = cl_fagl_lib_cds_util=>get_proxy_for_view( gd_sel_v
   iew ).
42
43 * download the first result list
44   if gd_create_file = abap_true.
45
46 *   triggers download in PIVB: on presentation or application server
47     append value #( paramname = 'TRIGGERDL'
48                     custom = cond #( when p_dpres = abap_true then 'DPRE
   S' else 'DAPPL' ) ) to gt_pivb_param.
49
50     if p_dmxml = abap_true.
51       data(lv_download_mode) = conv string( 'XML' ).
52     elseif p_dmcmp = abap_true.
53       lv_download_mode = 'COMPRESSED'.
54     else.
55       lv_download_mode = 'RAW'.
56     endif.
```

```
 57      append value #( paramname = 'DOWNLOAD_MODE' custom = lv_download_mod
    e ) to gt_pivb_param.
 58      append value #( paramname = 'DOWNLOAD_WR_HEADER' custom = p_dwhdr )
    to gt_pivb_param.
 59      append value #( paramname = 'DOWNLOAD_WR_METADATA' custom = p_dwmta
    ) to gt_pivb_param.
 60
 61      append value #( paramname = 'FILENAME' custom = p_dfile ) to gt_pivb
    _param.
 62      append value #( paramname = 'OUTCONV' custom = p_dconv ) to gt_pivb_
    param.
 63      append value #( paramname = 'VAR_LAYOUT' custom = gd_variant ) to gt
    _pivb_param.
 64
 65      data lr_dummy type ref to data.
 66      call function 'PIVB_SELECT_AND_RETURN'
 67        exporting
 68          i_report_catalog     = lv_sel_view
 69          i_report_scenario    = gc_scenario
 70          i_report_name        = sy-repid
 71          it_seltab            = gt_seltab
 72          it_and_seltab        = gt_and_seltab "n2647709
 73          i_layout             = gd_variant
 74          it_column_visibility = gt_column
 75          it_param             = gt_pivb_param
 76          i_handle             = pivb_handle
 77          i_log_group          = pivb_log_group
 78        changing
 79          ct_outtab            = lr_dummy.
 80
 81      clear gd_create_file.
 82
 83  * show result list?
 84      if p_outli = abap_false.
 85        return.
 86      endif.
 87    endif.
 88
 89  *   Handle call via SUBMIT      "n2636523
 90    if sy-calld is not initial                                    "n2636523
 91      and p_dspovr <> abap_true                                   "n2711621
 92      and cl_gui_alv_grid=>offline( ) = 1                         "n2778804
 93      and sy-tcode <> 'FAGLB03'                                   "n2636523
 94      and sy-tcode <> 'FS10N'                                     "n2636523
 95      and sy-tcode <> 'FK10N'                                     "n2636523
 96      and sy-tcode <> 'FD10N'.                                    "n2636523
 97      data(ld_display_style) = 'S'.                               "n2636523
 98    endif.                                                        "n2636523
 99
100    if p_outfi = abap_true.
101      delete gt_pivb_param
102        where paramname = 'TRIGGERDL'.
103    endif.
104
105    call function 'PIVB_SELECT_AND_DISPLAY'
106      exporting
107        i_report_catalog     = lv_sel_view
108        i_report_scenario    = gc_scenario
109        i_report_name        = sy-repid
110        it_seltab            = gt_seltab
111        it_and_seltab        = gt_and_seltab "n2647709
```

```
112         i_layout             = gd_variant
113         it_column_visibility = gt_column
114         it_param             = gt_pivb_param
115         i_handle             = pivb_handle
116         i_log_group          = pivb_log_group
117         i_display_style      = ld_display_style "n2636523
118       exceptions
119         others               = 1.
120
121     if sy-subrc <> 0.
122       message s033(msitem).
123     endif.
124
125   endform.                    " DISPLAY_DATA
126
127   form add_pca_selections.
128     data lt_ra_prctr                type rsds_selopt_t.
129     data lt_ra_racct                type rsds_selopt_t.
130
131     check gd_subapplication = gc_hdb_subappl-s_pca-line_item_browser.
132
133     perform setval_from_group using gc_s_setclass-pc_group
134                                     'P_PCGRP'
135                                     'S'
136                                changing lt_ra_prctr.
137
138     go_util->add_seltab( value #( fieldname = 'rprctr' selopt_t = lt_ra_pr
    ctr ) ).
139
140     perform setval_from_group using gc_s_setclass-acct_group
141                                     'P_ACGRP'
142                                     'S'
143                                changing lt_ra_racct.
144
145     go_util->add_seltab( value #( fieldname = 'racct' selopt_t = lt_ra_rac
    ct ) ).
146   endform.
147
148   form add_sl_selections changing log_group type pivb_selopt_t.
149     check gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_br
    owser.
150
151     go_util->add_seltab( value #( fieldname = 'rldnr' selopt_t = value #(
    ( sign = 'I' option = 'EQ' low = p_ledger ) ) ) ).
152
153     append value #( sign = 'I' option = 'EQ' low = p_ledger ) to log_group
    .
154     append value #( paramname = 'VAR_LOG_GROUP' custom = p_ledger ) to gt_
    pivb_param.
155   endform.
156
157   form add_prctr_groups.
158     data lt_ra_prctr                type rsds_selopt_t.
159
160     check gv_lib_prctr_grp_select = abap_true
161       and ( gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
162          or gd_subapplication = gc_hdb_subappl-s_newgl-entry_view
163          or gd_subapplication = gc_hdb_subappl-s_newgl-line_item_browser
164          or gd_subapplication = gc_hdb_subappl-s_classic_gl-line_item_brow
    ser ).
165
```

```
166    if p_pcgrp is initial.
167      go_util->register( value #( ( 'prctr;s_rprctr' ) ) ).
168    else.
169      go_util->add_seltab( value #( fieldname = 'prctr' selopt_t = gt_ra_p
     rctr ) ).
170      go_util->register( value #( ( 'kokrs;s_coarea' ) ) ).
171    endif.
172  endform.
173
174  form add_racct_groups.
175    data lt_ra_racct                type rsds_selopt_t.
176
177    check gv_lib_prctr_grp_select = abap_true
178      and ( gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
179         or gd_subapplication = gc_hdb_subappl-s_newgl-entry_view
180         or gd_subapplication = gc_hdb_subappl-s_newgl-line_item_browser
181         or gd_subapplication = gc_hdb_subappl-s_classic_gl-line_item_brow
     ser ).
182
183    check p_acgrp is not initial.
184
185    go_util->add_seltab( value #( fieldname = 'hkont' selopt_t = gt_ra_rac
     ct ) ).
186    go_util->register( value #( ( 'kokrs;s_coarea' ) ) ).
187  endform.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_PCL2
3  *&---------------------------------------------------------------------*
4  CLASS cl_screen_handler IMPLEMENTATION.
5
6  * Init_sel_screen
7    INCLUDE fagl_line_item_browser_pcl3.
8
9  * Initialization
10   INCLUDE fagl_line_item_browser_pcl4.
11
12 * Start_selection
13   INCLUDE fagl_line_item_browser_cl5.
14
15 * At Selection Screen
16   INCLUDE fagl_line_item_browser_pcl6.
17
18 * At Selection Screen Output
19   INCLUDE fagl_line_item_browser_cl7.
20
21 * Fieldcat_Adjust
22   INCLUDE fagl_line_item_browser_cl8.
23
24 ENDCLASS.
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_PCL3
*&---------------------------------------------------------------------*
* add default fields to KESS
DEFINE add_field.
*  macro looks at DFIES tab if field &1 is available
*  (with binary search)
  READ TABLE lt_available_fields
       WITH KEY fieldname = &1
       TRANSPORTING NO FIELDS
       BINARY SEARCH.

      IF sy-subrc = 0.
*       Add field to KESS
        gr_screen->set_so_field( i_tablename = gd_sel_view
                                 i_fieldname = &1 ).
      ENDIF.

END-OF-DEFINITION.


*&---------------------------------------------------------------------*
METHOD init_sel_screen.
*---------------------------------------------------------------------*
  DATA lt_fields            TYPE TABLE OF fieldname.
  DATA ls_ledger_info       TYPE t881.
  DATA ls_tab_info          TYPE t800a.
  DATA ls_start_par         TYPE gdx3_s_pers_start.
  DATA ld_view              TYPE viewname.

  DATA lt_hdb_range         TYPE hdb_t_range.                 "n2636622
  DATA ls_hdb_range         TYPE hdb_s_range.                 "n2636622

  DATA lt_dfies             TYPE STANDARD TABLE OF dfies.
  DATA ls_dfies             TYPE dfies.
  DATA ld_curtp             TYPE curtp.

  DATA lt_available_fields TYPE TABLE OF dfies.

*---------------------------------------------------------------------*
  FIELD-SYMBOLS <dfies> TYPE dfies.
  field-symbols <kess_range> type rsds_range.               "3140727
*---------------------------------------------------------------------*
  IF sy-cprog = 'FAGL_LINE_ITEM_BROWSER_SL'.
    IF p_ledger IS INITIAL.
      GET PARAMETER ID 'GLN'
        FIELD p_ledger.
    ENDIF.

    IF p_ledger = '00'
      OR p_ledger = '0L'
      OR p_ledger = '8A'.
      CLEAR p_ledger.
    ENDIF.

    IF p_ledger IS INITIAL.
      CALL METHOD cl_pers_admin=>get_data
        EXPORTING
          p_pers_key  = 'FI_SL_SEARCH_IT_START'
          p_uname     = sy-uname
        IMPORTING
```

```
62            p_pers_data = ls_start_par
63          EXCEPTIONS
64            OTHERS      = 0.
65        p_ledger = ls_start_par-ledger.
66      ENDIF.
67
68      IF p_ledger IS NOT INITIAL.
69        CALL FUNCTION 'FAGL_FISL_VIEW_FOR_RLDNR_GET'
70          EXPORTING
71            id_rldnr = p_ledger
72          EXCEPTIONS
73            OTHERS   = 1.
74
75        IF sy-subrc <> 0.
76          CLEAR p_ledger.
77        ENDIF.
78      ENDIF.
79
80      IF p_ledger IS INITIAL.
81        PERFORM f4_ledger_browser
82          CHANGING
83            p_ledger.
84      ENDIF.
85
86      IF p_ledger IS NOT INITIAL.
87        SET PARAMETER ID 'GLN'
88          FIELD p_ledger.
89      ENDIF.
90
91      IF p_ledger IS INITIAL.
92        LEAVE PROGRAM.
93      ENDIF.
94
95      CALL FUNCTION 'G_GET_LEDGER_INFO'
96        EXPORTING
97          i_rldnr       = p_ledger
98        IMPORTING
99          e_ledger_info = ls_ledger_info.
100
101     CALL FUNCTION 'G_GET_TABLE_INFO'
102       EXPORTING
103         i_tab     = ls_ledger_info-tab
104       IMPORTING
105         e_si_info = ls_tab_info.
106
107     CALL FUNCTION 'FAGL_VIEWS_GET_VIEWNAME_FISL'
108       EXPORTING
109         i_tabname  = ls_tab_info-tab
110       IMPORTING
111         e_viewname = ld_view.
112
113   ELSE.
114 *       Set default variant handling for other browsers
115 *       (no table-dependent variants via KESS!)
116     gr_screen->set_variant_get( i_standard = abap_true ).
117   ENDIF.
118
119   PERFORM initialization.
120
121   IF p_ledger <> gd_ledger.
122     gd_ledger = p_ledger.
```

```
123       gr_screen->set_table( i_tablename = ld_view ).
124     ENDIF.
125
126     "Begin of note 3031177
127     CALL FUNCTION 'FAGL_GET_FAGL_SETTINGS'
128       EXPORTING
129         id_param_name = 'LIB_PRCTR_GRP_SELECT'
130       IMPORTING
131         ed_value      = gv_lib_prctr_grp_select.
132
133     IF gv_lib_prctr_grp_select = abap_true
134       AND ( gd_subapplication = gc_hdb_subappl-s_newgl-gl_view
135          OR gd_subapplication = gc_hdb_subappl-s_newgl-entry_view
136          OR gd_subapplication = gc_hdb_subappl-s_newgl-line_item_browser
137          OR gd_subapplication = gc_hdb_subappl-s_classic_gl-line_item_brow
    ser ).
138       DATA lv_exclude_prctr TYPE fieldname VALUE 'PRCTR'.
139       COLLECT lv_exclude_prctr INTO lt_fields.
140     ENDIF.
141     "End of note 3031177
142
143     IF gd_subapplication = gc_hdb_subappl-s_special_ledger-line_item_brows
    er.
144       CALL FUNCTION 'G_GET_LEDGER_INFO'
145         EXPORTING
146           i_rldnr       = p_ledger
147         IMPORTING
148           e_ledger_info = ls_ledger_info
149         EXCEPTIONS
150           OTHERS        = 0.
151
152       CALL FUNCTION 'G_GET_TABLE_INFO'
153         EXPORTING
154           i_tab      = ls_ledger_info-tab
155         IMPORTING
156           e_tab_info = ls_tab_info
157         EXCEPTIONS
158           OTHERS     = 0.
159     ENDIF.
160
161     PERFORM get_curtp_info
162       USING
163         ld_view
164         p_ledger
165         ls_tab_info-comptab
166       CHANGING
167         gts_curtp.
168
169     CALL FUNCTION 'DDIF_NAMETAB_GET'
170       EXPORTING
171         tabname   = 'FISL_S_CURRENCY_VALUE'
172       TABLES
173         dfies_tab = lt_dfies.
174
175     LOOP AT lt_dfies
176       INTO  ls_dfies.
177       ld_curtp = ls_dfies-fieldname+8(2).
178       READ TABLE gts_curtp
179         WITH TABLE KEY
180           table_line = ld_curtp
181         TRANSPORTING NO FIELDS.
```

```
182       IF sy-subrc <> 0.
183         COLLECT ls_dfies-fieldname
184           INTO lt_fields.
185       ENDIF.
186     ENDLOOP.
187
188     IF gd_sel_view IS NOT INITIAL
189       AND p_appl <> gc_hdb_subappl-s_special_ledger-line_item_browser.
190       gr_screen->set_table( i_tablename = gd_sel_view ).
191     ENDIF.
192
193     CALL METHOD gr_screen->set_excluded_so
194       EXPORTING
195         i_tablename  = gd_sel_view "ld_view ???
196         it_fieldname = lt_fields.
197
198   **  all variants are passed to the application exit for validation
199     gr_screen->set_variant_get_kess_table( abap_false ).
200
201     CALL FUNCTION 'DDIF_FIELDINFO_GET'
202       EXPORTING
203         tabname   = gd_sel_view
204       TABLES
205         dfies_tab = lt_available_fields[].
206
207
208     SORT lt_available_fields BY fieldname ASCENDING.
209
210   *                                                    "begin of "n2716343
211   ** Check if the user has maintained a default layout or
212   ** if there is a global layout which should be applied,
213   ** otherwise provide a suitable default screen
214     SELECT SINGLE COUNT( * )
215       FROM tkess_scr_init
216       WHERE prgname = sy-repid
217       AND   tabname = gd_sel_view
218       AND  ( username = sy-uname OR username = '' ).
219     IF sy-subrc <> 0.                                    "end of "n2716343
220
221   * Provide a useful SelScreen for GD20H
222     IF sy-cprog = 'FAGL_LINE_ITEM_BROWSER_SL'.
223       add_field 'RYEAR'.
224       add_field 'POPER'.
225       add_field 'RBUKRS'.
226       add_field 'RACCT'.
227     ENDIF.
228
229
230   * BELNR (or DOCNR) are default fields on the SelScreen
231   * for all browsers
232     READ TABLE lt_available_fields
233         WITH KEY fieldname = 'BELNR'
234         TRANSPORTING NO FIELDS
235         BINARY SEARCH.
236
237     IF sy-subrc = 0.
238       gr_screen->set_so_field( i_tablename = gd_sel_view
239                                i_fieldname = 'BELNR').
240     ELSE.
241       READ TABLE lt_available_fields
242       WITH KEY fieldname = 'DOCNR'
```

```
243       TRANSPORTING NO FIELDS
244       BINARY SEARCH.
245
246       IF sy-subrc = 0.
247         gr_screen->set_so_field( i_tablename = gd_sel_view
248                                  i_fieldname = 'DOCNR').
249       ENDIF.
250     ENDIF.
251
252   * Additional fields for GD20H
253     IF sy-cprog = 'FAGL_LINE_ITEM_BROWSER_SL'.
254       add_field 'BUDAT'.
255       add_field 'BLDAT'.
256       add_field 'ROBUKRS'.
257       add_field 'RCOMP'.
258       add_field 'CPUDT'.
259       add_field 'CPUTM'.
260       add_field 'RCOMP'.
261     ENDIF.
262
263     ENDIF.                                                    "n2716343
264
265   * Disable KESS selection screen if desired          "begin of "n2636622
266     IF sy-cprog <> 'FAGL_LINE_ITEM_BROWSER_SL'.
267       CALL FUNCTION 'HDB_RANGE_READ'
268         EXPORTING
269           i_application    = gc_hdb_appl-financials
270           i_subapplication = gd_subapplication
271           i_range_type     = gc_hdb_range_type-disable_kess
272         IMPORTING
273           et_range         = lt_hdb_range.
274       LOOP AT lt_hdb_range
275         INTO ls_hdb_range.
276         gd_disable_kess = ls_hdb_range-low.
277         EXIT.
278       ENDLOOP.
279     ELSE.
280   *   We need KESS for SL Browser
281       gd_disable_kess = abap_false.
282     ENDIF.
283
284     IF gd_disable_kess = abap_true.
285       gr_screen->set_screendef_visible( i_visible = abap_false ).
286     ENDIF.                                              "end of "n2636622
287
288   ENDMETHOD.
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_PCL4
*&---------------------------------------------------------------------*
METHOD initialization.
*---------------------------------------------------------------------*
  DATA ls_coarea                  LIKE LINE OF s_coarea.
  DATA ld_popup TYPE c.                                          "n2587427
*---------------------------------------------------------------------*
  PERFORM initialization.

  IF sy-repid = 'FAGL_LINE_ITEM_BROWSER_PCA'.
    ls_coarea-sign   = 'I'.
    ls_coarea-option = 'EQ'.
    GET PARAMETER ID 'CAC' FIELD ls_coarea-low.
    IF s_coarea-low IS INITIAL.
      IF sy-batch IS NOT INITIAL.                                "n2587427
        ld_popup = '0'.                                          "n2587427
      ENDIF.                                                     "n2587427

      CALL FUNCTION 'K_KOKRS_SET'
        EXPORTING                 "2587427
          popup   = ld_popup        "2587427
        IMPORTING
          e_kokrs = ls_coarea-low
        EXCEPTIONS
          OTHERS  = 0.
    ENDIF.
    IF ls_coarea-low IS NOT INITIAL.
      APPEND ls_coarea
        TO s_coarea.
    ENDIF.
  ENDIF.

** Clean up internal variables for return to selscr."begin of "n2767139
  IF ( gd_consider_worklists = abap_true                         "begin of "n2869685
    AND gd_worklist_active <> abap_false )
    OR ( gd_consider_sets = abap_true
      AND gd_sets_active <> abap_false ).

    CLEAR gs_reset_selection.
    IF p_setbuk IS NOT INITIAL OR p_wlbuk IS NOT INITIAL.
      gs_reset_selection-ccode = abap_true.
    ENDIF.
    IF p_setrac IS NOT INITIAL OR p_wlrac IS NOT INITIAL.
      gs_reset_selection-racct = abap_true.
    ENDIF.
    IF p_setven IS NOT INITIAL OR p_wlven IS NOT INITIAL.
      gs_reset_selection-vendor = abap_true.
    ENDIF.
    IF p_setcus IS NOT INITIAL OR p_wlcus IS NOT INITIAL.
      gs_reset_selection-customer = abap_true.
    ENDIF.
  ENDIF.                                      "end of "n2767139 "n2869685


ENDMETHOD.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_PCL6
3  *&---------------------------------------------------------------------*
4  METHOD sel_screen.
5  *---------------------------------------------------------------------*
6      DATA lt_coarea                TYPE STANDARD TABLE OF kokrs.
7      DATA ld_lines                 TYPE i.
8      DATA ld_pcgrp                 TYPE string.
9  *---------------------------------------------------------------------*
10     FIELD-SYMBOLS <ld_pcgrp>      TYPE any.
11 *---------------------------------------------------------------------*
12   CHECK e_simul_exec = abap_false.
13
14 **  begin of note 2636530
15 **  This method refreshes the used variant, thus no saved
16 **  variant can be applied anymore if it is always called
17 *  REFRESH psx_kess-trange.                  "n2571532
18 *
19 *  CALL METHOD gr_screen->get_selection    "n2571532
20 *    RECEIVING                             "n2571532
21 *      rt_seltab = psx_kess-trange.        "n2571532
22 *  end of note 2636530
23
24   PERFORM selection_screen.
25
26   IF sy-repid = 'FAGL_LINE_ITEM_BROWSER_PCA'.
27     ld_pcgrp = 'P_PCGRP'.
28     ASSIGN (ld_pcgrp) TO <ld_pcgrp>.
29     IF sy-subrc = 0.
30       SELECT kokrs
31         FROM tka01
32         INTO TABLE lt_coarea
33         WHERE kokrs IN s_coarea.
34
35       ld_lines = lines( lt_coarea ).
36       IF  ld_lines > 1
37       AND <ld_pcgrp> IS NOT INITIAL.
38         MESSAGE e017(fagl_reporting_en).
39       ENDIF.
40     ENDIF.
41   ENDIF.
42 ENDMETHOD.
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_PCLD
*&---------------------------------------------------------------------*

CLASS lcl_grid_event_receiver DEFINITION FINAL.
* Dummy class since this is handled in PIVB
* but referred to by some other includes
ENDCLASS.                    "lcl_grid_event_receiver DEFINITION
*---------------------------------------------------------------------*

*---------------------------------------------------------------------*
* KESS needs this to map the events correctly
CLASS cl_screen_handler DEFINITION.
  PUBLIC SECTION.
    CLASS-METHODS
      sel_screen_output
        FOR EVENT at_selection_screen_output
        OF cl_kess_free_selection.

    CLASS-METHODS
      sel_screen
      FOR EVENT at_selection_screen
                    OF cl_kess_free_selection
        IMPORTING e_simul_exec.

    CLASS-METHODS
      init_sel_screen
        FOR EVENT init_sel_screen
        OF cl_kess_free_selection.

    CLASS-METHODS
      initialization
        FOR EVENT initialization
        OF cl_kess_free_selection.

    CLASS-METHODS
      start_selection
      FOR EVENT start_of_selection
                    OF cl_kess_free_selection
        IMPORTING et_sel.

    CLASS-METHODS
      fieldcat_adjust
      FOR EVENT fieldcat_adjust
                    OF cl_kess_free_selection
        IMPORTING et_fcat.

ENDCLASS.
*---------------------------------------------------------------------*
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_PFORMS
3  *&---------------------------------------------------------------------*
4    INCLUDE find_relevant_ledger.
5    INCLUDE fagl_hr_only_check.
6    INCLUDE fagl_choose_ledger.
7
8  *  PIVB + KESS
9    INCLUDE fagl_line_item_browser_p01. " main
10   INCLUDE fagl_line_item_browser_p02. " layout f4 help
11   INCLUDE fagl_line_item_browser_p03. " display_data
12
13 *  legacy
14   INCLUDE fagl_line_item_browser_f02. " initialization
15   INCLUDE fagl_line_item_browser_f03. " selection_screen_output
16   INCLUDE fagl_line_item_browser_f04. " selection_screen
17   INCLUDE fagl_line_item_browser_f05. " dbcon_get
18   INCLUDE fagl_line_item_browser_f06. " fill_fieldlist
19   INCLUDE fagl_line_item_browser_f08. " check_before_start
20   INCLUDE fagl_line_item_browser_f09. " free_selections
21   INCLUDE fagl_line_item_browser_f13. " report_assign, get_text
22   INCLUDE fagl_line_item_browser_f20. " ledger_value_request
23   INCLUDE fagl_line_item_browser_f23. " call_hdbc_restricted
24   INCLUDE fagl_line_item_browser_f24. " messages_show
25   INCLUDE fagl_line_item_browser_f25. " filename_value_request
26   INCLUDE fagl_line_item_browser_f27. " rri_init
27   INCLUDE fagl_line_item_browser_f28. " sel_view_check_get
28   INCLUDE fagl_line_item_browser_f34. " get_curtp_info
29   INCLUDE fagl_line_item_browser_f36. " group_value_request
30   INCLUDE fagl_line_item_browser_f37. " setval_from_group
31   INCLUDE fagl_line_item_browser_f44. " f4_ledger_browser
32   INCLUDE fagl_line_item_browser_f45. " ledger_from_selscreen
33   INCLUDE fagl_line_item_browser_f50. " branch logic
34
35   INCLUDE fagl_line_item_browser_pcl2. " cl_screen_handler impl
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_PS01
*&---------------------------------------------------------------------*
PARAMETERS p_appl             TYPE sytcode AS LISTBOX
                              VISIBLE LENGTH 80
                              USER-COMMAND appl_change
                              MODIF ID app.

SELECTION-SCREEN FUNCTION KEY 2.
SELECTION-SCREEN FUNCTION KEY 3.
SELECTION-SCREEN FUNCTION KEY 4.                              "n2124059
SELECTION-SCREEN FUNCTION KEY 5.                              "n2767139

*---------------------------------------------------------------------*
* Company code
*---------------------------------------------------------------------*
SELECTION-SCREEN BEGIN OF BLOCK b05 WITH FRAME TITLE textb05.
* Company Code
SELECT-OPTIONS s_ccode
  FOR  rfbila_sel-ccode.
PARAMETERS p_wlbuk                                            "n2767139
  TYPE rf42b-idntb                                            "n2767139
  MODIF ID wlb.                                               "n2767139
PARAMETERS p_setbuk                                           "n2869685
  TYPE char24                                                 "n2869685
  MODIF ID stb.                                               "n2869685

PARAMETERS
  p_ledger                    TYPE fins_ledger                "n2745369
                              MODIF ID rld.

*---------------------------------------------------------------------*
* Account
*---------------------------------------------------------------------*
* Account
SELECT-OPTIONS s_racct
  FOR  rfbila_sel-racct
  MODIF ID gla.
PARAMETERS p_wlrac                                            "n2767139
  TYPE rf42b-idnts                                            "n2767139
  MODIF ID wlg.                                               "n2767139
PARAMETERS p_setrac                                           "n2869685
  TYPE char24                                                 "n2869685
  MODIF ID stg.                                               "n2869685
SELECT-OPTIONS s_cust
  FOR bseg-kunnr
  MODIF ID ara.
PARAMETERS p_wlcus                                            "n2767139
  TYPE rf42b-idntd                                            "n2767139
  MODIF ID wlr.                                               "n2767139
PARAMETERS p_setcus                                           "n2869685
  TYPE char24                                                 "n2869685
  MODIF ID str.                                               "n2869685
SELECT-OPTIONS s_vend
  FOR bseg-lifnr
  MODIF ID apa.
PARAMETERS p_wlven                                            "n2767139
  TYPE rf42b-idntk                                            "n2767139
  MODIF ID wlp.                                               "n2767139
PARAMETERS p_setven                                           "n2869685
  TYPE char24                                                 "n2869685
```

```
  MODIF ID stp.                                                  "n2869685
SELECT-OPTIONS s_acctp
  FOR bseg-koart
  MODIF ID atp.

SELECTION-SCREEN END OF BLOCK b05.

selection-screen begin of block group with frame title text-b30. "303117
7
* controlling area
  select-options s_coarea for glpca-kokrs modif id gpc no intervals no-e
xtension.
  selection-screen skip.
* profit center
  selection-screen begin of block prctr with frame title text-b31.
  select-options s_rprctr for glpca-rprctr modif id gpc.        "3031177
  selection-screen comment /3(10) text-cor modif id gpc.        "3031177
* profit center group
  parameters p_pcgrp type fagl_pcgru modif id gpc.              "3031177
  selection-screen end of block prctr.
* account group
  selection-screen begin of block acgrp with frame title text-b32.
  parameters p_acgrp type acctgrp modif id gpc.
  selection-screen end of block acgrp.
selection-screen end of block group.                            "3031177

SELECTION-SCREEN BEGIN OF BLOCK b07 WITH FRAME TITLE textb07.
*---------------------------------------------------------------------*
* Line Items
*---------------------------------------------------------------------*
SELECTION-SCREEN BEGIN OF BLOCK b10 WITH FRAME TITLE textb10.
*   open items:
PARAMETERS p_oi               LIKE itemset-xopsel
                              RADIOBUTTON GROUP rad1
                              DEFAULT 'X'
                              USER-COMMAND dummy.

SELECTION-SCREEN BEGIN OF BLOCK b12 WITH FRAME TITLE textb12.
PARAMETERS p_keydo            LIKE rfpdo-allgstid
                              DEFAULT sy-datlo
                              MODIF ID xoi.

SELECTION-SCREEN BEGIN OF LINE.
PARAMETERS p_xoim             TYPE fagl_open_item_incl_non_oi_acc
                              AS CHECKBOX
                              MODIF ID xom.
SELECTION-SCREEN COMMENT 3(55) gd_xoim FOR FIELD p_xoim
                              MODIF ID xom.
SELECTION-SCREEN END OF LINE.
SELECTION-SCREEN END OF BLOCK b12.

*   cleared items:
PARAMETERS p_ci               LIKE itemset-xclsel
                              RADIOBUTTON GROUP rad1.
SELECTION-SCREEN BEGIN OF BLOCK b14 WITH FRAME TITLE textb14.
SELECT-OPTIONS s_cdate        FOR bsis-augdt
                              MODIF ID xcl.

PARAMETERS p_keydc            LIKE rfpdo-allgstid
                              MODIF ID xcl.
SELECTION-SCREEN END OF BLOCK b14.
```

```
121 *   all items:
122 PARAMETERS p_ai               LIKE itemset-xaisel
123                              RADIOBUTTON GROUP rad1.
124
125 SELECTION-SCREEN BEGIN OF BLOCK b16 WITH FRAME TITLE textb16.
126 SELECT-OPTIONS s_pdate        FOR bsis-budat
127                              MODIF ID xai.
128
129 SELECTION-SCREEN COMMENT /1(71) gd_ypcmt
130                              MODIF ID xai.
131
132 SELECT-OPTIONS s_ryear
133   FOR rfbila_sel-rep_year    MODIF ID xai.
134
135 SELECT-OPTIONS s_period
136   FOR rfbila_sel-rep_period  MODIF ID xai.
137 SELECTION-SCREEN END OF BLOCK b16.
138
139 SELECTION-SCREEN END OF BLOCK b10.
140 SELECTION-SCREEN BEGIN OF BLOCK b18 WITH FRAME TITLE textb18.
141 PARAMETERS p_ty_nor         TYPE itemset-xnorm AS CHECKBOX
142                              DEFAULT abap_true.
143 PARAMETERS p_ty_spg         TYPE itemset-xshbv AS CHECKBOX
144                              MODIF ID xsp.
145 PARAMETERS p_ty_nit         TYPE itemset-xmerk AS CHECKBOX.
146 PARAMETERS p_ty_pit         TYPE itemset-xpark AS CHECKBOX.
147 PARAMETERS p_ty_ap          TYPE itemset-xapit AS CHECKBOX  "n2315306
148                              MODIF ID ara.                   "n2315306
149 PARAMETERS p_ty_ar          TYPE itemset-xarit AS CHECKBOX  "n2315306
150                              MODIF ID apa.                   "n2315306
151 SELECTION-SCREEN BEGIN OF LINE.
152 PARAMETERS p_ty_gly         TYPE fagl_yec_data_sel          "n2494719
153                              AS CHECKBOX                     "n2494719
154                              MODIF ID gly.                   "n2494719
155 SELECTION-SCREEN COMMENT 3(55) gd_tygly FOR FIELD p_ty_gly  "n2494719
156                              MODIF ID gly.                   "n2494719
157 SELECTION-SCREEN END OF LINE.                                "n2494719
158 SELECTION-SCREEN BEGIN OF LINE.
159 PARAMETERS p_exonly         TYPE fagl_ledger_ext_only_sel   "n2816760
160                              AS CHECKBOX                     "n2816760
161                              MODIF ID ext.                   "n2816760
162 SELECTION-SCREEN COMMENT 3(55) gd_exrld                      "n2816760
163                              FOR FIELD p_exonly              "n2816760
164                              MODIF ID ext.                   "n2816760
165 SELECTION-SCREEN END OF LINE.                                "n2816760
166
167 ** Enforce selection of BSTAT = C items (n2857175)
168 SELECTION-SCREEN BEGIN OF LINE.
169 PARAMETERS p_enfoj TYPE fagl_enfoj NO-DISPLAY.
170 SELECTION-SCREEN END OF LINE.
171
172 SELECTION-SCREEN END OF BLOCK b18.
173
174 *---------------------------------------------------------------------*
175 * Additional Restrictions
176 *---------------------------------------------------------------------*
177 * outer frame for item selection:
178 SELECTION-SCREEN BEGIN OF BLOCK b15 WITH FRAME TITLE textb15.
179 * Free selections for line items
180 SELECTION-SCREEN
181   PUSHBUTTON /1(75) item_sel
```

```
182    USER-COMMAND item_sel
183    VISIBLE LENGTH 30.
184  SELECTION-SCREEN END OF BLOCK b15.
185  SELECTION-SCREEN END OF BLOCK b07.
186
187  *---------------------------------------------------------------------*
188  * KESS
189  *---------------------------------------------------------------------*
190  INCLUDE rkess_free_selection.
191
192
193  *---------------------------------------------------------------------*
194  * Output
195  *---------------------------------------------------------------------*
196  * outer frame for item selection:
197  SELECTION-SCREEN BEGIN OF BLOCK b20 WITH FRAME TITLE textb20.
198  PARAMETERS p_layout           LIKE rfbila_sel-output_grid_variant.
199  SELECTION-SCREEN SKIP.
200  SELECTION-SCREEN BEGIN OF LINE.
201  PARAMETERS p_outfi            TYPE fagl_download_first_list
202                                AS CHECKBOX
203                                USER-COMMAND dummy.
204  SELECTION-SCREEN COMMENT 3(55) gd_outfi FOR FIELD p_outfi.
205  SELECTION-SCREEN END OF LINE.
206
207  SELECTION-SCREEN BEGIN OF BLOCK b25 WITH FRAME TITLE textb25.
208  SELECTION-SCREEN BEGIN OF LINE.
209  PARAMETERS p_outli            TYPE fagl_download_display_result
210                                AS CHECKBOX MODIF ID dwn
211                                DEFAULT abap_true.
212  SELECTION-SCREEN COMMENT 3(55) gd_outli FOR FIELD p_outli.
213  SELECTION-SCREEN END OF LINE.
214
215  SELECTION-SCREEN SKIP.
216  * File Name
217  PARAMETERS p_dfile            TYPE fagl_download_filename
218                                MODIF ID dwn
219                                LOWER CASE.
220
221  * Output to presentation server
222  SELECTION-SCREEN BEGIN OF LINE.
223  PARAMETERS p_dpres            TYPE fagl_download_pres_server
224                                RADIOBUTTON GROUP dwn
225                                DEFAULT 'X'
226                                MODIF ID dwn
227                                USER-COMMAND dummy.
228  SELECTION-SCREEN COMMENT 3(55) gd_dpres FOR FIELD p_dpres.
229  SELECTION-SCREEN END OF LINE.
230
231  * Output to application server
232  SELECTION-SCREEN BEGIN OF LINE.
233  PARAMETERS p_dappl            TYPE fagl_download_appl_server
234                                RADIOBUTTON GROUP dwn.
235  SELECTION-SCREEN COMMENT 3(55) gd_dappl FOR FIELD p_dappl.
236  SELECTION-SCREEN END OF LINE.
237
238  SELECTION-SCREEN SKIP.                          "begin of "n2436588
239
240  * Output conversion for values
241  SELECTION-SCREEN BEGIN OF LINE.
242  PARAMETERS p_dconv            TYPE boole_d
```

```
243                                AS CHECKBOX
244                                MODIF ID dwn
245                                DEFAULT 'X'.
246  SELECTION-SCREEN COMMENT 3(75) gd_dconv FOR FIELD p_dconv.
247  SELECTION-SCREEN END OF LINE.                      "end of "n2436588
248
249  selection-screen begin of line.
250  parameters p_dwmta             type fagl_download_wr_meta
251                                 as checkbox default ''
252                                 modif id dwe.
253  selection-screen comment 3(55) gd_dwmta for field p_dwmta modif id dwe.
254  selection-screen end of line.
255
256  selection-screen skip.
257
258  selection-screen begin of line.
259  parameters p_dmraw             type fagl_download_mode_raw
260                                 radiobutton group dwm default 'X'
261                                 modif id dwe user-command dw_dummy.
262  selection-screen comment 3(55) gd_dmraw for field p_dmraw modif id dwe.
263  selection-screen end of line.
264  selection-screen begin of line.
265    selection-screen position 4.
266  parameters p_dwhdr             type fagl_download_wr_head
267                                 as checkbox default 'X'
268                                 modif id dwe.
269  selection-screen comment 7(55) gd_dwhdr for field p_dwhdr modif id dwe.
270  selection-screen end of line.
271  selection-screen begin of line.
272  parameters p_dmxml             type fagl_download_mode_xml
273                                 radiobutton group dwm
274                                 modif id dwe.
275  selection-screen comment 3(55) gd_dmxml for field p_dmxml modif id dwe.
276  selection-screen end of line.
277  selection-screen begin of line.
278  parameters p_dmcmp              type fagl_download_mode_cmp
279                                  radiobutton group dwm
280                                  modif id dwe.
281  selection-screen comment 3(55) gd_dmcmp for field p_dmcmp modif id dwe.
282  selection-screen end of line.
283
284  SELECTION-SCREEN END OF BLOCK b25.
285
286
287  SELECTION-SCREEN END OF BLOCK b20.
288  * end of outer frame.
289
290  *---------------------------------------------------------------------*
291  * Additional Parameters
292  *---------------------------------------------------------------------*
293  PARAMETERS psx_item
294    TYPE rsds_type
295    NO-DISPLAY.
296
297  PARAMETERS psx_kess
298    TYPE rsds_type
299    NO-DISPLAY.
300
301  PARAMETERS p_dspovr                                    "n2711621
302    TYPE boole_d                                         "n2711621
303    NO-DISPLAY.                                          "n2711621
```

```
304
305  SELECT-OPTIONS s_ccnowl                                    "n2767139
306    FOR  rfbila_sel-ccode                                    "n2767139
307    NO-DISPLAY.                                              "n2767139
308  SELECT-OPTIONS s_acnowl                                    "n2767139
309    FOR  rfbila_sel-racct                                    "n2767139
310    NO-DISPLAY.                                              "n2767139
311
312  PARAMETERS p_setidb                                        "n2869685
313    TYPE rgsb4-setnr                                         "n2869685
314    NO-DISPLAY.                                              "n2869685
315  PARAMETERS p_setidr                                        "n2869685
316    TYPE rgsb4-setnr                                         "n2869685
317    NO-DISPLAY.                                              "n2869685
318  PARAMETERS p_setidd                                        "n2869685
319    TYPE rgsb4-setnr                                         "n2869685
320    NO-DISPLAY.                                              "n2869685
321  PARAMETERS p_setidk                                        "n2869685
322    TYPE rgsb4-setnr                                         "n2869685
323    NO-DISPLAY.                                              "n2869685
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           FAGL_LINE_ITEM_BROWSER_PTOP
3  *&---------------------------------------------------------------------*
4  CONSTANTS gc_scenario             TYPE pivb_report_scenario
5                                    VALUE 'FAGL_LIB_PIVB'.
6
7  DATA gt_seltab                    TYPE pivb_frange_t.
8  DATA gt_and_seltab                TYPE pivb_trange_t. "n2647709
9  DATA gt_pivb_param                TYPE pivb_param_t.
10
11 DATA gt_column                    TYPE pivb_column_f4_t.
```

```
*&---------------------------------------------------------------------*
*&  Include           FAGL_LINE_ITEM_BROWSER_TOP
*&---------------------------------------------------------------------*
TABLES rfbila_sel.
TABLES bsis.
TABLES bseg.
TABLES glpca.                                              "n1973812
TABLES bsegh.
TABLES bsega.
TABLES rf42b.                                              "n2767139
*---------------------------------------------------------------------*
TYPE-POOLS abap.
TYPE-POOLS rsds.
TYPE-POOLS icon.
TYPE-POOLS slis.
TYPE-POOLS gusl.
TYPE-POOLS fbcon.
TYPE-POOLS vrm.
TYPE-POOLS gseth.
TYPE-POOLS kess.
*---------------------------------------------------------------------*
TYPES BEGIN OF ts_ledger_info.
TYPES   ledger                TYPE rldnr.
TYPES   tot_table             TYPE tabname.
TYPES   si_table              TYPE tabname.
TYPES END OF ts_ledger_info.

TYPES BEGIN OF ts_bkpf_key.
TYPES   rbukrs                TYPE bukrs.
TYPES   bukrs                 TYPE bukrs.
TYPES   belnr                 TYPE belnr_d.
TYPES   gjahr                 TYPE gjahr.
TYPES   buzei                 TYPE bseg-buzei.             "n2250572
TYPES END OF ts_bkpf_key.

TYPES BEGIN OF ts_fagl_key.
TYPES   rbukrs                TYPE bukrs.
TYPES   ryear                 TYPE ryear.
TYPES   docnr                 TYPE belnr_d.
TYPES   docln                 TYPE faglflexa-docln.        "n2250572
TYPES END OF ts_fagl_key.

TYPES BEGIN OF ts_pca_key.
TYPES   rbukrs                TYPE glpca-rbukrs.
TYPES   ryear                 TYPE glpca-ryear.
TYPES   docnr                 TYPE glpca-docnr.
TYPES   docty                 TYPE glpca-docty.
TYPES   activ                 TYPE glpca-activ.
TYPES   rep_matnr             TYPE glpca-rep_matnr.
TYPES   msl                   TYPE glpca-msl.
TYPES   docct                 TYPE glpca-docct.
TYPES   refdocnr              TYPE glpca-refdocnr.
TYPES   refryear              TYPE glpca-refryear.
TYPES   refdocct              TYPE glpca-refdocct.
TYPES   logsys                TYPE glpca-logsys.
TYPES   awsys                 TYPE glpca-awsys.
TYPES   awtyp                 TYPE glpca-awtyp.
TYPES   aworg                 TYPE glpca-aworg.
TYPES END OF ts_pca_key.

TYPES BEGIN OF ts_awkey.
```

```
 62  TYPES   awsys                 TYPE awsys.
 63  TYPES   awtyp                 TYPE awtyp.
 64  TYPES   awkey                 TYPE awkey.
 65  TYPES   awref                 TYPE acchd-awref.
 66  TYPES   aworg                 TYPE acchd-aworg.
 67  TYPES   refdocnr              TYPE glpca-refdocnr.
 68  TYPES END OF ts_awkey.
 69
 70  TYPES BEGIN OF ts_variants.
 71          INCLUDE STRUCTURE ltvariant.
 72  TYPES   style(3).
 73  TYPES END OF ts_variants.
 74  TYPES tt_variants             TYPE STANDARD TABLE OF ts_variants.
 75
 76  TYPES tt_fields               TYPE STANDARD TABLE OF char72
 77                                WITH DEFAULT KEY.
 78
 79  TYPES BEGIN OF tsx_stack.
 80  TYPES   t_fieldsel            TYPE tt_fields.
 81  TYPES   t_where               TYPE STANDARD TABLE OF string
 82                                WITH NON-UNIQUE DEFAULT KEY.
 83  TYPES   use_restrictions      TYPE boole_d.
 84  TYPES   t_group               TYPE tt_fields.
 85  TYPES   variant               TYPE slis_vari.
 86  TYPES   t_fieldlist           TYPE tt_fields.
 87  TYPES   t_fieldcat            TYPE lvc_t_fcat.
 88  TYPES   t_filter              TYPE lvc_t_filt.
 89  TYPES   t_sort                TYPE lvc_t_sort.
 90  TYPES   data_export_id        TYPE sychar22.
 91  TYPES END OF tsx_stack.
 92
 93  TYPES tts_curtp               TYPE SORTED TABLE OF curtp
 94                                WITH UNIQUE DEFAULT KEY.
 95  TYPES tt_string               TYPE STANDARD TABLE OF string.
 96
 97  TYPES BEGIN OF ts_user_settings.
 98  TYPES   save_sel.
 99  TYPES   popup_doc_number.
100  TYPES   popup_doc_line.
101  TYPES   popup_account.
102  TYPES   popup_vendor.
103  TYPES   popup_customer.
104  TYPES   profit_center.
105  TYPES   material.
106  TYPES END OF ts_user_settings.
107
108
109  TYPES tts_fields              TYPE SORTED TABLE OF fieldname
110                                WITH UNIQUE DEFAULT KEY.
111
112  TYPES BEGIN OF ts_text.                                    "n2318460
113  TYPES   acctp                 TYPE bseg-koart.             "n2318460
114  TYPES   account               TYPE bseg-hkont.             "n2318460
115  TYPES   txt_s                 TYPE string.                 "n2318460
116  TYPES   txt_l                 TYPE string.                 "n2318460
117  TYPES END OF ts_text.                                      "n2318460
118  TYPES tth_text                TYPE HASHED TABLE OF ts_text  "n2318460
119                                WITH UNIQUE KEY acctp account. "n2318460
120
121  types: begin of enum e_appl_view,
122          fi_entry,
```

```
123          fi_gl,
124          pca,
125          sl,
126        end of enum e_appl_view.
127  *---------------------------------------------------------------------*
128  CONSTANTS gc_owner             TYPE gl_owner
129                                 VALUE 'FAGL_BALANCE_DISPLAY'.
130  CONSTANTS gc_parameter_id      TYPE memoryid
131                                 VALUE 'GLN_FLEX'.
132  CONSTANTS BEGIN OF gc_s_ucomm.
133  CONSTANTS   alv_func_show      TYPE syucomm
134                                 VALUE 'ALV_FUNC_SHOW'.
135  CONSTANTS   alv_func_hide      TYPE syucomm
136                                 VALUE 'ALV_FUNC_HIDE'.
137  CONSTANTS   display_doc        TYPE syucomm
138                                 VALUE 'FB03'.
139  CONSTANTS   display_doc_popup TYPE syucomm
140                                 VALUE 'FB03_POPUP'.
141  CONSTANTS   display_doc_orig   TYPE syucomm
142                                 VALUE 'ORIG'.
143  CONSTANTS   display_doc_orig_popup
144                                 TYPE syucomm
145                                 VALUE 'ORIG_POPUP'.
146  CONSTANTS   display_doc_rw     TYPE syucomm
147                                 VALUE 'RWDOC'.
148  CONSTANTS   display_doc_rw_popup
149                                 TYPE syucomm
150                                 VALUE 'RWDOC_POPUP'.
151  CONSTANTS   double_click       TYPE syucomm
152                                 VALUE '&DBCK'.
153  CONSTANTS   report_call_item   TYPE syucomm
154                                 VALUE 'REPORT_CALL_LINE_ITEM'.
155  CONSTANTS   report_call        TYPE syucomm
156                                 VALUE 'REPORT_CALL'.
157  CONSTANTS   report_assign      TYPE syucomm
158                                 VALUE 'REPORT_ASSIGN'.
159  CONSTANTS   user_settings      TYPE syucomm
160                                 VALUE 'USER_SETTINGS'.
161  CONSTANTS   mass_change        TYPE syucomm                    "n2021287
162                                 VALUE 'MASS_CHANGE'.            "n2021287
163  CONSTANTS END OF gc_s_ucomm.
164
165  CONSTANTS gc_handle_main       TYPE disvariant-handle
166                                 VALUE '100'.
167  CONSTANTS gc_handle_layouts    TYPE disvariant-handle
168                                 VALUE '200'.
169
170  CONSTANTS BEGIN OF gc_s_hdb_ddic.
171  CONSTANTS   gl_view            TYPE tabname
172                                 VALUE 'V_GLPOS_N_CT'.
173  CONSTANTS   gl_view_ext        TYPE tabname
174                                 VALUE 'V_GLPOS_N_GL_CT'.
175  CONSTANTS   entry_view         TYPE tabname
176                                 VALUE 'V_GLPOS_C_CT'.
177  CONSTANTS   gl_line_items      TYPE tabname
178                                 VALUE 'V_GLPOS_C_GL_CT'.
179  CONSTANTS   ar_line_items      TYPE tabname
180                                 VALUE 'V_GLPOS_C_DEB_CT'.
181  CONSTANTS   ap_line_items      TYPE tabname
182                                 VALUE 'V_GLPOS_C_VEN_CT'.
183  CONSTANTS   pca_line_items     TYPE tabname
```

```
184                                VALUE 'V_GLPCA_CT'.
185  CONSTANTS   pca_line_items_ext TYPE tabname
186                                VALUE 'V_GLPCA_T_CT'.
187  CONSTANTS END OF gc_s_hdb_ddic.
188
189  CONSTANTS BEGIN OF gc_s_hdb_ddic_sel.
190  CONSTANTS   gl_view            TYPE tabname
191                                VALUE 'GLPOS_N_CT'.
192  CONSTANTS   gl_view_ext        TYPE tabname
193                                VALUE 'GLPOS_N_GL_CT'.
194  CONSTANTS   entry_view         TYPE tabname
195                                VALUE 'GLPOS_C_CT'.
196  CONSTANTS   gl_line_items      TYPE tabname
197                                VALUE 'GLPOS_C_GL_CT'.
198  CONSTANTS   ar_line_items      TYPE tabname
199                                VALUE 'GLPOS_C_DEB_CT'.
200  CONSTANTS   ap_line_items      TYPE tabname
201                                VALUE 'GLPOS_C_VEN_CT'.
202  CONSTANTS   pca_line_items     TYPE tabname
203                                VALUE 'GLPCA_CT'.
204  CONSTANTS   pca_line_items_ext TYPE tabname
205                                VALUE 'GLPCA_T_CT'.
206  CONSTANTS END OF gc_s_hdb_ddic_sel.
207
208  CONSTANTS BEGIN OF gc_hdb_appl.
209  CONSTANTS   financials         TYPE char5   VALUE 'FI'.
210  CONSTANTS END OF gc_hdb_appl.
211  CONSTANTS BEGIN OF gc_hdb_subappl.
212  CONSTANTS   BEGIN OF s_newgl.
213  CONSTANTS     gl_view          TYPE sytcode VALUE 'FAGLL03H_GLV'.
214  CONSTANTS     entry_view       TYPE sytcode VALUE 'FAGLL03H_EV'.
215  CONSTANTS     line_item_browser TYPE    char40              "n2166692
216                                   VALUE   'FAGL_BROWSE'.     "n2166692
217  CONSTANTS   END OF s_newgl.
218
219  CONSTANTS classic_gl           TYPE    char5
220                                 VALUE   'FIGL'.
221  CONSTANTS BEGIN OF s_classic_gl.
222  CONSTANTS   line_item_browser TYPE    char40
223                                 VALUE   'FBL3H'.
224  CONSTANTS END OF s_classic_gl.
225
226  CONSTANTS receivables          TYPE    char5
227                                 VALUE   'FIAR'.
228  CONSTANTS BEGIN OF s_receivables.
229  CONSTANTS   line_item_browser TYPE    char40
230                                 VALUE   'FBL5H'.
231  CONSTANTS END OF s_receivables.
232
233  CONSTANTS payables             TYPE    char5
234                                 VALUE   'FIAP'.
235  CONSTANTS BEGIN OF s_payables.
236  CONSTANTS   line_item_browser TYPE    char40
237                                 VALUE   'FBL1H'.
238  CONSTANTS END OF s_payables.
239
240  CONSTANTS pca                  TYPE    char5
241                                 VALUE   'PCA'.
242  CONSTANTS BEGIN OF s_pca.
243  CONSTANTS   line_item_browser TYPE    char40
244                                 VALUE   'KE5ZH'.
```

```
245  CONSTANTS END OF s_pca.
246
247  CONSTANTS BEGIN OF s_special_ledger.
248  CONSTANTS   line_item_browser TYPE    char40
249                                VALUE   'GD20H'.
250  CONSTANTS END OF s_special_ledger.
251
252  CONSTANTS END OF gc_hdb_subappl.
253
254  CONSTANTS BEGIN OF gc_hdb_range_type.
255  CONSTANTS   user              TYPE    char20
256                                VALUE   'USER'.
257  CONSTANTS   report            TYPE    char20
258                                VALUE   'REPORT'.
259  CONSTANTS   datasource        TYPE    char20
260                                VALUE   'DATASOURCE'.
261  CONSTANTS   sel_max_data      TYPE    char20                  "n1974538
262                                VALUE   'SEL_MAX_ENTRIES'.      "n1974538
263  CONSTANTS   sel_max_hier      TYPE    char20                  "n1974538
264                                VALUE   'SEL_MAX_HIER'.         "n1974538
265  CONSTANTS   sel_view          TYPE    char20
266                                VALUE   'SEL_VIEW'.
267  CONSTANTS   sel_view_x        TYPE    char20
268                                VALUE   'SEL_VIEW_X'.
269  CONSTANTS   sel_view_fm       TYPE    char20
270                                VALUE   'SEL_VIEW_FM'.
271  CONSTANTS   sel_view_warn     TYPE    char20
272                                VALUE   'SEL_VIEW_WARN'.
273  CONSTANTS   sel_screen_dynsel TYPE    char20
274                                VALUE   'SEL_SCREEN_DYNSEL'.
275  CONSTANTS   sel_screen_ledger TYPE    char20
276                                VALUE   'SEL_SCREEN_LEDGER'.
277  CONSTANTS   sel_screen_yrper  TYPE    char20
278                                VALUE   'SEL_SCREEN_YEARPER'.
279  CONSTANTS   report_assign     TYPE    char20
280                                VALUE   'REPORT_ASSIGN'.
281  CONSTANTS   disable_kess      TYPE    char20                    "n2636622
282                                VALUE   'DISABLE_KESS_SCREEN'.    "n2636622
283  CONSTANTS END OF gc_hdb_range_type.
284
285  CONSTANTS BEGIN OF gc_s_hdb_ledger_sel.
286  CONSTANTS   dialog            VALUE space.
287  CONSTANTS   all_users         VALUE '1'.
288  CONSTANTS   some_users        VALUE '2'.
289  CONSTANTS END OF gc_s_hdb_ledger_sel.
290
291  CONSTANTS BEGIN OF gc_s_hdb_yearper_sel.
292  CONSTANTS   nobody            VALUE space.
293  CONSTANTS   all_users         VALUE '1'.
294  CONSTANTS   some_users        VALUE '2'.
295  CONSTANTS END OF gc_s_hdb_yearper_sel.
296
297  CONSTANTS BEGIN OF gc_s_hdb_report_assign.
298  CONSTANTS   require_hdbc      VALUE space.
299  CONSTANTS   all_users         VALUE '1'.
300  CONSTANTS   some_users        VALUE '2'.
301  CONSTANTS END OF gc_s_hdb_report_assign.
302
303  CONSTANTS BEGIN OF gc_s_acctp.
304  CONSTANTS   gl_account        TYPE koart VALUE 'S'.
305  CONSTANTS   customer          TYPE koart VALUE 'D'.
```

```
306  CONSTANTS   vendor            TYPE koart VALUE 'K'.
307  CONSTANTS END OF gc_s_acctp.
308
309  CONSTANTS gc_hdb_data_source  TYPE  hdb_range_type
310                                VALUE 'HDB_DATA_SOURCE'.
311
312  CONSTANTS BEGIN OF gc_s_setclass.
313  CONSTANTS   pc_group          LIKE sethier-setclass
314                                VALUE '0106'.
315  CONSTANTS   acct_group        LIKE sethier-setclass
316                                VALUE '0109'.
317  CONSTANTS END OF gc_s_setclass.
318  *---------------------------------------------------------------------*
319  DATA gcx_exception            TYPE REF TO cx_dynamic_check.
320  *---------------------------------------------------------------------*
321  DATA go_main_container        TYPE REF TO cl_gui_custom_container.
322  DATA go_main_splitter         TYPE REF TO cl_gui_splitter_container.
323  DATA go_contain_main_grid     TYPE REF TO cl_gui_container.
324  DATA go_main_grid             TYPE REF TO cl_gui_alv_grid.
325  DATA go_contain_layout_grid   TYPE REF TO cl_gui_container.
326  DATA go_layout_grid           TYPE REF TO cl_gui_alv_grid.
327  DATA gd_variant(12).
328  DATA gd_sel_view              TYPE tabname.
329  data gd_base_view             type tabname.
330  DATA gd_subapplication        TYPE fbcon_s_hdb-subappl.
331  data gd_cds_on                type abap_bool.
332  data gd_reload_sview          type abap_bool.
333  DATA gd_free_sel_number       TYPE i.
334  DATA gd_item_sel_number       TYPE i.
335  DATA gd_exit.
336  DATA gd_title                 TYPE string.
337
338  CLASS lcl_grid_event_receiver DEFINITION DEFERRED.
339  DATA go_grid_event_receiver TYPE REF TO lcl_grid_event_receiver.
340
341  DATA gd_dbcon_name            TYPE dbcon_name.
342  DATA ok_code                  TYPE syucomm.
343  *---------------------------------------------------------------------*
344  DATA gt_fieldlist             TYPE tt_fields.
345  DATA gt_fieldsel              TYPE tt_fields.
346  DATA gt_component             TYPE abap_component_tab.
347  DATA go_struc_type            TYPE REF TO cl_abap_structdescr.
348  DATA go_tab_type              TYPE REF TO cl_abap_tabledescr.
349  DATA gr_table                 TYPE REF TO data.
350  DATA gt_group                 TYPE tt_fields.
351  DATA gt_fieldcat              TYPE lvc_t_fcat.
352  DATA gt_fieldcat_save         TYPE lvc_t_fcat.              "n2204740
353  DATA gt_special_groups        TYPE lvc_t_sgrp.
354  DATA gt_filter                TYPE lvc_t_filt.
355  DATA gt_sort                  TYPE lvc_t_sort.
356
357  DATA gt_variants              TYPE tt_variants.
358
359  DATA gt_stack                 TYPE STANDARD TABLE OF tsx_stack.
360  DATA gt_where                 TYPE STANDARD TABLE OF string.
361  DATA gd_use_restrictions.
362  DATA gd_many_recs_ok.
363  DATA gd_doc_key_in_display.
364  DATA gd_doc_line_key_in_display.                            "n2250572
365  DATA gd_where_date            TYPE string.
366  DATA gd_where_date_oi         TYPE sydatum.
```

```
367  DATA gd_hide_appl.
368  DATA gd_alv_func_show.
369  DATA gd_hdb_is_primary.
370  DATA gt_guid_stack             TYPE STANDARD TABLE OF sychar22.
371  DATA gd_create_file.
372  DATA gd_shared_buffer_max_size TYPE i.
373  DATA text044                   TYPE textpool-entry.          "n1974538
374  DATA text045                   TYPE textpool-entry.
375  DATA text046                   TYPE textpool-entry.          "n2247001
376  DATA gd_sel_limit_data         TYPE i.                       "n1974538
377  DATA gd_sel_limit_hier         TYPE i.                       "n1974538
378
379  DATA gts_curtp                 TYPE tts_curtp.
380
381  DATA gs_user_settings          TYPE ts_user_settings.
382
383
384  CONSTANTS gc_check_file        TYPE fileintern
385                                 VALUE 'FI_EXTERNAL'.
386
387  FIELD-SYMBOLS <gt_table>       TYPE STANDARD TABLE.
388
389  DATA gr_screen                 TYPE REF TO cl_kess_free_selection.
390  DATA gd_disable_kess           TYPE char1.                   "n2636622
391  DATA gd_ledger                 TYPE rldnr.
392
393  DATA gd_first_init.
394
395  DATA gd_modif_2818431          TYPE c VALUE abap_undefined.  "n2816760
396
397  DATA go_badi_lib               TYPE REF TO fagl_lib.
398  DATA gt_message                TYPE bapirettab.              "n2204740
399  DATA go_contain_msg            TYPE REF TO cl_gui_docking_container. "n22
     04740
400  DATA gs_variant                TYPE disvariant.              "n2247001
401  DATA gd_save.                                                "n2247001
402  DATA gs_layout                 TYPE lvc_s_layo.              "n2247001
403  DATA gd_consider_worklists     TYPE boole_d VALUE abap_undefined."n276713
     9
404  DATA gd_consider_sets          TYPE boole_d VALUE abap_undefined."n286968
     5
405  DATA gd_worklist_active        TYPE boole_d VALUE abap_undefined."n276713
     9
406  DATA gd_sets_active            TYPE boole_d VALUE abap_undefined."n286968
     5
407  DATA: BEGIN OF gs_reset_selection,                           "n286968
     5
408          ccode     TYPE boole_d,                             "n286968
     5
409          racct     TYPE boole_d,                             "n286968
     5
410          vendor    TYPE boole_d,                             "n286968
     5
411          customer  TYPE boole_d,                             "n286968
     5
412        END OF gs_reset_selection.                            "n286968
     5
413  DATA: BEGIN OF gs_text_wl,                                   "n276713
     9
414      activate    TYPE string,                                "n276713
     9
```

```
415       deactivate  TYPE string,                                    "n276713
    9
416     END OF gs_text_wl.                                            "n276713
    9
417     DATA: BEGIN OF gs_text_set,                                   "n286968
    5
418       activate    TYPE string,                                    "n286968
    5
419       deactivate  TYPE string,                                    "n286968
    5
420     END OF gs_text_set.                                           "n286968
    5
421
422   DATA gv_lib_prctr_grp_select   TYPE fagl_settings-param_value.  "3031177
423   DATA gt_ra_prctr               TYPE rsdsselopt_t.               "3031177
424   DATA gt_ra_racct               TYPE rsdsselopt_t.
425
426   data go_util type ref to cl_fagl_lib_util.
427   data gv_ext_download_options type abap_bool.
428
429   data ge_appl_view type e_appl_view.
```

```
1  *---------------------------------------------------------------------*
2  ***INCLUDE FIND_RELEVANT_LEDGER .
3  *---------------------------------------------------------------------*
4  *&---------------------------------------------------------------------*
5  *&      Form  find_relevant_ledger
6  *&---------------------------------------------------------------------*
7  FORM find_relevant_ledger CHANGING cc_relevant_ledger TYPE fagl_rldnr.
8
9  *  DATA lv_return_code TYPE syst-subrc.
10 *  DATA lv_ledger_user_format TYPE usr05-parva.
11
12 * Access to user master data for the ledger.
13 * open question: Is the parameter ID correct?
14
15 *  CALL FUNCTION 'G_GET_USER_PARAMETER'
16 *    EXPORTING
17 *      parameter_id    = 'GLN_FLEX'
18 *    IMPORTING
19 *      parameter_value = lv_ledger_user_format
20 *      rc              = lv_return_code.
21
22   call function 'GL_USER_DATA_GET'
23     exporting
24       owner          = gc_owner
25       name           = gc_parameter_id
26     importing
27       value          = cc_relevant_ledger
28     exceptions
29       invalid_owner  = 1
30       name_not_found = 2.
31
32 *  cc_relevant_ledger = lv_ledger_user_format.
33
34   IF sy-subrc NE 0.
35 * default ledger.
36     CALL FUNCTION 'FAGL_GET_LEADING_LEDGER'
37       IMPORTING
38         e_rldnr   = cc_relevant_ledger
39       EXCEPTIONS
40         not_found = 1.
41
42     IF sy-subrc <> 0.
43 * MESSAGE ID SY-MSGID TYPE SY-MSGTY NUMBER SY-MSGNO
44 *         WITH SY-MSGV1 SY-MSGV2 SY-MSGV3 SY-MSGV4.
45     ENDIF.
46   ENDIF.
47
48 ENDFORM.                    " find_relevant_ledger
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           RKESS_CHARACTERISTICS
3  *&---------------------------------------------------------------------*
4
5  *** Dynamic SELECT-OPTIONS for Characteristics
6  SELECTION-SCREEN BEGIN OF LINE.
7      SELECTION-SCREEN COMMENT 1(25) TXT_C01 FOR FIELD SO_C01 MODIF ID SSC
   .
8      SELECTION-SCREEN POSITION 28.
9      SELECT-OPTIONS    SO_C01     FOR (PAR_C01)      MODIF ID SSC.
10 SELECTION-SCREEN END OF LINE.
11
12 SELECTION-SCREEN BEGIN OF LINE.
13     SELECTION-SCREEN COMMENT 1(25) TXT_C02 FOR FIELD SO_C02 MODIF ID SSC
   .
14     SELECTION-SCREEN POSITION 28.
15     SELECT-OPTIONS    SO_C02     FOR (PAR_C02)      MODIF ID SSC.
16 SELECTION-SCREEN END OF LINE.
17
18 SELECTION-SCREEN BEGIN OF LINE.
19     SELECTION-SCREEN COMMENT 1(25) TXT_C03 FOR FIELD SO_C03 MODIF ID SSC
   .
20     SELECTION-SCREEN POSITION 28.
21     SELECT-OPTIONS    SO_C03     FOR (PAR_C03)      MODIF ID SSC.
22 SELECTION-SCREEN END OF LINE.
23
24 SELECTION-SCREEN BEGIN OF LINE.
25     SELECTION-SCREEN COMMENT 1(25) TXT_C04 FOR FIELD SO_C04 MODIF ID SSC
   .
26     SELECTION-SCREEN POSITION 28.
27     SELECT-OPTIONS    SO_C04     FOR (PAR_C04)      MODIF ID SSC.
28 SELECTION-SCREEN END OF LINE.
29
30 SELECTION-SCREEN BEGIN OF LINE.
31     SELECTION-SCREEN COMMENT 1(25) TXT_C05 FOR FIELD SO_C05 MODIF ID SSC
   .
32     SELECTION-SCREEN POSITION 28.
33     SELECT-OPTIONS    SO_C05     FOR (PAR_C05)      MODIF ID SSC.
34 SELECTION-SCREEN END OF LINE.
35
36 SELECTION-SCREEN BEGIN OF LINE.
37     SELECTION-SCREEN COMMENT 1(25) TXT_C06 FOR FIELD SO_C06 MODIF ID SSC
   .
38     SELECTION-SCREEN POSITION 28.
39     SELECT-OPTIONS    SO_C06     FOR (PAR_C06)      MODIF ID SSC.
40 SELECTION-SCREEN END OF LINE.
41
42 SELECTION-SCREEN BEGIN OF LINE.
43     SELECTION-SCREEN COMMENT 1(25) TXT_C07 FOR FIELD SO_C07 MODIF ID SSC
   .
44     SELECTION-SCREEN POSITION 28.
45     SELECT-OPTIONS    SO_C07     FOR (PAR_C07)      MODIF ID SSC.
46 SELECTION-SCREEN END OF LINE.
47
48 SELECTION-SCREEN BEGIN OF LINE.
49     SELECTION-SCREEN COMMENT 1(25) TXT_C08 FOR FIELD SO_C08 MODIF ID SSC
   .
50     SELECTION-SCREEN POSITION 28.
51     SELECT-OPTIONS    SO_C08     FOR (PAR_C08)      MODIF ID SSC.
52 SELECTION-SCREEN END OF LINE.
53
```

```
 54  SELECTION-SCREEN BEGIN OF LINE.
 55      SELECTION-SCREEN COMMENT 1(25) TXT_C09 FOR FIELD SO_C09 MODIF ID SSC
     .
 56      SELECTION-SCREEN POSITION 28.
 57      SELECT-OPTIONS    SO_C09     FOR (PAR_C09)      MODIF ID SSC.
 58  SELECTION-SCREEN END OF LINE.
 59
 60  SELECTION-SCREEN BEGIN OF LINE.
 61      SELECTION-SCREEN COMMENT 1(25) TXT_C10 FOR FIELD SO_C10 MODIF ID SSC
     .
 62      SELECTION-SCREEN POSITION 28.
 63      SELECT-OPTIONS    SO_C10     FOR (PAR_C10)      MODIF ID SSC.
 64  SELECTION-SCREEN END OF LINE.
 65
 66  SELECTION-SCREEN BEGIN OF LINE.
 67      SELECTION-SCREEN COMMENT 1(25) TXT_C11 FOR FIELD SO_C11 MODIF ID SSC
     .
 68      SELECTION-SCREEN POSITION 28.
 69      SELECT-OPTIONS    SO_C11     FOR (PAR_C11)      MODIF ID SSC.
 70  SELECTION-SCREEN END OF LINE.
 71
 72  SELECTION-SCREEN BEGIN OF LINE.
 73      SELECTION-SCREEN COMMENT 1(25) TXT_C12 FOR FIELD SO_C12 MODIF ID SSC
     .
 74      SELECTION-SCREEN POSITION 28.
 75      SELECT-OPTIONS    SO_C12     FOR (PAR_C12)      MODIF ID SSC.
 76  SELECTION-SCREEN END OF LINE.
 77
 78  SELECTION-SCREEN BEGIN OF LINE.
 79      SELECTION-SCREEN COMMENT 1(25) TXT_C13 FOR FIELD SO_C13 MODIF ID SSC
     .
 80      SELECTION-SCREEN POSITION 28.
 81      SELECT-OPTIONS    SO_C13     FOR (PAR_C13)      MODIF ID SSC.
 82  SELECTION-SCREEN END OF LINE.
 83
 84  SELECTION-SCREEN BEGIN OF LINE.
 85      SELECTION-SCREEN COMMENT 1(25) TXT_C14 FOR FIELD SO_C14 MODIF ID SSC
     .
 86      SELECTION-SCREEN POSITION 28.
 87      SELECT-OPTIONS    SO_C14     FOR (PAR_C14)      MODIF ID SSC.
 88  SELECTION-SCREEN END OF LINE.
 89
 90  SELECTION-SCREEN BEGIN OF LINE.
 91      SELECTION-SCREEN COMMENT 1(25) TXT_C15 FOR FIELD SO_C15 MODIF ID SSC
     .
 92      SELECTION-SCREEN POSITION 28.
 93      SELECT-OPTIONS    SO_C15     FOR (PAR_C15)      MODIF ID SSC.
 94  SELECTION-SCREEN END OF LINE.
 95
 96  SELECTION-SCREEN BEGIN OF LINE.
 97      SELECTION-SCREEN COMMENT 1(25) TXT_C16 FOR FIELD SO_C16 MODIF ID SSC
     .
 98      SELECTION-SCREEN POSITION 28.
 99      SELECT-OPTIONS    SO_C16     FOR (PAR_C16)      MODIF ID SSC.
100  SELECTION-SCREEN END OF LINE.
101
102  SELECTION-SCREEN BEGIN OF LINE.
103      SELECTION-SCREEN COMMENT 1(25) TXT_C17 FOR FIELD SO_C17 MODIF ID SSC
     .
104      SELECTION-SCREEN POSITION 28.
105      SELECT-OPTIONS    SO_C17     FOR (PAR_C17)      MODIF ID SSC.
```

```
106  SELECTION-SCREEN END OF LINE.
107
108  SELECTION-SCREEN BEGIN OF LINE.
109      SELECTION-SCREEN COMMENT 1(25) TXT_C18 FOR FIELD SO_C18 MODIF ID SSC
     .
110      SELECTION-SCREEN POSITION 28.
111      SELECT-OPTIONS    SO_C18     FOR (PAR_C18)      MODIF ID SSC.
112  SELECTION-SCREEN END OF LINE.
113
114  SELECTION-SCREEN BEGIN OF LINE.
115      SELECTION-SCREEN COMMENT 1(25) TXT_C19 FOR FIELD SO_C19 MODIF ID SSC
     .
116      SELECTION-SCREEN POSITION 28.
117      SELECT-OPTIONS    SO_C19     FOR (PAR_C19)      MODIF ID SSC.
118  SELECTION-SCREEN END OF LINE.
119
120  SELECTION-SCREEN BEGIN OF LINE.
121      SELECTION-SCREEN COMMENT 1(25) TXT_C20 FOR FIELD SO_C20 MODIF ID SSC
     .
122      SELECTION-SCREEN POSITION 28.
123      SELECT-OPTIONS    SO_C20     FOR (PAR_C20)      MODIF ID SSC.
124  SELECTION-SCREEN END OF LINE.
125
126  SELECTION-SCREEN BEGIN OF LINE.
127      SELECTION-SCREEN COMMENT 1(25) TXT_C21 FOR FIELD SO_C21 MODIF ID SSC
     .
128      SELECTION-SCREEN POSITION 28.
129      SELECT-OPTIONS    SO_C21     FOR (PAR_C21)      MODIF ID SSC.
130  SELECTION-SCREEN END OF LINE.
131
132  SELECTION-SCREEN BEGIN OF LINE.
133      SELECTION-SCREEN COMMENT 1(25) TXT_C22 FOR FIELD SO_C22 MODIF ID SSC
     .
134      SELECTION-SCREEN POSITION 28.
135      SELECT-OPTIONS    SO_C22     FOR (PAR_C22)      MODIF ID SSC.
136  SELECTION-SCREEN END OF LINE.
137
138  SELECTION-SCREEN BEGIN OF LINE.
139      SELECTION-SCREEN COMMENT 1(25) TXT_C23 FOR FIELD SO_C23 MODIF ID SSC
     .
140      SELECTION-SCREEN POSITION 28.
141      SELECT-OPTIONS    SO_C23     FOR (PAR_C23)      MODIF ID SSC.
142  SELECTION-SCREEN END OF LINE.
143
144  SELECTION-SCREEN BEGIN OF LINE.
145      SELECTION-SCREEN COMMENT 1(25) TXT_C24 FOR FIELD SO_C24 MODIF ID SSC
     .
146      SELECTION-SCREEN POSITION 28.
147      SELECT-OPTIONS    SO_C24     FOR (PAR_C24)      MODIF ID SSC.
148  SELECTION-SCREEN END OF LINE.
149
150  SELECTION-SCREEN BEGIN OF LINE.
151      SELECTION-SCREEN COMMENT 1(25) TXT_C25 FOR FIELD SO_C25 MODIF ID SSC
     .
152      SELECTION-SCREEN POSITION 28.
153      SELECT-OPTIONS    SO_C25     FOR (PAR_C25)      MODIF ID SSC.
154  SELECTION-SCREEN END OF LINE.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           RKESS_EVENTS
3  *&---------------------------------------------------------------------*
4  *&                    Don't change this coding !!!
5  *&---------------------------------------------------------------------*
6  *&                    ABAP EVENTS HANDLING
7  *&---------------------------------------------------------------------*
8
9  ************************************************************************
10 ***   INITIALIZATION.   ***********************************************
11 ************************************************************************
12 INITIALIZATION.
13
14   SS_GR_EXT = CL_KESS_FREE_SELECTION=>GET_INSTANCE( ).
15 * Is it already 'running session'? IF so there is data in memory
16   CL_KESS_FREE_SELECTION_INT=>IMPORT_INSTANCE( IMPORTING
17                                                E_REF = SS_GR_INT
18                                                E_FIRST_INIT = SS_GD-FI
   RST_INIT ).
19   SS_GR_EXT->SET_INT_REF( SS_GR_INT ).
20
21 * read default texts
22   PERFORM SS_INIT_READ_TEXPOOL.
23 *** Custom extension
24 *** Selection screen initialization - called only once on beginning
25   IF SS_GD-FIRST_INIT = ABAP_TRUE AND SY-BATCH IS INITIAL.
26     SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_INIT_SEL_SCREEN ).
27   ENDIF.
28
29 *** Standard initialization - called always
30   SS_GR_EXT->RAISE( I_EVENT      = SS_GR_EXT->EVENT_INITIALIZATION
31                     I_FIRST_INIT = SS_GD-FIRST_INIT ).
32
33   IF  SY-BATCH IS INITIAL.
34 ** standard init (based on custom initialization)
35     PERFORM SS_EVENT_INITIALIZATION.
36   ENDIF.
37
38 * Transaction KE25 is not supported anymore in S/4Hana Cloud
39 * from release S/4Hana Cloud 1902
40   IF cl_fco_copa_feature_handle=>is_reduced_copa_a000_active( ) = abap_t
   rue AND
41        sy-tcode = 'KE25'.
42     MESSAGE i101(fco_copa) WITH sy-tcode.
43     SET SCREEN '0000'.
44     LEAVE SCREEN.
45   ENDIF.
46
47   " If parallel accounting is ON only Event-Based Production Accounting
48   " is allowed, Period-End Production Accounting is not allowed.
49   cl_fco_pcc_op_restriction=>is_tcode_dactvtd_for_upa_on( sy-tcode ).
50
51
52 ************************************************************************
53 ***   AT SELECTION-SCREEN ON EXIT-COMMAND           ******************
54 ************************************************************************
55 AT SELECTION-SCREEN ON EXIT-COMMAND.
56
57 *** Adjusted Variant upload
58   IF SSCRFIELDS-UCOMM = 'GET'.
59     CLEAR SSCRFIELDS-UCOMM.
```

```
60      PERFORM SS_EVENT_SY_UCOMM_GET.
61      LEAVE SCREEN.
62    ENDIF.
63
64    SS_GR_INT->CLEAR_MEMORY( ).
65  *** Custom extension of event
66    SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_ON_EXIT_COMMAND ).
67
68  ************************************************************************
69  ***   AT SELECTION-SCREEN ON VALUE REQUEST          ******************
70  ************************************************************************
71  ***   AT SELECTION-SCREEN.   ***********************************************
72  AT SELECTION-SCREEN.
73
74    CASE SY-UCOMM.
75      WHEN 'PUSHDEFI'.
76        PERFORM SS_EVENT_SY_UCOMM_PUSHDEFI.
77
78      WHEN 'PUSHSAVE'.
79        PERFORM SS_EVENT_SY_UCOMM_PUSHSAVE.
80
81      WHEN 'PUSHMANA'.
82        PERFORM SS_EVENT_SY_UCOMM_PUSHMANA.
83
84      WHEN 'PUSHSLCR'.
85        PERFORM SS_EVENT_SY_UCOMM_PUSHSLCR.
86
87      WHEN 'PUSHTABL'.
88        PERFORM SS_EVENT_SY_UCOMM_PUSHTABL.
89
90      WHEN 'PUSHTNAM'.
91        IF TECHNAME = ABAP_TRUE.
92          TECHNAME = ABAP_FALSE.
93        ELSE.
94          TECHNAME = ABAP_TRUE.
95        ENDIF.
96
97      WHEN 'EXP'.
98        EXPERT = ABAP_TRUE.
99
100     WHEN OTHERS.
101   ENDCASE.
102
103 *** Adjusted Variant upload
104   IF SSCRFIELDS-UCOMM = 'GET'.
105     CLEAR SSCRFIELDS-UCOMM.
106     PERFORM SS_EVENT_SY_UCOMM_GET.
107   ENDIF.
108
109   IF SS_GR_INT->VARIANT_NAME IS NOT INITIAL.
110     DATA(L_KESSTABL) = KESSTABL.
111     DATA: LD_PRGNAME LIKE SYST-CPROG.
112     LD_PRGNAME = PRGNAME.
113     CALL FUNCTION 'RS_SUPPORT_SELECTIONS'
114       EXPORTING
115         REPORT                     = SY-CPROG
116         VARIANT                    = SS_GR_INT->VARIANT_NAME
117       EXCEPTIONS
118         VARIANT_NOT_EXISTENT       = 1
119         VARIANT_OBSOLETE           = 2
120         OTHERS                     = 3.
```

```
121
122       IF SY-SUBRC <> 0.
123         CASE SY-SUBRC.
124           WHEN 1.
125             MESSAGE I612(DB) WITH SS_GR_INT->VARIANT_NAME SY-CPROG.
126           WHEN 2.
127             MESSAGE I634(DB) WITH SS_GR_INT->VARIANT_NAME SY-CPROG.
128           WHEN 3.
129             MESSAGE X612(DB) WITH SS_GR_INT->VARIANT_NAME SY-CPROG.
130         ENDCASE.
131       ENDIF.
132
133       IF KESSTABL IS INITIAL.
134         KESSTABL = L_KESSTABL.
135       ENDIF.
136
137       IF PRGNAME IS INITIAL.
138         PRGNAME = LD_PRGNAME.
139       ENDIF.
140
141       DATA: S_SS_SF  LIKE LINE OF T_SS_SF,
142             S_SS_EF  LIKE LINE OF T_SS_EF,
143             EXISTS   TYPE SAP_BOOL,
144             S_SEQ    LIKE LINE OF SS_GR_INT->T_SS_SF.
145
146       REFRESH SS_GR_INT->T_SS_CLEAR.
147
148   *** selected fields
149       LOOP AT T_SS_SF INTO S_SS_SF.
150
151         READ TABLE SS_GR_INT->T_SS_EF WITH KEY TABLE_LINE = S_SS_SF-HIGH T
      RANSPORTING NO FIELDS.
152
153         IF SY-SUBRC = 0.
154           SS_TFNAME = S_SS_SF-HIGH.
155           PERFORM SS_SO_UNASSIGN
156             USING SS_TFNAME.
157         ENDIF.
158
159   ** check whether field (still) exists in the table/structure def
160         PERFORM SS_CHECK_FIELD_EXISTS
161           USING
162             S_SS_SF-HIGH
163           CHANGING
164             EXISTS.
165
166         IF EXISTS = ABAP_TRUE.
167
168           S_SEQ-TFNAME   = S_SS_SF-HIGH.
169           S_SEQ-SEQUENCE = S_SS_SF-LOW.
170
171           APPEND S_SEQ TO SS_GR_INT->T_SS_SF.
172
173         ENDIF.
174       ENDLOOP.
175
176       SORT SS_GR_INT->T_SS_SF BY SEQUENCE.
177
178       CLEAR SS_GR_INT->VARIANT_NAME.
179
180       PERFORM SS_SYNC_PAR_TO_GS.
```

```
181   ENDIF.
182
183   SS_GR_EXT->RAISE( I_EVENT      = SS_GR_EXT->EVENT_AT_SEL_SCREEN
184                     I_SIMUL_EXEC = SS_GD-SIMUL_EXEC ).
185
186 ************************************************************************
187 ***   AT SELECTION-SCREEN OUTPUT.   ***********************************
188 ************************************************************************
189 AT SELECTION-SCREEN OUTPUT.
190
191 *** Dynamic select-options, definition and expert mode subscreen handlin
    g
192   PERFORM SS_EVENT_AT_SELSCR_OUTPUT.
193 *** Custom Extension of event
194   SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_AT_SEL_SCREEN_OUTPUT ).
195
196 ************************************************************************
197 ***   START-OF-SELECTION           ************************************
198 ************************************************************************
199 START-OF-SELECTION.
200
201 * Transaction KE25 is not supported anymore in S/4Hana Cloud
202 * from release S/4Hana Cloud 1902
203   IF cl_fco_copa_feature_handle=>is_reduced_copa_a000_active( ) = abap_t
    rue AND
204        sy-tcode = 'KE25'.
205     MESSAGE i101(fco_copa) WITH sy-tcode.
206     SET SCREEN '0000'.
207     LEAVE SCREEN.
208   ENDIF.
209
210 *** "Simulated" execution ?
211     IF SS_GD-SIMUL_EXEC    = ABAP_TRUE.
212       EXIT.
213     ENDIF.
214     SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_START_OF_SELECTION ).
215
216 ************************************************************************
217 ***   AT SELECTION-SCREEN ON VALUE REQUEST          ******************
218 ************************************************************************
219 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SCRNAME.
220   PERFORM SS_SCREEN_CHECK_CHANGED.
221
222 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C01-LOW.
223   ASSIGN SO_C01-LOW TO <FS>.
224   PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C01.
225
226 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C01-HIGH.
227   ASSIGN SO_C01-HIGH TO <FS>.
228   PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C01.
229
230 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C02-LOW.
231   ASSIGN SO_C02-LOW TO <FS>.
232   PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C02.
233
234 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C02-HIGH.
235   ASSIGN SO_C02-HIGH TO <FS>.
236   PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C02.
237
238 AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C03-LOW.
239   ASSIGN SO_C03-LOW TO <FS>.
```

```
240    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C03.
241
242  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C03-HIGH.
243    ASSIGN SO_C03-HIGH TO <FS>.
244    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C03.
245
246  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C04-LOW.
247    ASSIGN SO_C04-LOW TO <FS>.
248    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C04.
249
250  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C04-HIGH.
251    ASSIGN SO_C04-HIGH TO <FS>.
252    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C04.
253
254  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C05-LOW.
255    ASSIGN SO_C05-LOW TO <FS>.
256    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C05.
257
258  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C05-HIGH.
259    ASSIGN SO_C05-HIGH TO <FS>.
260    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C05.
261
262  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C06-LOW.
263    ASSIGN SO_C06-LOW TO <FS>.
264    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C06.
265
266  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C06-HIGH.
267    ASSIGN SO_C06-HIGH TO <FS>.
268    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C06.
269
270  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C07-LOW.
271    ASSIGN SO_C07-LOW TO <FS>.
272    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C07.
273
274  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C07-HIGH.
275    ASSIGN SO_C07-HIGH TO <FS>.
276    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C07.
277
278  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C08-LOW.
279    ASSIGN SO_C08-LOW TO <FS>.
280    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C08.
281
282  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C08-HIGH.
283    ASSIGN SO_C08-HIGH TO <FS>.
284    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C08.
285
286  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C09-LOW.
287    ASSIGN SO_C09-LOW TO <FS>.
288    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C09.
289
290  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C09-HIGH.
291    ASSIGN SO_C09-HIGH TO <FS>.
292    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C09.
293
294  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C10-LOW.
295    ASSIGN SO_C10-LOW TO <FS>.
296    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C10.
297
298  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C10-HIGH.
299    ASSIGN SO_C10-HIGH TO <FS>.
300    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C10.
```

```
301
302  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C11-LOW.
303    ASSIGN SO_C11-LOW TO <FS>.
304    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C11.
305
306  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C11-HIGH.
307    ASSIGN SO_C11-HIGH TO <FS>.
308    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C11.
309
310  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C12-LOW.
311    ASSIGN SO_C12-LOW TO <FS>.
312    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C12.
313
314  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C12-HIGH.
315    ASSIGN SO_C12-HIGH TO <FS>.
316    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C12.
317
318  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C13-LOW.
319    ASSIGN SO_C13-LOW TO <FS>.
320    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C13.
321
322  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C13-HIGH.
323    ASSIGN SO_C13-HIGH TO <FS>.
324    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C13.
325
326  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C14-LOW.
327    ASSIGN SO_C14-LOW TO <FS>.
328    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C14.
329
330  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C14-HIGH.
331    ASSIGN SO_C14-HIGH TO <FS>.
332    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C14.
333
334  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C15-LOW.
335    ASSIGN SO_C15-LOW TO <FS>.
336    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C15.
337
338  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C15-HIGH.
339    ASSIGN SO_C15-HIGH TO <FS>.
340    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C15.
341
342  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C16-LOW.
343    ASSIGN SO_C16-LOW TO <FS>.
344    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C16.
345
346  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C16-HIGH.
347    ASSIGN SO_C16-HIGH TO <FS>.
348    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C16.
349
350  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C17-LOW.
351    ASSIGN SO_C17-LOW TO <FS>.
352    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C17.
353
354  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C17-HIGH.
355    ASSIGN SO_C17-HIGH TO <FS>.
356    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C17.
357
358  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C18-LOW.
359    ASSIGN SO_C18-LOW TO <FS>.
360    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C18.
361
```

```
362  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C18-HIGH.
363    ASSIGN SO_C18-HIGH TO <FS>.
364    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C18.
365
366  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C19-LOW.
367    ASSIGN SO_C19-LOW TO <FS>.
368    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C19.
369
370  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C19-HIGH.
371    ASSIGN SO_C19-HIGH TO <FS>.
372    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C19.
373
374  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C20-LOW.
375    ASSIGN SO_C20-LOW TO <FS>.
376    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C20.
377
378  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C20-HIGH.
379    ASSIGN SO_C20-HIGH TO <FS>.
380    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C20.
381
382  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C21-LOW.
383    ASSIGN SO_C21-LOW TO <FS>.
384    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C21.
385
386  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C21-HIGH.
387    ASSIGN SO_C21-HIGH TO <FS>.
388    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C21.
389
390  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C22-LOW.
391    ASSIGN SO_C22-LOW TO <FS>.
392    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C22.
393
394  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C22-HIGH.
395    ASSIGN SO_C22-HIGH TO <FS>.
396    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C22.
397
398  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C23-LOW.
399    ASSIGN SO_C23-LOW TO <FS>.
400    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C23.
401
402  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C23-HIGH.
403    ASSIGN SO_C23-HIGH TO <FS>.
404    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C23.
405
406  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C24-LOW.
407    ASSIGN SO_C24-LOW TO <FS>.
408    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C24.
409
410  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C24-HIGH.
411    ASSIGN SO_C24-HIGH TO <FS>.
412    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C24.
413
414  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C25-LOW.
415    ASSIGN SO_C25-LOW TO <FS>.
416    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C25.
417
418  AT SELECTION-SCREEN ON VALUE-REQUEST FOR SO_C25-HIGH.
419    ASSIGN SO_C25-HIGH TO <FS>.
420    PERFORM SS_EVENT_ON_VALUE_REQUEST USING PAR_C25.
```

```
1  ************************************************************************
2  ********* DON'T CHANGE CODING OF THIS INCLUDE!!! ************************
3  ************************************************************************
4
5  *&---------------------------------------------------------------------*
6  *&  Include           ZLC_SS_FORMS
7  *&---------------------------------------------------------------------*
8  *----------------------------------------------------------------------*
9  *       CLASS lcl_handle_events IMPLEMENTATION
10 *----------------------------------------------------------------------*
11 * implement the events for handling the events of cl_salv_table
12 *----------------------------------------------------------------------*
13 CLASS SS_LCL_HANDLER_VARI IMPLEMENTATION.
14
15   METHOD ADDED_FUNCTION.
16
17     CASE E_SALV_FUNCTION.
18       WHEN 'CANC'.
19 ** close popup
20         SS_GD-R_ALV->CLOSE_SCREEN( ).
21         FREE SS_GD-R_ALV.
22
23       WHEN OTHERS.
24 ** do nothing
25
26     ENDCASE.
27
28   ENDMETHOD.
29
30   METHOD DOUBLE_CLICK.
31
32   DATA:
33     S_VARIANT TYPE RSVARIINFO.
34
35   READ TABLE SS_GD-T_VARIANT INDEX ROW INTO S_VARIANT.
36   IF SY-SUBRC = 0.
37 *** new variant selected, determine content of GR_SS_INT from variant
38 *** parameter and sel-option values.
39     PERFORM SS_SCREEN_UPDATE_FROM_VARIANT
40       USING S_VARIANT-VARIANT.
41
42     REFRESH SS_GD-T_VARIANT.
43 *** close and release ALV session
44     SS_GD-R_ALV->CLOSE_SCREEN( ).
45     FREE SS_GD-R_ALV.
46   ENDIF.
47
48   ENDMETHOD.
49
50 ENDCLASS.                    "SS_LCL_HANDLER_vari IMPLEMENTATION
51
52 CLASS SS_LCL_HANDLER_MANA IMPLEMENTATION.
53
54   METHOD ADDED_FUNCTION.
55
56     DATA: LR_SELECTIONS    TYPE REF TO CL_SALV_SELECTIONS.
57     DATA: LT_SELECTED_ROWS TYPE SALV_T_ROW.
58     DATA: LS_SELECTED_ROWS LIKE LINE OF LT_SELECTED_ROWS.
59     DATA: LD_RETURN        TYPE SY-SUBRC.
60     FIELD-SYMBOLS: <FS>    TYPE TKESS_YS_SCR_MANAGE.
61
```

```
62      CASE E_SALV_FUNCTION.
63        WHEN 'CANC'.
64  ** close popup
65          SS_GD-R_ALV->CLOSE_SCREEN( ).
66          FREE SS_GD-R_ALV.
67
68        WHEN 'DELETE'.
69          DATA: ANSWER(1)         TYPE C.
70          DATA: S_MANA            TYPE        TKESS_YS_SCR_MANAGE.
71
72          LR_SELECTIONS = SS_GD-R_ALV->GET_SELECTIONS( ).
73          LT_SELECTED_ROWS = LR_SELECTIONS->GET_SELECTED_ROWS( ).
74
75          LOOP AT LT_SELECTED_ROWS INTO LS_SELECTED_ROWS.
76            READ TABLE SS_GD-T_SCR_MANAGE ASSIGNING <FS> INDEX LS_SELECTED
    _ROWS.
77            <FS>-SCRDELE = ABAP_TRUE.
78          ENDLOOP.
79          CHECK SY-SUBRC = 0.
80
81          IF <FS>-SCRNAME IS NOT INITIAL AND <FS>-USER_SPEC IS INITIAL.
82            PERFORM SS_AUTH_CHECK_GLOBAL_SCREEN USING SS_C_DELETE
83                                                      SS_GR_INT->S_SCR-PRG
    NAME
84                                                      SS_GR_INT->S_SCR-TAB
    NAME
85                                                CHANGING LD_RETURN.
86
87            IF LD_RETURN <> 0.
88              MESSAGE i030(K/).
89              LOOP AT LT_SELECTED_ROWS INTO LS_SELECTED_ROWS.
90                READ TABLE SS_GD-T_SCR_MANAGE ASSIGNING <FS> INDEX LS_SELE
    CTED_ROWS.
91                <FS>-SCRDELE = ABAP_FALSE.
92              ENDLOOP.
93              RETURN.
94            ENDIF.
95          ENDIF.
96
97          READ TABLE SS_GD-T_SCR_MANAGE TRANSPORTING NO FIELDS
98            WITH KEY SCRDELE = ABAP_TRUE.
99
100         IF SY-SUBRC = 0.
101           CALL FUNCTION 'POPUP_TO_CONFIRM'
102             EXPORTING
103               DEFAULT_BUTTON        = '2'
104               DISPLAY_CANCEL_BUTTON = ABAP_FALSE
105               TITLEBAR              = SSTXT_09 " 'Deletion'(009)
106               TEXT_QUESTION         = SSTXT_10 "'Do you really want to d
    elete selected screen variants?'(010)
107               POPUP_TYPE            = 'ICON_MESSAGE_WARNING'
108             IMPORTING
109               ANSWER                = ANSWER.
110
111           IF ANSWER = '1'.
112             LOOP AT SS_GD-T_SCR_MANAGE INTO S_MANA
113               WHERE SCRDELE = ABAP_TRUE.
114
115 ** is currently used screen also selected for deletion
116               IF SCRNAME = S_MANA-SCRNAME.
117 * delete value of SCRNAME on selection screen
```

```
118                 CLEAR SCRNAME.
119               ENDIF.
120  ** delete screen
121               PERFORM SS_SCREEN_DELETE
122                 USING
123                   SS_GR_INT->S_SCR-PRGNAME
124                   SS_GR_INT->S_SCR-TABNAME
125                   S_MANA-SCRNAME
126                   ABAP_TRUE.
127             ENDLOOP.
128
129             DELETE SS_GD-T_SCR_MANAGE WHERE SCRDELE = ABAP_TRUE.
130             SS_GD-R_ALV->REFRESH( ).
131           ENDIF.
132         ENDIF.
133
134       WHEN 'TRANSPORT'.
135         DATA: LS_SCR_MANA LIKE LINE OF SS_GD-T_SCR_MANAGE.
136         DATA: LS_SCREEN TYPE TKESS_SCR.
137         DATA: LD_TASK TYPE TRKORR.
138
139         DATA: LT_OBJECTS TYPE TR_OBJECTS.
140         DATA: LT_KEYS    TYPE TR_KEYS.
141         DATA: LS_E071  TYPE LINE OF TR_OBJECTS.
142         DATA: LS_E071K TYPE LINE OF TR_KEYS.
143         DATA: LD_TABNAME TYPE TABNAME.
144         DATA: LD_KEY TYPE CHAR120.
145
146         LR_SELECTIONS = SS_GD-R_ALV->GET_SELECTIONS( ).
147         LT_SELECTED_ROWS = LR_SELECTIONS->GET_SELECTED_ROWS( ).
148
149         LOOP AT LT_SELECTED_ROWS INTO LS_SELECTED_ROWS.
150           READ TABLE SS_GD-T_SCR_MANAGE ASSIGNING <FS> INDEX LS_SELECTED
     _ROWS.
151         ENDLOOP.
152         CHECK SY-SUBRC = 0.
153
154         IF <FS>-SCRNAME IS NOT INITIAL AND <FS>-USER_SPEC IS INITIAL.
155           PERFORM SS_AUTH_CHECK_GLOBAL_SCREEN USING SS_C_TRANSPORT
156                                                     SS_GR_INT->S_SCR-PRG
     NAME
157                                                     SS_GR_INT->S_SCR-TAB
     NAME
158                                                CHANGING LD_RETURN.
159
160           IF LD_RETURN <> 0.
161             MESSAGE i030(K/).
162             RETURN.
163           ENDIF.
164         ENDIF.
165
166         IF LT_SELECTED_ROWS IS NOT INITIAL.
167           CALL FUNCTION 'TR_ORDER_CHOICE_CORRECTION'
168             EXPORTING
169               IV_CATEGORY = 'SYST'
170               IV_CLI_DEP  = 'X'
171             IMPORTING
172               EV_TASK     = LD_TASK
173             EXCEPTIONS
174               OTHERS      = 3.
175
```

```
176           IF SY-SUBRC <> 0.
177             EXIT.
178           ENDIF.
179
180           LOOP AT LT_SELECTED_ROWS INTO LS_SELECTED_ROWS.
181             READ TABLE SS_GD-T_SCR_MANAGE INTO LS_SCR_MANA INDEX LS_SELE
    CTED_ROWS.
182
183             READ TABLE SS_GD-T_SCREEN INTO LS_SCREEN WITH KEY SCRNAME =
    LS_SCR_MANA-SCRNAME.
184
185             LS_E071-PGMID       = 'R3TR'.
186             LS_E071-OBJECT      = 'TABU'.
187             LS_E071-OBJFUNC     = 'K'. "'K' = OBJEKT-KEY GEMÄß EINTRÄGE
    IN OBJ-LISTE
188             LS_E071K-PGMID      = 'R3TR'.
189             LS_E071K-OBJECT     = 'TABU'.
190             LS_E071K-MASTERTYPE = 'TABU'.
191
192             LD_TABNAME = 'TKESS_SCR'.
193             LD_KEY+0(3) = SY-MANDT.
194             LD_KEY+3(40) =  LS_SCREEN-PRGNAME.
195             LD_KEY+43(30) = LS_SCREEN-TABNAME..
196             LD_KEY+73(30) = LS_SCREEN-SCRNAME.
197
198             LS_E071-OBJ_NAME    = LD_TABNAME.
199             LS_E071K-MASTERNAME = LD_TABNAME.
200             LS_E071K-OBJNAME    = LD_TABNAME.
201             LS_E071K-TABKEY     = LD_KEY.
202
203             APPEND LS_E071 TO LT_OBJECTS.
204             APPEND LS_E071K TO LT_KEYS.
205
206             LD_TABNAME = 'TKESS_SCR_DESCR'.
207             LD_KEY+0(3) = SY-MANDT.
208             LD_KEY+3(40) =  LS_SCREEN-PRGNAME.
209             LD_KEY+43(30) = LS_SCREEN-TABNAME.
210             LD_KEY+73(30) = LS_SCREEN-SCRNAME.
211
212             LS_E071-OBJ_NAME    = LD_TABNAME.
213             LS_E071K-MASTERNAME = LD_TABNAME.
214             LS_E071K-OBJNAME    = LD_TABNAME.
215             LS_E071K-TABKEY     = LD_KEY.
216
217             APPEND LS_E071 TO LT_OBJECTS.
218             APPEND LS_E071K TO LT_KEYS.
219
220             LD_TABNAME = 'TKESS_SCR_FIELD'.
221             LD_KEY+0(3) = SY-MANDT.
222             LD_KEY+3(40) =  LS_SCREEN-PRGNAME.
223             LD_KEY+43(30) = LS_SCREEN-TABNAME.
224             LD_KEY+73(30) = LS_SCREEN-SCRNAME.
225             LD_KEY+103(1) = '*'.
226
227             LS_E071-OBJ_NAME    = LD_TABNAME.
228             LS_E071K-MASTERNAME = LD_TABNAME.
229             LS_E071K-OBJNAME    = LD_TABNAME.
230             LS_E071K-TABKEY     = LD_KEY.
231
232             APPEND LS_E071 TO LT_OBJECTS.
233             APPEND LS_E071K TO LT_KEYS.
```

```
234
235             "n. 3075278
236             DATA: LT_TKESS_SCR_INIT TYPE STANDARD TABLE OF TKESS_SCR_INI
    T.
237             DATA: LS_TKESS_SCR_INIT LIKE LINE OF LT_TKESS_SCR_INIT.
238
239             SELECT * FROM TKESS_SCR_INIT INTO TABLE LT_TKESS_SCR_INIT WH
    ERE PRGNAME = LS_SCREEN-PRGNAME AND TABNAME = LS_SCREEN-TABNAME AND SCRN
    AME = LS_SCREEN-SCRNAME.
240
241             IF SY-SUBRC = 0.
242               LD_TABNAME = 'TKESS_SCR_INIT'.
243               LS_E071-OBJ_NAME    = LD_TABNAME.
244               APPEND LS_E071 TO LT_OBJECTS.
245               LOOP AT LT_TKESS_SCR_INIT INTO LS_TKESS_SCR_INIT.
246                 CLEAR LD_KEY.
247
248                 LD_KEY+0(3) = SY-MANDT.
249                 LD_KEY+3(40) =  LS_SCREEN-PRGNAME.
250                 LD_KEY+43(30) = LS_SCREEN-TABNAME.
251                 LD_KEY+73(12) = LS_TKESS_SCR_INIT-USERNAME.
252
253                 LS_E071K-MASTERNAME = LD_TABNAME.
254                 LS_E071K-OBJNAME    = LD_TABNAME.
255                 LS_E071K-TABKEY     = LD_KEY.
256
257                 APPEND LS_E071K TO LT_KEYS.
258               ENDLOOP.
259             ENDIF.
260           ENDLOOP.
261
262           IF LT_OBJECTS IS NOT INITIAL AND LT_KEYS IS NOT INITIAL.
263             CALL FUNCTION 'TR_APPEND_TO_COMM_OBJS_KEYS'
264               EXPORTING
265                 WI_SIMULATION         = ' '
266                 WI_SUPPRESS_KEY_CHECK = ' '
267                 WI_TRKORR             = LD_TASK
268               TABLES
269                 WT_E071               = LT_OBJECTS
270                 WT_E071K              = LT_KEYS
271               EXCEPTIONS
272                 OTHERS                = 68.
273             IF SY-SUBRC <> 0.
274               MESSAGE ID SY-MSGID TYPE SY-MSGTY NUMBER SY-MSGNO
275               WITH SY-MSGV1 SY-MSGV2 SY-MSGV3 SY-MSGV4.
276             ELSE.
277               MESSAGE S101(WUSL).
278             ENDIF.
279           ENDIF.
280         ENDIF.
281
282       WHEN OTHERS.
283 ** do nothing
284
285     ENDCASE.
286
287   ENDMETHOD.
288
289   METHOD LINK_CLICK.
290     DATA:
291         S_SCR_MANAGE TYPE TKESS_YS_SCR_MANAGE,
```

```
292         S_SCR_DEFA   TYPE TKESS_YS_SCR_MANAGE.
293
294     DATA: LD_GLOBAL_ALLOWED TYPE FLAG.
295     DATA: LD_RETURN         TYPE SY-SUBRC.
296
297     PERFORM SS_AUTH_CHECK_GLOBAL_SCREEN USING SS_C_MAINTAIN
298                                               SS_GR_INT->S_SCR-PRGNAME
299                                               SS_GR_INT->S_SCR-TABNAME
300                                       CHANGING LD_RETURN.
301
302     IF LD_RETURN = 0.
303       LD_GLOBAL_ALLOWED = ABAP_TRUE.
304     ENDIF.
305
306     READ TABLE SS_GD-T_SCR_MANAGE INDEX ROW INTO S_SCR_MANAGE.
307
308     CASE COLUMN.
309 ** mark screens to be deleted
310       WHEN 'SCRDELE'.
311
312         IF S_SCR_MANAGE-SCRDELE IS INITIAL.
313
314           IF LD_GLOBAL_ALLOWED      IS INITIAL AND
315              S_SCR_MANAGE-USER_SPEC IS INITIAL.
316             MESSAGE I030(K/).
317             RETURN.
318           ENDIF.
319
320           S_SCR_MANAGE-SCRDELE  = ABAP_TRUE.
321           CLEAR S_SCR_MANAGE-DEFAGLOB.
322           CLEAR S_SCR_MANAGE-DEFAUSER.
323
324         ELSE.
325
326           CLEAR S_SCR_MANAGE-SCRDELE.
327
328         ENDIF.
329 ** define default global layout
330       WHEN 'DEFAGLOB'.
331
332         IF LD_GLOBAL_ALLOWED IS INITIAL.
333           MESSAGE I030(K/).
334           RETURN.
335         ENDIF.
336
337         IF S_SCR_MANAGE-DEFAGLOB   IS INITIAL AND
338            S_SCR_MANAGE-SCRDELE    IS INITIAL AND
339            S_SCR_MANAGE-USER_SPEC  IS INITIAL.
340
341           READ TABLE SS_GD-T_SCR_MANAGE INTO S_SCR_DEFA
342             WITH KEY DEFAGLOB = ICON_CHECKED.
343
344           IF SY-SUBRC = 0.
345             CLEAR S_SCR_DEFA-DEFAGLOB.
346 *             TABIX = SY-TABIX.
347             MODIFY SS_GD-T_SCR_MANAGE FROM S_SCR_DEFA INDEX SY-TABIX.
348           ENDIF.
349
350           S_SCR_MANAGE-DEFAGLOB = ICON_CHECKED.
351
352         ELSE.
```

```
353           CLEAR S_SCR_MANAGE-DEFAGLOB.
354         ENDIF.
355 ** define default user layout
356       WHEN 'DEFAUSER'.
357
358         IF S_SCR_MANAGE-DEFAUSER IS INITIAL AND
359            S_SCR_MANAGE-SCRDELE  IS INITIAL.
360
361           READ TABLE SS_GD-T_SCR_MANAGE INTO S_SCR_DEFA
362             WITH KEY DEFAUSER = ICON_CHECKED.
363
364           IF SY-SUBRC = 0.
365             CLEAR S_SCR_DEFA-DEFAUSER.
366             MODIFY SS_GD-T_SCR_MANAGE FROM S_SCR_DEFA INDEX SY-TABIX.
367           ENDIF.
368           S_SCR_MANAGE-DEFAUSER = ICON_CHECKED.
369         ELSE.
370
371           CLEAR S_SCR_MANAGE-DEFAUSER.
372         ENDIF.
373
374     ENDCASE.
375
376 *** update new info to global data for later posting
377 *** in form SS_EVENT_SSCRFIELDS_UCOMM_FC01
378     MODIFY SS_GD-T_SCR_MANAGE FROM S_SCR_MANAGE INDEX ROW.
379
380     SS_GD-R_ALV->REFRESH( ).
381
382   ENDMETHOD.
383                     "on_user_command
384 ENDCLASS.                    "lcl_handle_events IMPLEMENTATION
385 *** END
386
387 ***********************************************************************
388 ***   FORMS.             *********************************************
389 ***********************************************************************
390
391 *&---------------------------------------------------------------------*
392 *&      Form  SS_RECEIVE_CLASS_INSTANCE
393 *&---------------------------------------------------------------------*
394 *&
395 *&---------------------------------------------------------------------*
396 FORM SS_RECEIVE_CLASS_INSTANCE
397   USING
398     IR_INT TYPE REF TO CL_KESS_FREE_SELECTION_INT.
399
400   SS_GR_INT = IR_INT.
401
402 ENDFORM.                    "GET_INNER
403
404
405 *&---------------------------------------------------------------------*
406 *&      Form  SS_EVENT_INITIALIZATION
407 *&---------------------------------------------------------------------*
408 *&      INITIALIZATION
409 *&---------------------------------------------------------------------*
410
411 FORM SS_EVENT_INITIALIZATION .
412
413   DATA: S_INIT      LIKE TKESS_SCR_INIT,
```

```
414           FIRST_INIT  TYPE FLAG VALUE ABAP_FALSE,
415   *        S_RANGE     TYPE RSDSSELOPT,
416           NEW_TABNAME TYPE TABNAME.
417
418     DATA: LD_START_VARIANT LIKE SY-SUBRC.
419
420     IF SY-SLSET IS NOT INITIAL.
421       CALL FUNCTION 'RS_VARIANT_EXISTS'
422         EXPORTING
423           REPORT                    = SY-CPROG
424           VARIANT                   = SY-SLSET
425         IMPORTING
426           R_C                       = LD_START_VARIANT
427         EXCEPTIONS
428           OTHERS                    = 1.
429
430       IF SY-SUBRC <> 0.
431         LD_START_VARIANT = 4.
432       ENDIF.
433     ENDIF.
434
435   *** init selection screen buttons, icons etc,
436     PERFORM SS_INIT_ICONS_AND_BUTTONS.
437   ** determine current list of available screens
438     PERFORM SS_INIT_LISTBOX_SCRNAME.
439   ** some SO options should be only equal e.g. single values
440     PERFORM SS_INIT_ADJUST_SO_TO_EQUAL.
441
442   *** Make sure that report name is always filled, default value is SY-CPR
      OG
443   *** but it can be changed by user
444     IF SS_GR_INT->S_SCR-PRGNAME IS INITIAL.
445       PRGNAME = SS_GR_INT->S_SCR-PRGNAME = SY-CPROG.
446     ELSE.
447       PRGNAME = SS_GR_INT->S_SCR-PRGNAME.
448     ENDIF.
449
450     KESSTABL = SS_GR_INT->S_SCR-TABNAME.
451
452   *  IF LD_START_VARIANT IS INITIAL AND SY-SLSET IS NOT INITIAL AND SS_GD-
      FIRST_INIT = ABAP_TRUE.
453   *    PERFORM SS_SCREEN_UPDATE_FROM_VARIANT USING SY-SLSET.
454   *  ENDIF.
455
456   *** do nothing in case of background execution, system handles everythin
      g
457     CHECK SY-BATCH IS INITIAL AND ( LD_START_VARIANT IS NOT INITIAL OR SY-
      SLSET IS INITIAL ).
458
459   *** Screen Title
460     IF SY-TITLE IS INITIAL.
461       CONCATENATE SSTXT_17 SPACE SS_GR_INT->S_SCR-TABNAME INTO SY-TITLE
462         RESPECTING BLANKS.
463     ENDIF.
464
465   *** 'very first' session set to default layout
466     IF SS_GD-FIRST_INIT = ABAP_TRUE.
467
468       FIRST_INIT = ABAP_TRUE.
469       SS_GD-FIRST_INIT = ABAP_FALSE.
470   *** structure info
```

```
471      SS_GR_INT->TAB_CHANGED = ABAP_TRUE.
472  ** if table name not defined by user during ext_init
473  ** see form EC_SET_TABLE
474      IF SS_GR_INT->S_SCR-TABNAME IS INITIAL.
475  ** determine name of table
476        CALL FUNCTION 'F4_DD_ALLTYPES'
477          EXPORTING
478            OBJECT = NEW_TABNAME
479          IMPORTING
480            RESULT = NEW_TABNAME.
481
482        IF NEW_TABNAME IS NOT INITIAL.
483          KESSTABL  = NEW_TABNAME.
484          SS_GR_INT->SET_TABLE( KESSTABL ).
485  *         APPEND LINES OF SS_GR_INT->T_SS_TAB TO T_SS_TAB.
486        ELSE.
487          RETURN.
488        ENDIF.
489      ENDIF.
490
491      IF SS_GR_INT->T_SS_TAB IS INITIAL.
492        MESSAGE X899(KG).
493      ENDIF.
494
495
496    ELSE.
497
498  ** list of tables must not be empty
499      IF SS_GR_INT->T_SS_TAB IS INITIAL.
500        MESSAGE X899(KG).
501      ENDIF.
502
503    ENDIF.
504
505  ** is it first init or table name was changed
506    IF SS_GR_INT->TAB_CHANGED = ABAP_TRUE.
507
508      SS_GR_INT->TAB_CHANGED = ABAP_FALSE.
509
510        IF SS_GR_INT->T_SS_SF IS INITIAL.
511  *** issue with not updated/cleared parameter value
512        CLEAR SCRNAME.
513  ** determine default screen for user
514        SELECT SINGLE * FROM TKESS_SCR_INIT INTO S_INIT
515          WHERE PRGNAME   = SS_GR_INT->S_SCR-PRGNAME  AND
516                TABNAME   = SS_GR_INT->S_SCR-TABNAME  AND
517                USERNAME  = SY-UNAME.
518  ** default screen for current user is defined
519        IF SY-SUBRC = 0.
520          SS_GR_INT->S_SCR-SCRNAME = SCRNAME = S_INIT-SCRNAME.
521        ENDIF.
522  ** nothing was found for user, check for global default screen
523        IF SCRNAME IS INITIAL.
524
525          SELECT SINGLE * FROM TKESS_SCR_INIT INTO S_INIT
526            WHERE PRGNAME   = SS_GR_INT->S_SCR-PRGNAME AND
527                  TABNAME   = SS_GR_INT->S_SCR-TABNAME AND
528                  USERNAME  = ''.
529
530  ** Default Global Screen was found
531          IF SY-SUBRC = 0.
```

```
532           SS_GR_INT->S_SCR-SCRNAME = SCRNAME = S_INIT-SCRNAME.
533         ENDIF.
534
535       ENDIF.
536
537       IF SCRNAME IS NOT INITIAL.
538
539         PERFORM SS_SCREEN_SET
540           USING SS_GR_INT->S_SCR-PRGNAME
541                 SS_GR_INT->S_SCR-TABNAME
542                 SS_GR_INT->S_SCR-SCRNAME
543                 ABAP_TRUE
544                 ABAP_TRUE.
545
546       ENDIF.
547 ** No default (global, user) screen exists for table
548 ** determine default fields
549       IF SS_GR_INT->T_SS_SF[] IS INITIAL.
550         IF FIRST_INIT = ABAP_TRUE.
551
552           SS_GR_INT->SET_DEFAULT_SO( ).
553
554         ENDIF.
555       ENDIF.
556
557     ENDIF.
558   ENDIF.
559
560   PERFORM SS_SYNC_GS_TO_PARAM.
561
562 ENDFORM.                    " SS_EVENT_INITIALIZATION
563
564 *&---------------------------------------------------------------------*
565 *&      Form  REFRESH_ASSIGNMENT
566 *&---------------------------------------------------------------------*
567 *&      Refresh Dynamic Select Options definition
568 *&---------------------------------------------------------------------*
569 FORM SS_SCREEN_REFRESH_ASSIGNMENT
570   USING I_ONLI TYPE FLAG.
571
572 ***  refresh table, which contain info about selected fields
573   REFRESH SS_GR_INT->T_SS_SF.
574   REFRESH T_SS_SF.
575 *** refresh dynamic SO and paramaters used for SO definition
576 *** Characteristics
577   CLEAR PAR_C01. APPEND 'SO_C01' TO SS_GR_INT->T_SS_CLEAR.
578   CLEAR PAR_C02. APPEND 'SO_C02' TO SS_GR_INT->T_SS_CLEAR.
579   CLEAR PAR_C03. APPEND 'SO_C03' TO SS_GR_INT->T_SS_CLEAR.
580   CLEAR PAR_C04. APPEND 'SO_C04' TO SS_GR_INT->T_SS_CLEAR.
581   CLEAR PAR_C05. APPEND 'SO_C05' TO SS_GR_INT->T_SS_CLEAR.
582   CLEAR PAR_C06. APPEND 'SO_C06' TO SS_GR_INT->T_SS_CLEAR.
583   CLEAR PAR_C07. APPEND 'SO_C07' TO SS_GR_INT->T_SS_CLEAR.
584   CLEAR PAR_C08. APPEND 'SO_C08' TO SS_GR_INT->T_SS_CLEAR.
585   CLEAR PAR_C09. APPEND 'SO_C09' TO SS_GR_INT->T_SS_CLEAR.
586   CLEAR PAR_C10. APPEND 'SO_C10' TO SS_GR_INT->T_SS_CLEAR.
587   CLEAR PAR_C11. APPEND 'SO_C11' TO SS_GR_INT->T_SS_CLEAR.
588   CLEAR PAR_C12. APPEND 'SO_C12' TO SS_GR_INT->T_SS_CLEAR.
589   CLEAR PAR_C13. APPEND 'SO_C13' TO SS_GR_INT->T_SS_CLEAR.
590   CLEAR PAR_C14. APPEND 'SO_C14' TO SS_GR_INT->T_SS_CLEAR.
591   CLEAR PAR_C15. APPEND 'SO_C15' TO SS_GR_INT->T_SS_CLEAR.
592   CLEAR PAR_C16. APPEND 'SO_C16' TO SS_GR_INT->T_SS_CLEAR.
```

```
593    CLEAR PAR_C17. APPEND 'SO_C17' TO SS_GR_INT->T_SS_CLEAR.
594    CLEAR PAR_C18. APPEND 'SO_C18' TO SS_GR_INT->T_SS_CLEAR.
595    CLEAR PAR_C19. APPEND 'SO_C19' TO SS_GR_INT->T_SS_CLEAR.
596    CLEAR PAR_C20. APPEND 'SO_C20' TO SS_GR_INT->T_SS_CLEAR.
597    CLEAR PAR_C21. APPEND 'SO_C21' TO SS_GR_INT->T_SS_CLEAR.
598    CLEAR PAR_C22. APPEND 'SO_C22' TO SS_GR_INT->T_SS_CLEAR.
599    CLEAR PAR_C23. APPEND 'SO_C23' TO SS_GR_INT->T_SS_CLEAR.
600    CLEAR PAR_C24. APPEND 'SO_C24' TO SS_GR_INT->T_SS_CLEAR.
601    CLEAR PAR_C25. APPEND 'SO_C25' TO SS_GR_INT->T_SS_CLEAR.
602
603  **** Key figures + units for quantity fields
604    CLEAR PAR_V01. APPEND 'SO_V01' TO SS_GR_INT->T_SS_CLEAR.
605    CLEAR PAR_U01. APPEND 'SO_U01' TO SS_GR_INT->T_SS_CLEAR.
606
607    CLEAR PAR_V02. APPEND 'SO_V02' TO SS_GR_INT->T_SS_CLEAR.
608    CLEAR PAR_U02. APPEND 'SO_U02' TO SS_GR_INT->T_SS_CLEAR.
609
610    CLEAR PAR_V03. APPEND 'SO_V03' TO SS_GR_INT->T_SS_CLEAR.
611    CLEAR PAR_U03. APPEND 'SO_U03' TO SS_GR_INT->T_SS_CLEAR.
612
613    CLEAR PAR_V04. APPEND 'SO_V04' TO SS_GR_INT->T_SS_CLEAR.
614    CLEAR PAR_U04. APPEND 'SO_U04' TO SS_GR_INT->T_SS_CLEAR.
615
616    CLEAR PAR_V05. APPEND 'SO_V05' TO SS_GR_INT->T_SS_CLEAR.
617    CLEAR PAR_U05. APPEND 'SO_U05' TO SS_GR_INT->T_SS_CLEAR.
618
619    CLEAR PAR_V06. APPEND 'SO_V06' TO SS_GR_INT->T_SS_CLEAR.
620    CLEAR PAR_U06. APPEND 'SO_U06' TO SS_GR_INT->T_SS_CLEAR.
621
622    CLEAR PAR_V07. APPEND 'SO_V07' TO SS_GR_INT->T_SS_CLEAR.
623    CLEAR PAR_U07. APPEND 'SO_U07' TO SS_GR_INT->T_SS_CLEAR.
624
625    CLEAR PAR_V08. APPEND 'SO_V08' TO SS_GR_INT->T_SS_CLEAR.
626    CLEAR PAR_U08. APPEND 'SO_U08' TO SS_GR_INT->T_SS_CLEAR.
627
628    CLEAR PAR_V09. APPEND 'SO_V09' TO SS_GR_INT->T_SS_CLEAR.
629    CLEAR PAR_U09. APPEND 'SO_U09' TO SS_GR_INT->T_SS_CLEAR.
630
631    CLEAR PAR_V10. APPEND 'SO_V10' TO SS_GR_INT->T_SS_CLEAR.
632    CLEAR PAR_U10. APPEND 'SO_V10' TO SS_GR_INT->T_SS_CLEAR.
633
634    CLEAR PAR_V11. APPEND 'SO_V11' TO SS_GR_INT->T_SS_CLEAR.
635    CLEAR PAR_U11. APPEND 'SO_U11' TO SS_GR_INT->T_SS_CLEAR.
636
637    CLEAR PAR_V12. APPEND 'SO_V12' TO SS_GR_INT->T_SS_CLEAR.
638    CLEAR PAR_U12. APPEND 'SO_U12' TO SS_GR_INT->T_SS_CLEAR.
639
640    CLEAR PAR_V13. APPEND 'SO_V13' TO SS_GR_INT->T_SS_CLEAR.
641    CLEAR PAR_U13. APPEND 'SO_U13' TO SS_GR_INT->T_SS_CLEAR.
642
643    CLEAR PAR_V14. APPEND 'SO_V14' TO SS_GR_INT->T_SS_CLEAR.
644    CLEAR PAR_U14. APPEND 'SO_U14' TO SS_GR_INT->T_SS_CLEAR.
645
646    CLEAR PAR_V15. APPEND 'SO_V15' TO SS_GR_INT->T_SS_CLEAR.
647    CLEAR PAR_U15. APPEND 'SO_U15' TO SS_GR_INT->T_SS_CLEAR.
648
649    CLEAR PAR_V16. APPEND 'SO_V16' TO SS_GR_INT->T_SS_CLEAR.
650    CLEAR PAR_U16. APPEND 'SO_U16' TO SS_GR_INT->T_SS_CLEAR.
651
652    CLEAR PAR_V17. APPEND 'SO_V17' TO SS_GR_INT->T_SS_CLEAR.
653    CLEAR PAR_U17. APPEND 'SO_U17' TO SS_GR_INT->T_SS_CLEAR.
```

```
654
655    CLEAR PAR_V18. APPEND 'SO_V18' TO SS_GR_INT->T_SS_CLEAR.
656    CLEAR PAR_U18. APPEND 'SO_U18' TO SS_GR_INT->T_SS_CLEAR.
657
658    CLEAR PAR_V19. APPEND 'SO_V19' TO SS_GR_INT->T_SS_CLEAR.
659    CLEAR PAR_U19. APPEND 'SO_V19' TO SS_GR_INT->T_SS_CLEAR.
660
661    CLEAR PAR_V20. APPEND 'SO_V20' TO SS_GR_INT->T_SS_CLEAR.
662    CLEAR PAR_U20. APPEND 'SO_V20' TO SS_GR_INT->T_SS_CLEAR.
663
664    CLEAR PAR_V21. APPEND 'SO_V21' TO SS_GR_INT->T_SS_CLEAR.
665    CLEAR PAR_U21. APPEND 'SO_U21' TO SS_GR_INT->T_SS_CLEAR.
666
667    CLEAR PAR_V22. APPEND 'SO_V22' TO SS_GR_INT->T_SS_CLEAR.
668    CLEAR PAR_U22. APPEND 'SO_U22' TO SS_GR_INT->T_SS_CLEAR.
669
670    CLEAR PAR_V23. APPEND 'SO_V23' TO SS_GR_INT->T_SS_CLEAR.
671    CLEAR PAR_U23. APPEND 'SO_U23' TO SS_GR_INT->T_SS_CLEAR.
672
673    CLEAR PAR_V24. APPEND 'SO_V24' TO SS_GR_INT->T_SS_CLEAR.
674    CLEAR PAR_U24. APPEND 'SO_U24' TO SS_GR_INT->T_SS_CLEAR.
675
676    CLEAR PAR_V25. APPEND 'SO_V25' TO SS_GR_INT->T_SS_CLEAR.
677    CLEAR PAR_U25. APPEND 'SO_U25' TO SS_GR_INT->T_SS_CLEAR.
678
679  *** Is update of dynpro fields required
680    IF I_ONLI = ABAP_TRUE.
681  *** Update Dynpro fields definition
682      SSCRFIELDS-UCOMM = 'ONLI'.
683  *** "Simulated" execution
684      SS_GD-SIMUL_EXEC    = ABAP_TRUE.
685    ENDIF.
686
687  ENDFORM.                    " REFRESH_ASSIGNMENT
688
689
690  *&---------------------------------------------------------------------*
691  *&      Form  UNASSIGN_CC
692  *&---------------------------------------------------------------------*
693  FORM SS_SO_UNASSIGN
694    USING    I_TFNAME TYPE RSSCR_DBFI.
695
696    DATA:
697      NAME      TYPE RSSCR_DBFI.
698
699    DELETE  SS_GR_INT->T_SS_SF
700      WHERE TFNAME  = I_TFNAME.
701
702    DELETE T_SS_SF
703      WHERE
704       HIGH = I_TFNAME.
705
706    SPLIT I_TFNAME AT '-' INTO SS_TABLENAME SS_FIELDNAME.
707    READ TABLE SS_GR_INT->T_FCAT INTO SS_S_FCAT
708      WITH KEY
709        TABNAME   = SS_TABLENAME
710        FIELDNAME = SS_FIELDNAME.
711    IF SY-SUBRC <> 0.
712      MESSAGE x899(KG).
713    ENDIF.
714
```

```
715    NAME = I_TFNAME.
716  *** Value Field
717    IF SS_S_FCAT-DATATYPE = 'CURR' OR
718       SS_S_FCAT-DATATYPE = 'QUAN'.
719
720      IF PAR_V01 = NAME.
721        CLEAR PAR_V01. APPEND 'SO_V01' TO SS_GR_INT->T_SS_CLEAR.
722        CLEAR PAR_U01.  CLEAR TXT_V01. APPEND 'SO_U01' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
723      ENDIF.
724
725      IF PAR_V02 = NAME.
726        CLEAR PAR_V02. APPEND 'SO_V02' TO SS_GR_INT->T_SS_CLEAR.
727        CLEAR PAR_U02.  CLEAR TXT_V02. APPEND 'SO_U02' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
728      ENDIF.
729
730      IF PAR_V03 = NAME.
731        CLEAR PAR_V03. APPEND 'SO_V03' TO SS_GR_INT->T_SS_CLEAR.
732        CLEAR PAR_U03.  CLEAR TXT_V03. APPEND 'SO_U03' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
733      ENDIF.
734
735      IF PAR_V04 = NAME.
736        CLEAR PAR_V04. APPEND 'SO_V04' TO SS_GR_INT->T_SS_CLEAR.
737        CLEAR PAR_U04.  CLEAR TXT_V04. APPEND 'SO_U04' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
738      ENDIF.
739
740      IF PAR_V05 = NAME.
741        CLEAR PAR_V05. APPEND 'SO_V05' TO SS_GR_INT->T_SS_CLEAR.
742        CLEAR PAR_U05.  CLEAR TXT_V05. APPEND 'SO_U05' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
743      ENDIF.
744
745      IF PAR_V06 = NAME.
746        CLEAR PAR_V06. APPEND 'SO_V06' TO SS_GR_INT->T_SS_CLEAR.
747        CLEAR PAR_U06.  CLEAR TXT_V06. APPEND 'SO_U06' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
748      ENDIF.
749
750      IF PAR_V07 = NAME.
751        CLEAR PAR_V07. APPEND 'SO_V07' TO SS_GR_INT->T_SS_CLEAR.
752        CLEAR PAR_U07.  CLEAR TXT_V07. APPEND 'SO_V07' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
753      ENDIF.
754
755      IF PAR_V08 = NAME.
756        CLEAR PAR_V08. APPEND 'SO_V08' TO SS_GR_INT->T_SS_CLEAR.
757        CLEAR PAR_U08.  CLEAR TXT_V08. APPEND 'SO_V08' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
758      ENDIF.
759
760      IF PAR_V09 = NAME.
761        CLEAR PAR_V09. APPEND 'SO_V09' TO SS_GR_INT->T_SS_CLEAR.
762        CLEAR PAR_U09.  CLEAR TXT_V09. APPEND 'SO_V09' TO SS_GR_INT->T_SS_
     CLEAR. RETURN.
763      ENDIF.
764
765      IF PAR_V10 = NAME.
766        CLEAR PAR_V10. APPEND 'SO_V10' TO SS_GR_INT->T_SS_CLEAR.
```

```
767       CLEAR PAR_U10.  CLEAR TXT_V10. APPEND 'SO_V10' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
768     ENDIF.
769
770     IF PAR_V11 = NAME.
771       CLEAR PAR_V11. APPEND 'SO_V11' TO SS_GR_INT->T_SS_CLEAR.
772       CLEAR PAR_U11.  CLEAR TXT_V11. APPEND 'SO_V11' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
773     ENDIF.
774
775     IF PAR_V12 = NAME.
776       CLEAR PAR_V12. APPEND 'SO_V12' TO SS_GR_INT->T_SS_CLEAR.
777       CLEAR PAR_U12.  CLEAR TXT_V12. APPEND 'SO_V12' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
778     ENDIF.
779
780     IF PAR_V13 = NAME.
781       CLEAR PAR_V13. APPEND 'SO_V13' TO SS_GR_INT->T_SS_CLEAR.
782       CLEAR PAR_U13.  CLEAR TXT_V13. APPEND 'SO_V13' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
783     ENDIF.
784
785     IF PAR_V14 = NAME.
786       CLEAR PAR_V14. APPEND 'SO_V14' TO SS_GR_INT->T_SS_CLEAR.
787       CLEAR PAR_U14.  CLEAR TXT_V14. APPEND 'SO_V14' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
788     ENDIF.
789
790     IF PAR_V15 = NAME.
791       CLEAR PAR_V15. APPEND 'SO_V15' TO SS_GR_INT->T_SS_CLEAR.
792       CLEAR PAR_U15. CLEAR TXT_V15.  APPEND 'SO_V15' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
793     ENDIF.
794
795     IF PAR_V16 = NAME.
796       CLEAR PAR_V16. APPEND 'SO_V16' TO SS_GR_INT->T_SS_CLEAR.
797       CLEAR PAR_U16.  CLEAR TXT_V16. APPEND 'SO_V16' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
798     ENDIF.
799
800     IF PAR_V17 = NAME.
801       CLEAR PAR_V17. APPEND 'SO_V17' TO SS_GR_INT->T_SS_CLEAR.
802       CLEAR PAR_U17.  CLEAR TXT_V17. APPEND 'SO_V17' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
803     ENDIF.
804
805     IF PAR_V18 = NAME.
806       CLEAR PAR_V18. APPEND 'SO_V18' TO SS_GR_INT->T_SS_CLEAR.
807       CLEAR PAR_U18.  CLEAR TXT_V18. APPEND 'SO_V18' TO SS_GR_INT->T_SS_
    CLEAR. RETURN.
808     ENDIF.
809
810     IF PAR_V19 = NAME.
811       CLEAR PAR_V19. APPEND 'SO_V19' TO SS_GR_INT->T_SS_CLEAR.
812       CLEAR PAR_U19.  CLEAR TXT_V19. APPEND 'SO_V19' TO SS_GR_INT->T_SS_
    CLEAR.RETURN.
813     ENDIF.
814
815     IF PAR_V20 = NAME.
816       CLEAR PAR_V20. APPEND 'SO_V20' TO SS_GR_INT->T_SS_CLEAR.
817       CLEAR PAR_U20.  CLEAR TXT_V20. APPEND 'SO_V20' TO SS_GR_INT->T_SS_
```

```
     CLEAR.RETURN.
818      ENDIF.
819
820      IF PAR_V21 = NAME.
821        CLEAR PAR_V21. APPEND 'SO_V21' TO SS_GR_INT->T_SS_CLEAR.
822        CLEAR PAR_U21.  CLEAR TXT_V21. APPEND 'SO_V21' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
823      ENDIF.
824
825      IF PAR_V22 = NAME.
826        CLEAR PAR_V22. APPEND 'SO_V22' TO SS_GR_INT->T_SS_CLEAR.
827        CLEAR PAR_U22.  CLEAR TXT_V22. APPEND 'SO_V22' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
828      ENDIF.
829
830      IF PAR_V23 = NAME.
831        CLEAR PAR_V23. APPEND 'SO_V23' TO SS_GR_INT->T_SS_CLEAR.
832        CLEAR PAR_U23.  CLEAR TXT_V23. APPEND 'SO_V23' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
833      ENDIF.
834
835      IF PAR_V24 = NAME.
836        CLEAR PAR_V24. APPEND 'SO_V24' TO SS_GR_INT->T_SS_CLEAR.
837        CLEAR PAR_U24.  CLEAR TXT_V24. APPEND 'SO_V24' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
838      ENDIF.
839
840      IF PAR_V25 = NAME.
841        CLEAR PAR_V25. APPEND 'SO_V25' TO SS_GR_INT->T_SS_CLEAR.
842        CLEAR PAR_U25.  CLEAR TXT_V25. APPEND 'SO_V25' TO SS_GR_INT->T_SS_
     CLEAR.RETURN.
843      ENDIF.
844
845  ** Field
846    ELSE.
847      IF PAR_C01 = NAME. CLEAR PAR_C01. APPEND 'SO_C01' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
848      IF PAR_C02 = NAME. CLEAR PAR_C02. APPEND 'SO_C02' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
849      IF PAR_C03 = NAME. CLEAR PAR_C03. APPEND 'SO_C03' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
850      IF PAR_C04 = NAME. CLEAR PAR_C04. APPEND 'SO_C04' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
851      IF PAR_C05 = NAME. CLEAR PAR_C05. APPEND 'SO_C05' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
852      IF PAR_C06 = NAME. CLEAR PAR_C06. APPEND 'SO_C06' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
853      IF PAR_C07 = NAME. CLEAR PAR_C07. APPEND 'SO_C07' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
854      IF PAR_C08 = NAME. CLEAR PAR_C08. APPEND 'SO_C08' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
855      IF PAR_C09 = NAME. CLEAR PAR_C09. APPEND 'SO_C09' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
856      IF PAR_C10 = NAME. CLEAR PAR_C10. APPEND 'SO_C10' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
857      IF PAR_C11 = NAME. CLEAR PAR_C11. APPEND 'SO_C11' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
858      IF PAR_C12 = NAME. CLEAR PAR_C12. APPEND 'SO_C12' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
859      IF PAR_C13 = NAME. CLEAR PAR_C13. APPEND 'SO_C13' TO SS_GR_INT->T_SS
     _CLEAR.RETURN. ENDIF.
```

```
860       IF PAR_C14 = NAME. CLEAR PAR_C14. APPEND 'SO_C14' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
861       IF PAR_C15 = NAME. CLEAR PAR_C15. APPEND 'SO_C15' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
862       IF PAR_C16 = NAME. CLEAR PAR_C16. APPEND 'SO_C16' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
863       IF PAR_C17 = NAME. CLEAR PAR_C17. APPEND 'SO_C17' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
864       IF PAR_C18 = NAME. CLEAR PAR_C18. APPEND 'SO_C18' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
865       IF PAR_C19 = NAME. CLEAR PAR_C19. APPEND 'SO_C19' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
866       IF PAR_C20 = NAME. CLEAR PAR_C20. APPEND 'SO_C20' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
867       IF PAR_C21 = NAME. CLEAR PAR_C21. APPEND 'SO_C21' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
868       IF PAR_C22 = NAME. CLEAR PAR_C22. APPEND 'SO_C22' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
869       IF PAR_C23 = NAME. CLEAR PAR_C23. APPEND 'SO_C23' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
870       IF PAR_C24 = NAME. CLEAR PAR_C24. APPEND 'SO_C24' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
871       IF PAR_C25 = NAME. CLEAR PAR_C25. APPEND 'SO_C25' TO SS_GR_INT->T_SS
    _CLEAR.RETURN. ENDIF.
872     ENDIF.
873
874
875   ENDFORM.                    " UNASSIGN_CC
876   *&---------------------------------------------------------------------*
877   *&      Form  ASSIGN_CC
878   *&---------------------------------------------------------------------*
879   *&      Assign field to dynamic select option
880   *&---------------------------------------------------------------------*
881   FORM SS_SO_ASSIGN
882     USING    I_TFNAME TYPE RSSCR_DBFI.
883
884     DATA:
885       UOM_NAME    TYPE RSSCR_DBFI,
886       S_SCR_SF    LIKE LINE OF T_SS_SF,
887       NO_REFFIELD TYPE FLAG,
888       S_SEQ LIKE LINE OF SS_GR_INT->T_SS_SF.
889
890   ************************************************************************
891   DEFINE APPEND_SO.
892
893     S_SEQ-TFNAME = SS_TFNAME.
894     S_SEQ-SEQUENCE  = &1.
895     APPEND S_SEQ TO SS_GR_INT->T_SS_SF.
896
897     SORT SS_GR_INT->T_SS_SF BY SEQUENCE.
898
899     S_SCR_SF-SIGN   = 'I'.
900     S_SCR_SF-OPTION = 'BT'.
901     S_SCR_SF-HIGH   = S_SEQ-TFNAME.
902     S_SCR_SF-LOW    = S_SEQ-SEQUENCE.
903     APPEND S_SCR_SF TO T_SS_SF.
904
905   END-OF-DEFINITION.
906   ************************************************************************
907
908     SPLIT I_TFNAME AT '-' INTO SS_TABLENAME SS_FIELDNAME.
```

```
909
910    READ TABLE SS_GR_INT->T_FCAT INTO SS_S_FCAT
911      WITH KEY
912        TABNAME   = SS_TABLENAME
913        FIELDNAME = SS_FIELDNAME.
914
915    IF SY-SUBRC <> 0.
916      MESSAGE x899(KG).
917    ENDIF.
918
919    SS_TFNAME = I_TFNAME.
920  ** Key Figure
921    IF SS_S_FCAT-DATATYPE = 'CURR' OR
922       SS_S_FCAT-DATATYPE = 'QUAN'.
923  ** get whole name (structure - fieldname) for unit of measure field
924      IF SS_S_FCAT-REFFIELD IS NOT INITIAL.
925
926          NO_REFFIELD =
927            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO          = SS_TFNAME   "TODO
928                                         I_NO_REFFIELD = ABAP_TRUE ).
929  *** display reference field only in case that reftable and table is the
     same.
930          IF NO_REFFIELD = ABAP_FALSE AND SS_S_FCAT-TABNAME = SS_S_FCAT-RE
     FTABLE.
931            CONCATENATE SS_S_FCAT-TABNAME '-' SS_S_FCAT-REFFIELD INTO UOM_
     NAME.
932          ENDIF.
933
934      ENDIF.
935
936      IF PAR_V01 IS INITIAL. PAR_V01 = SS_TFNAME. PAR_U01 = UOM_NAME. APPE
     ND_SO 101. RETURN. ENDIF.
937      IF PAR_V02 IS INITIAL. PAR_V02 = SS_TFNAME. PAR_U02 = UOM_NAME. APPE
     ND_SO 102. RETURN. ENDIF.
938      IF PAR_V03 IS INITIAL. PAR_V03 = SS_TFNAME. PAR_U03 = UOM_NAME. APPE
     ND_SO 103. RETURN. ENDIF.
939      IF PAR_V04 IS INITIAL. PAR_V04 = SS_TFNAME. PAR_U04 = UOM_NAME. APPE
     ND_SO 104. RETURN. ENDIF.
940      IF PAR_V05 IS INITIAL. PAR_V05 = SS_TFNAME. PAR_U05 = UOM_NAME. APPE
     ND_SO 105. RETURN. ENDIF.
941      IF PAR_V06 IS INITIAL. PAR_V06 = SS_TFNAME. PAR_U06 = UOM_NAME. APPE
     ND_SO 106. RETURN. ENDIF.
942      IF PAR_V07 IS INITIAL. PAR_V07 = SS_TFNAME. PAR_U07 = UOM_NAME. APPE
     ND_SO 107. RETURN. ENDIF.
943      IF PAR_V08 IS INITIAL. PAR_V08 = SS_TFNAME. PAR_U08 = UOM_NAME. APPE
     ND_SO 108. RETURN. ENDIF.
944      IF PAR_V09 IS INITIAL. PAR_V09 = SS_TFNAME. PAR_U09 = UOM_NAME. APPE
     ND_SO 109. RETURN. ENDIF.
945      IF PAR_V10 IS INITIAL. PAR_V10 = SS_TFNAME. PAR_U10 = UOM_NAME. APPE
     ND_SO 110. RETURN. ENDIF.
946      IF PAR_V11 IS INITIAL. PAR_V11 = SS_TFNAME. PAR_U11 = UOM_NAME. APPE
     ND_SO 111. RETURN. ENDIF.
947      IF PAR_V12 IS INITIAL. PAR_V12 = SS_TFNAME. PAR_U12 = UOM_NAME. APPE
     ND_SO 112. RETURN. ENDIF.
948      IF PAR_V13 IS INITIAL. PAR_V13 = SS_TFNAME. PAR_U13 = UOM_NAME. APPE
     ND_SO 113. RETURN. ENDIF.
949      IF PAR_V14 IS INITIAL. PAR_V14 = SS_TFNAME. PAR_U14 = UOM_NAME. APPE
     ND_SO 114. RETURN. ENDIF.
950      IF PAR_V15 IS INITIAL. PAR_V15 = SS_TFNAME. PAR_U15 = UOM_NAME. APPE
     ND_SO 115. RETURN. ENDIF.
951      IF PAR_V16 IS INITIAL. PAR_V16 = SS_TFNAME. PAR_U16 = UOM_NAME. APPE
```

```
    ND_SO 116. RETURN. ENDIF.
952     IF PAR_V17 IS INITIAL. PAR_V17 = SS_TFNAME. PAR_U17 = UOM_NAME. APPE
    ND_SO 117. RETURN. ENDIF.
953     IF PAR_V18 IS INITIAL. PAR_V18 = SS_TFNAME. PAR_U18 = UOM_NAME. APPE
    ND_SO 118. RETURN. ENDIF.
954     IF PAR_V19 IS INITIAL. PAR_V19 = SS_TFNAME. PAR_U19 = UOM_NAME. APPE
    ND_SO 119. RETURN. ENDIF.
955     IF PAR_V20 IS INITIAL. PAR_V20 = SS_TFNAME. PAR_U20 = UOM_NAME. APPE
    ND_SO 120. RETURN. ENDIF.
956     IF PAR_V21 IS INITIAL. PAR_V21 = SS_TFNAME. PAR_U21 = UOM_NAME. APPE
    ND_SO 121. RETURN. ENDIF.
957     IF PAR_V22 IS INITIAL. PAR_V22 = SS_TFNAME. PAR_U22 = UOM_NAME. APPE
    ND_SO 122. RETURN. ENDIF.
958     IF PAR_V23 IS INITIAL. PAR_V23 = SS_TFNAME. PAR_U23 = UOM_NAME. APPE
    ND_SO 123. RETURN. ENDIF.
959     IF PAR_V24 IS INITIAL. PAR_V24 = SS_TFNAME. PAR_U24 = UOM_NAME. APPE
    ND_SO 124. RETURN. ENDIF.
960     IF PAR_V25 IS INITIAL. PAR_V25 = SS_TFNAME. PAR_U25 = UOM_NAME. APPE
    ND_SO 125. RETURN. ENDIF.
961 *TXT_V01 = SS_S_FCAT-SCRTEXT_M.
962 ** Characteristic
963   ELSE.
964     IF PAR_C01 IS INITIAL. PAR_C01 = SS_TFNAME. APPEND_SO  1. RETURN. EN
    DIF.
965     IF PAR_C02 IS INITIAL. PAR_C02 = SS_TFNAME. APPEND_SO  2. RETURN. EN
    DIF.
966     IF PAR_C03 IS INITIAL. PAR_C03 = SS_TFNAME. APPEND_SO  3. RETURN. EN
    DIF.
967     IF PAR_C04 IS INITIAL. PAR_C04 = SS_TFNAME. APPEND_SO  4. RETURN. EN
    DIF.
968     IF PAR_C05 IS INITIAL. PAR_C05 = SS_TFNAME. APPEND_SO  5. RETURN. EN
    DIF.
969     IF PAR_C06 IS INITIAL. PAR_C06 = SS_TFNAME. APPEND_SO  6. RETURN. EN
    DIF.
970     IF PAR_C07 IS INITIAL. PAR_C07 = SS_TFNAME. APPEND_SO  7. RETURN. EN
    DIF.
971     IF PAR_C08 IS INITIAL. PAR_C08 = SS_TFNAME. APPEND_SO  8. RETURN. EN
    DIF.
972     IF PAR_C09 IS INITIAL. PAR_C09 = SS_TFNAME. APPEND_SO  9. RETURN. EN
    DIF.
973     IF PAR_C10 IS INITIAL. PAR_C10 = SS_TFNAME. APPEND_SO 10. RETURN. EN
    DIF.
974     IF PAR_C11 IS INITIAL. PAR_C11 = SS_TFNAME. APPEND_SO 11. RETURN. EN
    DIF.
975     IF PAR_C12 IS INITIAL. PAR_C12 = SS_TFNAME. APPEND_SO 12. RETURN. EN
    DIF.
976     IF PAR_C13 IS INITIAL. PAR_C13 = SS_TFNAME. APPEND_SO 13. RETURN. EN
    DIF.
977     IF PAR_C14 IS INITIAL. PAR_C14 = SS_TFNAME. APPEND_SO 14. RETURN. EN
    DIF.
978     IF PAR_C15 IS INITIAL. PAR_C15 = SS_TFNAME. APPEND_SO 15. RETURN. EN
    DIF.
979     IF PAR_C16 IS INITIAL. PAR_C16 = SS_TFNAME. APPEND_SO 16. RETURN. EN
    DIF.
980     IF PAR_C17 IS INITIAL. PAR_C17 = SS_TFNAME. APPEND_SO 17. RETURN. EN
    DIF.
981     IF PAR_C18 IS INITIAL. PAR_C18 = SS_TFNAME. APPEND_SO 18. RETURN. EN
    DIF.
982     IF PAR_C19 IS INITIAL. PAR_C19 = SS_TFNAME. APPEND_SO 19. RETURN. EN
    DIF.
983     IF PAR_C20 IS INITIAL. PAR_C20 = SS_TFNAME. APPEND_SO 20. RETURN. EN
```

```
    DIF.
 984      IF PAR_C21 IS INITIAL. PAR_C21 = SS_TFNAME. APPEND_SO 21. RETURN. EN
    DIF.
 985      IF PAR_C22 IS INITIAL. PAR_C22 = SS_TFNAME. APPEND_SO 22. RETURN. EN
    DIF.
 986      IF PAR_C23 IS INITIAL. PAR_C23 = SS_TFNAME. APPEND_SO 23. RETURN. EN
    DIF.
 987      IF PAR_C24 IS INITIAL. PAR_C24 = SS_TFNAME. APPEND_SO 24. RETURN. EN
    DIF.
 988      IF PAR_C25 IS INITIAL. PAR_C25 = SS_TFNAME. APPEND_SO 25. RETURN. EN
    DIF.
 989
 990    ENDIF.
 991
 992  ENDFORM.                    " ASSIGN_CC
 993
 994  *&---------------------------------------------------------------------*
 995  *&   form CONVERT_TO_SELTAB
 996  *&---------------------------------------------------------------------*
 997  FORM SS_SO_TO_SEL
 998    USING
 999      I_FIELDNAME   TYPE RSSCR_DBFI
1000      IT_SO         TYPE ANY TABLE.
1001
1002    DATA: S_TRANGE  TYPE RSDS_RANGE,
1003          TABIX     LIKE SY-TABIX VALUE 0.
1004
1005    FIND '-' IN I_FIELDNAME.
1006    IF SY-SUBRC = 0.
1007      SPLIT I_FIELDNAME AT '-' INTO SS_TABLENAME SS_FIELDNAME.
1008    ELSE.
1009      SS_FIELDNAME = I_FIELDNAME.
1010    ENDIF.
1011
1012    CHECK SS_FIELDNAME IS NOT INITIAL.
1013
1014    READ TABLE SS_GR_INT->T_TRANGE INTO S_TRANGE
1015      WITH KEY TABLENAME = SS_TABLENAME.
1016
1017    IF SY-SUBRC = 0.
1018      TABIX = SY-TABIX.
1019    ELSE.
1020      S_TRANGE-TABLENAME = SS_TABLENAME.
1021    ENDIF.
1022
1023    CL_KESS_FREE_SELECTION_INT=>CONVERT_RANGE_TO_SELTAB(
1024      EXPORTING
1025        I_FIELDNAME = SS_FIELDNAME
1026        IT_TABLE    = IT_SO
1027      CHANGING
1028        XT_SELTAB = S_TRANGE-FRANGE_T ).
1029
1030    IF TABIX = 0.
1031      APPEND S_TRANGE TO SS_GR_INT->T_TRANGE.
1032    ELSE.
1033      MODIFY SS_GR_INT->T_TRANGE FROM S_TRANGE INDEX TABIX.
1034    ENDIF.
1035
1036  ENDFORM.
1037
1038  *&---------------------------------------------------------------------*
```

```
1039  *&      Form  CONVERT_SELSCREEN_TO_SELTAB
1040  *&---------------------------------------------------------------------*
1041  *&      Transform selection criteria from screen into seltab = GT_TRANGE
1042  *&---------------------------------------------------------------------*
1043  FORM SS_SCREEN_GET_SELTAB .
1044
1045    REFRESH SS_GR_INT->T_TRANGE.
1046
1047  *** Characteristics
1048    PERFORM SS_SO_TO_SEL USING PAR_C01  SO_C01[].
1049    PERFORM SS_SO_TO_SEL USING PAR_C02  SO_C02[].
1050    PERFORM SS_SO_TO_SEL USING PAR_C03  SO_C03[].
1051    PERFORM SS_SO_TO_SEL USING PAR_C04  SO_C04[].
1052    PERFORM SS_SO_TO_SEL USING PAR_C05  SO_C05[].
1053    PERFORM SS_SO_TO_SEL USING PAR_C06  SO_C06[].
1054    PERFORM SS_SO_TO_SEL USING PAR_C07  SO_C07[].
1055    PERFORM SS_SO_TO_SEL USING PAR_C08  SO_C08[].
1056    PERFORM SS_SO_TO_SEL USING PAR_C09  SO_C09[].
1057    PERFORM SS_SO_TO_SEL USING PAR_C10  SO_C10[].
1058    PERFORM SS_SO_TO_SEL USING PAR_C11  SO_C11[].
1059    PERFORM SS_SO_TO_SEL USING PAR_C12  SO_C12[].
1060    PERFORM SS_SO_TO_SEL USING PAR_C13  SO_C13[].
1061    PERFORM SS_SO_TO_SEL USING PAR_C14  SO_C14[].
1062    PERFORM SS_SO_TO_SEL USING PAR_C15  SO_C15[].
1063    PERFORM SS_SO_TO_SEL USING PAR_C16  SO_C16[].
1064    PERFORM SS_SO_TO_SEL USING PAR_C17  SO_C17[].
1065    PERFORM SS_SO_TO_SEL USING PAR_C18  SO_C18[].
1066    PERFORM SS_SO_TO_SEL USING PAR_C19  SO_C19[].
1067    PERFORM SS_SO_TO_SEL USING PAR_C20  SO_C20[].
1068    PERFORM SS_SO_TO_SEL USING PAR_C21  SO_C21[].
1069    PERFORM SS_SO_TO_SEL USING PAR_C22  SO_C22[].
1070    PERFORM SS_SO_TO_SEL USING PAR_C23  SO_C23[].
1071    PERFORM SS_SO_TO_SEL USING PAR_C24  SO_C24[].
1072    PERFORM SS_SO_TO_SEL USING PAR_C25  SO_C25[].
1073
1074  *** Key Figures
1075    PERFORM SS_SO_TO_SEL USING PAR_V01  SO_V01[].
1076    PERFORM SS_SO_TO_SEL USING PAR_U01  SO_U01[].
1077    PERFORM SS_SO_TO_SEL USING PAR_V02  SO_V02[].
1078    PERFORM SS_SO_TO_SEL USING PAR_U02  SO_U02[].
1079    PERFORM SS_SO_TO_SEL USING PAR_V03  SO_V03[].
1080    PERFORM SS_SO_TO_SEL USING PAR_U03  SO_U03[].
1081    PERFORM SS_SO_TO_SEL USING PAR_V04  SO_V04[].
1082    PERFORM SS_SO_TO_SEL USING PAR_U04  SO_U04[].
1083    PERFORM SS_SO_TO_SEL USING PAR_V05  SO_V05[].
1084    PERFORM SS_SO_TO_SEL USING PAR_U05  SO_U05[].
1085    PERFORM SS_SO_TO_SEL USING PAR_V06  SO_V06[].
1086    PERFORM SS_SO_TO_SEL USING PAR_U06  SO_U06[].
1087    PERFORM SS_SO_TO_SEL USING PAR_V07  SO_V07[].
1088    PERFORM SS_SO_TO_SEL USING PAR_U07  SO_U07[].
1089    PERFORM SS_SO_TO_SEL USING PAR_V08  SO_V08[].
1090    PERFORM SS_SO_TO_SEL USING PAR_U08  SO_U08[].
1091    PERFORM SS_SO_TO_SEL USING PAR_V09  SO_V09[].
1092    PERFORM SS_SO_TO_SEL USING PAR_U09  SO_U09[].
1093    PERFORM SS_SO_TO_SEL USING PAR_V10  SO_V10[].
1094    PERFORM SS_SO_TO_SEL USING PAR_U10  SO_U10[].
1095    PERFORM SS_SO_TO_SEL USING PAR_V11  SO_V11[].
1096    PERFORM SS_SO_TO_SEL USING PAR_U11  SO_U11[].
1097    PERFORM SS_SO_TO_SEL USING PAR_V12  SO_V12[].
1098    PERFORM SS_SO_TO_SEL USING PAR_U12  SO_U12[].
1099    PERFORM SS_SO_TO_SEL USING PAR_V13  SO_V13[].
```

```
1100    PERFORM SS_SO_TO_SEL USING PAR_U13  SO_U13[].
1101    PERFORM SS_SO_TO_SEL USING PAR_V14  SO_V14[].
1102    PERFORM SS_SO_TO_SEL USING PAR_U14  SO_U14[].
1103    PERFORM SS_SO_TO_SEL USING PAR_V15  SO_V15[].
1104    PERFORM SS_SO_TO_SEL USING PAR_U15  SO_U15[].
1105    PERFORM SS_SO_TO_SEL USING PAR_V16  SO_V16[].
1106    PERFORM SS_SO_TO_SEL USING PAR_U16  SO_U16[].
1107    PERFORM SS_SO_TO_SEL USING PAR_V17  SO_V17[].
1108    PERFORM SS_SO_TO_SEL USING PAR_U17  SO_U17[].
1109    PERFORM SS_SO_TO_SEL USING PAR_V18  SO_V18[].
1110    PERFORM SS_SO_TO_SEL USING PAR_U18  SO_U18[].
1111    PERFORM SS_SO_TO_SEL USING PAR_V19  SO_V19[].
1112    PERFORM SS_SO_TO_SEL USING PAR_U19  SO_U19[].
1113    PERFORM SS_SO_TO_SEL USING PAR_V20  SO_V20[].
1114    PERFORM SS_SO_TO_SEL USING PAR_U20  SO_U20[].
1115    PERFORM SS_SO_TO_SEL USING PAR_V21  SO_V21[].
1116    PERFORM SS_SO_TO_SEL USING PAR_U21  SO_U21[].
1117    PERFORM SS_SO_TO_SEL USING PAR_V22  SO_V22[].
1118    PERFORM SS_SO_TO_SEL USING PAR_U22  SO_U22[].
1119    PERFORM SS_SO_TO_SEL USING PAR_V23  SO_V23[].
1120    PERFORM SS_SO_TO_SEL USING PAR_U23  SO_U23[].
1121    PERFORM SS_SO_TO_SEL USING PAR_V24  SO_V24[].
1122    PERFORM SS_SO_TO_SEL USING PAR_U24  SO_U24[].
1123    PERFORM SS_SO_TO_SEL USING PAR_V25  SO_V25[].
1124
1125  ENDFORM.                    " SS_CONVERT_SELSCREEN_TO_SELTAB
1126
1127
1128  *&---------------------------------------------------------------------*
1129  *&      Form  SS_EVENT_SY_UCOMM_PUSHMANA
1130  *&      deletion and definition of default/initial screens
1131  *&---------------------------------------------------------------------*
1132  FORM SS_EVENT_SY_UCOMM_PUSHMANA .
1133
1134    DATA:
1135      ANSWER(1)     TYPE C,
1136      R_ALV         TYPE REF TO CL_SALV_TABLE,
1137      R_DS          TYPE REF TO CL_SALV_DISPLAY_SETTINGS,
1138      R_COLUMNS     TYPE REF TO CL_SALV_COLUMNS_TABLE,
1139      R_COLUMN      TYPE REF TO CL_SALV_COLUMN_TABLE,
1140      R_SELECTIONS TYPE REF TO CL_SALV_SELECTIONS,
1141      R_ALV_FUNC    TYPE REF TO CL_SALV_FUNCTIONS_LIST,
1142      S_COLOR       TYPE        LVC_S_COLO,
1143  ***  register to the events of cl_salv_table
1144      R_EVENTS      TYPE REF TO CL_SALV_EVENTS_TABLE,
1145      S_MANA        TYPE        TKESS_YS_SCR_MANAGE,
1146      S_DESCR       LIKE        TKESS_SCR_DESCR,
1147      S_INIT        TYPE        TKESS_SCR_INIT,
1148      T_SCR_MANAGE TYPE TABLE OF TKESS_YS_SCR_MANAGE.
1149
1150    SY-TITLE = SSTXT_08.
1151    REFRESH SS_GD-T_SCR_MANAGE.
1152
1153  *** Find All Global
1154    SELECT * FROM TKESS_SCR
1155      INTO CORRESPONDING FIELDS OF TABLE T_SCR_MANAGE
1156      WHERE PRGNAME   = SS_GR_INT->S_SCR-PRGNAME AND
1157            TABNAME   = SS_GR_INT->S_SCR-TABNAME AND
1158            USER_SPEC = ABAP_FALSE.
1159
1160    APPEND LINES OF T_SCR_MANAGE TO SS_GD-T_SCR_MANAGE.
```

```
1161
1162  *** & User Spec Screens
1163    SELECT * FROM TKESS_SCR
1164      INTO CORRESPONDING FIELDS OF TABLE T_SCR_MANAGE
1165      WHERE PRGNAME    = SS_GR_INT->S_SCR-PRGNAME AND
1166            TABNAME    = SS_GR_INT->S_SCR-TABNAME AND
1167            USER_SPEC  = ABAP_TRUE                AND
1168            CREATED_BY = SY-UNAME.
1169
1170    APPEND LINES OF T_SCR_MANAGE TO SS_GD-T_SCR_MANAGE.
1171
1172    IF SS_GD-T_SCR_MANAGE IS INITIAL.
1173      MESSAGE s114(KB). "List contains no data
1174      RETURN.
1175    ENDIF.
1176  *** initial global layout
1177    SELECT SINGLE * FROM TKESS_SCR_INIT INTO S_INIT
1178      WHERE PRGNAME  = SS_GR_INT->S_SCR-PRGNAME AND
1179            TABNAME  = SS_GR_INT->S_SCR-TABNAME AND
1180            USERNAME = ''.
1181
1182    IF SY-SUBRC = 0.
1183
1184      READ TABLE SS_GD-T_SCR_MANAGE INTO S_MANA
1185        WITH KEY
1186          SCRNAME = S_INIT-SCRNAME.
1187
1188      IF SY-SUBRC = 0.
1189        S_MANA-DEFAGLOB = ICON_CHECKED.
1190        MODIFY SS_GD-T_SCR_MANAGE FROM S_MANA INDEX SY-TABIX.
1191      ENDIF.
1192
1193    ENDIF.
1194
1195  *** initial user layout
1196    SELECT SINGLE * FROM TKESS_SCR_INIT INTO S_INIT
1197      WHERE PRGNAME  = SS_GR_INT->S_SCR-PRGNAME AND
1198            TABNAME  = SS_GR_INT->S_SCR-TABNAME AND
1199            USERNAME = SY-UNAME.
1200
1201    IF SY-SUBRC = 0.
1202
1203      READ TABLE SS_GD-T_SCR_MANAGE INTO S_MANA
1204        WITH KEY
1205          SCRNAME = S_INIT-SCRNAME.
1206
1207      IF SY-SUBRC = 0.
1208        S_MANA-DEFAUSER = ICON_CHECKED.
1209        MODIFY SS_GD-T_SCR_MANAGE FROM S_MANA INDEX SY-TABIX.
1210      ENDIF.
1211
1212    ENDIF.
1213
1214  *** get description
1215    LOOP AT SS_GD-T_SCR_MANAGE INTO S_MANA.
1216
1217      SELECT SINGLE * FROM TKESS_SCR_DESCR INTO S_DESCR
1218        WHERE PRGNAME   = SS_GR_INT->S_SCR-PRGNAME   AND
1219              TABNAME   = SS_GR_INT->S_SCR-TABNAME   AND
1220              SCRNAME   = S_MANA-SCRNAME             AND
1221              LANGU     = SY-LANGU.
```

```
1222
1223      IF SY-SUBRC = 0.
1224        S_MANA-SCRDESCR = S_DESCR-SCRDESCR.
1225        MODIFY SS_GD-T_SCR_MANAGE FROM S_MANA INDEX SY-TABIX.
1226      ENDIF.
1227
1228    ENDLOOP.
1229
1230
1231    TRY.
1232
1233        CALL METHOD CL_SALV_TABLE=>FACTORY
1234          IMPORTING
1235            R_SALV_TABLE = R_ALV
1236          CHANGING
1237            T_TABLE      = SS_GD-T_SCR_MANAGE.
1238
1239      CATCH CX_SALV_MSG .  "#EC NO_HANDLER
1240
1241    ENDTRY.
1242
1243    TRY.
1244  *** Set Optimized
1245        R_COLUMNS = R_ALV->GET_COLUMNS( ).
1246  ** set type hotspot for column DEFAULT
1247        R_COLUMN ?= R_columns->get_column( 'SCRDELE' ).
1248        R_COLUMN->SET_CELL_TYPE( IF_SALV_C_CELL_TYPE=>CHECKBOX_HOTSPOT ).
1249        R_COLUMN->SET_TECHNICAL( ABAP_TRUE ).
1250  *       R_COLUMN->SET_ICON( ABAP_TRUE ).
1251        S_COLOR-COL = 5. "green
1252        R_COLUMN->SET_COLOR( S_COLOR ).
1253
1254        R_COLUMN ?= R_columns->get_column( 'DEFAGLOB' ).
1255        R_COLUMN->SET_CELL_TYPE( IF_SALV_C_CELL_TYPE=>HOTSPOT ).
1256  *       S_COLOR-INT = 1.  "intensified
1257        S_COLOR-COL = 5. "green
1258        R_COLUMN->SET_ICON( ABAP_TRUE ).
1259        R_COLUMN->SET_COLOR( S_COLOR ).
1260
1261        R_COLUMN ?= R_columns->get_column( 'DEFAUSER' ).
1262        R_COLUMN->SET_CELL_TYPE( IF_SALV_C_CELL_TYPE=>HOTSPOT ).
1263  *       S_COLOR-INT = 1.  "intensified
1264        S_COLOR-COL = 5. "green
1265        R_COLUMN->SET_ICON( ABAP_TRUE ).
1266        R_COLUMN->SET_COLOR( S_COLOR ).
1267
1268        R_COLUMN ?= R_columns->get_column( 'USER_SPEC').
1269        R_COLUMN->SET_ICON( ABAP_TRUE ).
1270        R_COLUMN->SET_OUTPUT_LENGTH( 8 ).
1271
1272      CATCH CX_SALV_NOT_FOUND.  "#EC NO_HANDLER
1273
1274    ENDTRY.
1275
1276  *** Set Zebra Pattern
1277    R_DS = R_ALV->GET_DISPLAY_SETTINGS( ).
1278    R_DS->SET_STRIPED_PATTERN( ABAP_TRUE ).
1279
1280  *** Display as Popup
1281    R_ALV->SET_SCREEN_POPUP(
1282      START_COLUMN = 10
```

```
1283      END_COLUMN   = 100
1284      START_LINE   = 5
1285      END_LINE     = 15
1286                           ).
1287
1288  *** add all functions
1289     R_ALV_FUNC = R_ALV->GET_FUNCTIONS( ).
1290     R_ALV_FUNC->SET_ALL( ABAP_TRUE ).
1291
1292  *** Selection Mode
1293    R_SELECTIONS = R_ALV->GET_SELECTIONS( ).
1294    R_SELECTIONS->SET_SELECTION_MODE( R_SELECTIONS->MULTIPLE ).
1295    R_SELECTIONS->SET_SELECTION_MODE( IF_SALV_C_SELECTION_MODE=>NONE ). "R
      OW_COLUMN
1296
1297
1298    R_EVENTS = R_ALV->GET_EVENT( ).
1299    CREATE OBJECT SS_GD-R_HANDLER_MANA.
1300  *** register to the event USER_COMMAND
1301  ***???  SET HANDLER SS_GD-R_EVENTS->ON_USER_COMMAND FOR R_EVENTS.
1302    SET HANDLER SS_GD-R_HANDLER_MANA->LINK_CLICK     FOR R_EVENTS.
1303    SET HANDLER SS_GD-R_HANDLER_MANA->ADDED_FUNCTION FOR R_EVENTS.
1304
1305    R_ALV->SET_SCREEN_STATUS(
1306        PFSTATUS      = 'SALV_POPUP_MAN_SCR'
1307        REPORT        = 'SAPLKESS'
1308        SET_FUNCTIONS = R_ALV->C_FUNCTIONS_ALL ).
1309
1310    SS_GD-R_ALV = R_ALV.
1311  *** display list
1312    R_ALV->DISPLAY( ).
1313
1314    CHECK SS_GD-R_ALV IS BOUND.
1315
1316    S_INIT-PRGNAME   = SS_GR_INT->S_SCR-PRGNAME.
1317    S_INIT-TABNAME   = SS_GR_INT->S_SCR-TABNAME.
1318
1319    READ TABLE SS_GD-T_SCR_MANAGE INTO S_MANA
1320      WITH KEY
1321         DEFAGLOB = ICON_CHECKED.
1322
1323    IF SY-SUBRC = 0.
1324  ** default global screen exists => redefine
1325      S_INIT-USERNAME  = ''.
1326      S_INIT-SCRNAME   = S_MANA-SCRNAME.
1327      MODIFY TKESS_SCR_INIT FROM S_INIT.
1328
1329    ELSE.
1330  ** No default global screen => delete current default settings if exists
1331      DELETE FROM TKESS_SCR_INIT
1332        WHERE
1333          PRGNAME  = SS_GR_INT->S_SCR-PRGNAME AND
1334          TABNAME  = SS_GR_INT->S_SCR-TABNAME AND
1335          USERNAME = ''.
1336    ENDIF.
1337
1338    READ TABLE SS_GD-T_SCR_MANAGE INTO S_MANA
1339      WITH KEY
1340         DEFAUSER = ICON_CHECKED.
1341
1342    IF SY-SUBRC = 0.
```

```
1343  ** default user screen exists => redefine
1344      S_INIT-USERNAME  = SY-UNAME.
1345      S_INIT-SCRNAME   = S_MANA-SCRNAME.
1346      MODIFY TKESS_SCR_INIT FROM S_INIT.
1347
1348    ELSE.
1349  ** No default user screen => delete current default settings if exists
1350  ** check for default variant
1351      IF S_INIT-VARNAME IS INITIAL.
1352        DELETE FROM TKESS_SCR_INIT
1353        WHERE
1354          PRGNAME  = SS_GR_INT->S_SCR-PRGNAME AND
1355          TABNAME  = SS_GR_INT->S_SCR-TABNAME AND
1356          USERNAME = SY-UNAME.
1357      ELSE.
1358        CLEAR S_INIT-SCRNAME.
1359        MODIFY TKESS_SCR_INIT FROM S_INIT.
1360
1361      ENDIF.
1362
1363    ENDIF.
1364
1365    FREE SS_GD-R_HANDLER_MANA.
1366    FREE SS_GD-R_ALV.
1367
1368    COMMIT WORK AND WAIT.
1369  *** update screen list values to exclude deleted screens
1370    PERFORM SS_INIT_LISTBOX_SCRNAME.
1371
1372  *** The changes made were saved so display status message
1373    MESSAGE s201(KT).
1374
1375  ENDFORM.                    " SS_EVENT_SY_UCOMM_PUSHMANA
1376
1377  *&---------------------------------------------------------------------*
1378  *&      Form  FC01_SAVE_SCR.
1379  *&---------------------------------------------------------------------*
1380  FORM SS_EVENT_SY_UCOMM_PUSHSAVE.
1381
1382    DATA:
1383      S_SCR LIKE TKESS_SCR .
1384
1385    MOVE-CORRESPONDING SS_GR_INT->S_SCR TO S_SCR.
1386
1387    CALL FUNCTION 'KESS_SAVE_SCREEN'
1388      EXPORTING
1389        IT_SS_SF       = SS_GR_INT->T_SS_SF
1390      CHANGING
1391        XS_SCR   = S_SCR.
1392
1393    MOVE-CORRESPONDING S_SCR TO SS_GR_INT->S_SCR.
1394    SCRNAME = S_SCR-SCRNAME.
1395
1396  *** determine current list of available screens
1397    PERFORM SS_INIT_LISTBOX_SCRNAME.
1398
1399  ENDFORM.                    " FC01_SAVE_SCR
1400
1401  *&---------------------------------------------------------------------*
1402  *&      Form  F4_SCRNAME_CHANGE.
1403  *&---------------------------------------------------------------------*
```

```
1404  *&      Check whether screen name was changed and if so set the new one
1405  *&---------------------------------------------------------------------*
1406
1407  FORM SS_SCREEN_CHECK_CHANGED.
1408  *** SCRNAME value changed by pushing listbox
1409
1410    IF SCRNAME IS NOT INITIAL AND
1411      SS_GR_INT->SCR_CHANGED = ABAP_TRUE AND
1412      SS_GR_INT->VARIANT_NAME IS INITIAL AND
1413      SS_GD-FIRST_INIT IS INITIAL.
1414  ** Do refresh & upload new screen definition
1415      PERFORM SS_SCREEN_SET
1416        USING PRGNAME
1417              KESSTABL
1418              SCRNAME
1419              ABAP_TRUE
1420              ABAP_FALSE.
1421
1422    ENDIF.
1423
1424    SS_GR_INT->SCR_CHANGED = ABAP_FALSE.
1425    SS_GD-FIRST_INIT       = ABAP_FALSE.
1426
1427  ENDFORM.
1428
1429  *&---------------------------------------------------------------------*
1430  *&      Form  INIT_LISTBOX_SCRNAME
1431  *&---------------------------------------------------------------------*
1432  *&      Determine available screen names list for listbox
1433  *&---------------------------------------------------------------------*
1434
1435  FORM SS_INIT_LISTBOX_SCRNAME.
1436
1437    DATA:
1438      SCRNAME   LIKE TKESS_SCR-SCRNAME,
1439      S_SCR     LIKE TKESS_SCR,
1440      T_SCREEN  TYPE KESS_YT_SCREEN.
1441
1442    DATA:
1443      ID  TYPE         VRM_ID,
1444      T_VALUE  TYPE      VRM_VALUES,
1445      S_VALUE LIKE LINE OF T_VALUE.
1446
1447    REFRESH SS_GD-T_SCREEN.
1448
1449  *** Find All Global & User Spec Screens
1450    SELECT * FROM TKESS_SCR INTO TABLE T_SCREEN
1451      WHERE PRGNAME   = SS_GR_INT->S_SCR-PRGNAME AND
1452            TABNAME   = SS_GR_INT->S_SCR-TABNAME AND
1453            USER_SPEC = ABAP_FALSE.
1454
1455    APPEND LINES OF T_SCREEN TO SS_GD-T_SCREEN.
1456
1457  *** Find All Global & User Spec Screens
1458    SELECT * FROM TKESS_SCR INTO TABLE T_SCREEN
1459      WHERE PRGNAME    = SS_GR_INT->S_SCR-PRGNAME AND
1460            TABNAME    = SS_GR_INT->S_SCR-TABNAME AND
1461            USER_SPEC  = ABAP_TRUE                AND
1462            CREATED_BY = SY-UNAME.
1463
1464    APPEND LINES OF T_SCREEN TO SS_GD-T_SCREEN.
```

```
1465
1466  *** Allow change of screen list
1467    SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_ALLOWED_SCREENS ).
1468
1469    LOOP AT SS_GD-T_SCREEN INTO S_SCR.
1470      S_VALUE-KEY = S_SCR-SCRNAME.
1471      APPEND S_VALUE TO T_VALUE.
1472    ENDLOOP.
1473
1474    ID = 'SCRNAME'.
1475  *** Set list of possible values
1476    CALL FUNCTION 'VRM_SET_VALUES'
1477      EXPORTING
1478        ID     = ID
1479        VALUES = T_VALUE.
1480
1481  ENDFORM.                    " INIT_LISTBOX_SCRNAME
1482  *&---------------------------------------------------------------------*
1483  *&      Form  SS_SCREEN_SET
1484  *&---------------------------------------------------------------------*
1485  FORM SS_SCREEN_SET
1486    USING
1487      I_PRGNAME  LIKE SYST-CPROG
1488      I_TABNAME TYPE TABNAME
1489      I_SCRNAME LIKE TKESS_SCR-SCRNAME
1490      I_REFRESH TYPE FLAG
1491      I_INIT    TYPE FLAG.
1492
1493    DATA:
1494      S_SCR     LIKE TKESS_SCR,
1495      S_FIELD   LIKE TKESS_SCR_FIELD,
1496      S_DESCR   LIKE TKESS_SCR_DESCR.
1497
1498  *** get header
1499    SELECT SINGLE * FROM TKESS_SCR INTO S_SCR
1500      WHERE PRGNAME    = I_PRGNAME  AND
1501            TABNAME    = I_TABNAME AND
1502            SCRNAME    = I_SCRNAME.
1503  *** Screen Variant doesn't exist
1504    IF SY-SUBRC <> 0.
1505      MESSAGE X899(KG).
1506    ENDIF.
1507
1508    IF I_REFRESH = ABAP_TRUE.
1509  *** Refresh Assignments
1510      PERFORM SS_SCREEN_REFRESH_ASSIGNMENT USING ABAP_FALSE.
1511      HIT_FOR_SCREEN_UPDATE.
1512    ENDIF.
1513
1514  *** Active/Displayed or Assigned Fields
1515    SELECT * FROM TKESS_SCR_FIELD INTO S_FIELD
1516      WHERE PRGNAME    = SS_GR_INT->S_SCR-PRGNAME  AND
1517            TABNAME    = SS_GR_INT->S_SCR-TABNAME AND
1518            SCRNAME    = SS_GR_INT->S_SCR-SCRNAME
1519      ORDER BY SEQUENCE.
1520
1521      SPLIT S_FIELD-TFNAME AT '-' INTO SS_TABLENAME SS_FIELDNAME.
1522
1523      READ TABLE SS_GR_INT->T_FCAT INTO SS_S_FCAT
1524        WITH KEY FIELDNAME = SS_FIELDNAME
1525                 TABNAME   = SS_TABLENAME
```

```
1526                EXCLUDED  = ''.
1527
1528      IF SY-SUBRC = 0.
1529        PERFORM SS_SO_ASSIGN
1530          USING S_FIELD-TFNAME.
1531      ENDIF.
1532
1533    ENDSELECT.
1534
1535    SELECT SINGLE * FROM TKESS_SCR_DESCR INTO S_DESCR
1536      WHERE PRGNAME    = SS_GR_INT->S_SCR-PRGNAME    AND
1537            TABNAME    = SS_GR_INT->S_SCR-TABNAME    AND
1538            SCRNAME    = SS_GR_INT->S_SCR-SCRNAME    AND
1539            LANGU      = SY-LANGU.
1540
1541    IF SY-SUBRC = 0.
1542      SS_GR_INT->DESCR = S_DESCR-SCRDESCR.
1543    ENDIF.
1544
1545
1546    SS_GR_INT->SCR_CHANGED = ABAP_FALSE.
1547  *** store definition of screen in memory to not loose
1548  *** info about impportant parameters after screen refresh
1549    SS_GR_INT->EXPORT_INSTANCE( ).
1550  ****** This is not initialization so 'real' refresh must take place
1551    IF I_INIT = ABAP_FALSE.
1552  ** Force System to Update Dynpro fields definition
1553      SSCRFIELDS-UCOMM = 'ONLI'.
1554  *** "Simulated" execution
1555      SS_GD-SIMUL_EXEC    = ABAP_TRUE.
1556    ENDIF.
1557
1558    HIT_FOR_SCREEN_UPDATE.
1559
1560  ENDFORM.                    " SS_SCREEN_SET
1561  *&---------------------------------------------------------------------*
1562  *&      Form  SS_SCREEN_DELETE
1563  *&---------------------------------------------------------------------*
1564  *&      Delete screen from DB
1565  *&---------------------------------------------------------------------*
1566  FORM SS_SCREEN_DELETE
1567    USING
1568       I_PRGNAME    TYPE PROGRAMM
1569       I_TABNAME    TYPE TABNAME
1570       I_SCRNAME    TYPE TKESS_SCR-SCRNAME
1571       I_ALL_LANGU TYPE FLAG.
1572
1573    DATA: S_INIT TYPE TKESS_SCR_INIT.
1574
1575  *** Descriptions(s)
1576  *** Delete description for current language only
1577    IF I_ALL_LANGU = ABAP_FALSE.
1578      DELETE FROM TKESS_SCR_DESCR
1579        WHERE PRGNAME    = I_PRGNAME AND
1580              TABNAME    = I_TABNAME AND
1581              SCRNAME    = I_SCRNAME AND
1582              LANGU      = SY-LANGU.
1583  ** delete descriptions in all languages
1584    ELSE.
1585      DELETE FROM TKESS_SCR_DESCR
1586        WHERE PRGNAME    = I_PRGNAME AND
```

```
1587              TABNAME    = I_TABNAME AND
1588              SCRNAME    = I_SCRNAME.
1589    ENDIF.
1590
1591  *** If variant is defined as default, delete entry
1592  ** determine default screen for user
1593    SELECT SINGLE * FROM TKESS_SCR_INIT INTO S_INIT
1594      WHERE PRGNAME    = I_PRGNAME  AND
1595            TABNAME    = I_TABNAME  AND
1596            SCRNAME    = I_SCRNAME.
1597
1598    IF SY-SUBRC = 0.
1599      IF S_INIT-VARNAME IS INITIAL.
1600  ** delete line when screen and var will be empty
1601        DELETE FROM TKESS_SCR_INIT
1602      WHERE PRGNAME    = I_PRGNAME AND
1603            TABNAME    = I_TABNAME AND
1604            SCRNAME    = I_SCRNAME.
1605
1606  ** if default variant is maintained only modify
1607      ELSE.
1608        CLEAR S_INIT-SCRNAME.
1609        MODIFY TKESS_SCR_INIT FROM S_INIT.
1610
1611      ENDIF.
1612    ENDIF.
1613
1614  *** Sel. screen fields definition
1615    DELETE FROM TKESS_SCR_FIELD
1616      WHERE PRGNAME    = I_PRGNAME AND
1617            TABNAME    = I_TABNAME AND
1618            SCRNAME    = I_SCRNAME.
1619
1620  *** Definition
1621    DELETE FROM TKESS_SCR
1622      WHERE PRGNAME    = I_PRGNAME AND
1623            TABNAME    = I_TABNAME AND
1624            SCRNAME    = I_SCRNAME.
1625
1626    COMMIT WORK.
1627
1628  ENDFORM.                    " DELETE_SCR
1629
1630
1631  *&---------------------------------------------------------------------*
1632  *&      Form SS_EVENT_SY_UCOMM_PUSHTABL.
1633  *&---------------------------------------------------------------------*
1634  *&      Popup to choose table/structure or view name
1635  *&---------------------------------------------------------------------*
1636
1637  FORM SS_EVENT_SY_UCOMM_PUSHTABL.
1638
1639   DATA: NEW_TABNAME TYPE TABNAME.
1640
1641    IF SS_GR_INT->EXPERT IS NOT INITIAL
1642      OR CHNG_TAB IS NOT INITIAL.
1643
1644
1645      CALL FUNCTION 'F4_DD_ALLTYPES'
1646        EXPORTING
1647          OBJECT = NEW_TABNAME
```

```
1648        IMPORTING
1649          RESULT = NEW_TABNAME.
1650
1651  ** Table name changed and not initial?
1652      IF NEW_TABNAME IS NOT INITIAL AND
1653         NEW_TABNAME <> KESSTABL.
1654
1655  * trigger actions connected to table name change
1656        PERFORM SS_SCREEN_TABLE_CHANGED
1657          USING NEW_TABNAME
1658                ABAP_FALSE    " no ad hoc table group
1659                ABAP_TRUE.    " do refresh
1660
1661      ENDIF.
1662    ENDIF.
1663
1664  ENDFORM.                     " SS_EVENT_SY_UCOMM_PUSHTABL.
1665
1666  *&---------------------------------------------------------------------*
1667  *&      Form SS_TABNAME_CHANGED
1668  *&---------------------------------------------------------------------*
1669  *&      Do needed in case table name was changed
1670  *&---------------------------------------------------------------------*
1671  FORM SS_SCREEN_TABLE_CHANGED
1672    USING I_TABLENAME     TYPE TABNAME
1673          I_AD_HOC_GROUP  TYPE SAP_BOOL
1674          I_REFRESH       TYPE SAP_BOOL.
1675
1676    SS_GR_INT->CLEAR_MEMORY( ).
1677
1678  ***
1679    KESSTABL = I_TABLENAME.
1680    CLEAR SCRNAME.
1681    REFRESH T_SS_TAB.
1682    REFRESH T_SS_EF.
1683
1684  *** Change table name
1685    SS_GR_INT->SET_TABLE( I_TABLENAME    = I_TABLENAME
1686                          I_AD_HOC_GROUP = I_AD_HOC_GROUP
1687                          I_REFRESH      = I_REFRESH ).
1688  *** Raise event for field catalogue adjustment
1689    SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_FIELDCAT_ADJUST ).
1690
1691    PERFORM SS_SCREEN_REFRESH_ASSIGNMENT USING ABAP_TRUE.
1692    SS_GR_INT->EXPORT_INSTANCE( ).
1693
1694    HIT_FOR_SCREEN_UPDATE.
1695  * perform screen initialization
1696    PERFORM SS_EVENT_INITIALIZATION.
1697
1698  ENDFORM.                     " SS_TABNAME_CHANGED
1699
1700  *&---------------------------------------------------------------------*
1701  *&      Form  SS_INIT_ICONS_AND_BUTTONS
1702  *&---------------------------------------------------------------------*
1703  *&      init screen buttons
1704  *&---------------------------------------------------------------------*
1705
1706  FORM SS_INIT_ICONS_AND_BUTTONS .
1707
1708  *** SubScreen Screen Definition is collapsed
```

```
1709    IF SS_GR_INT->SCR_DEF = ABAP_FALSE.
1710      ICON_CREATE ICON_DATA_AREA_EXPAND ' '
1711        SSTXT_18 PUSHDEFI. " 'Selection Screen Definition'(018)
1712  ** SubScreen Screen Definition is expanded
1713    ELSE.
1714      ICON_CREATE ICON_DATA_AREA_COLLAPSE ' '
1715        SSTXT_18 PUSHDEFI. " 'Selection Screen Definition'(018)
1716    ENDIF.
1717  *** button technical names
1718    PERFORM SS_BUTTON_STATUS_PUSHTNAM .
1719
1720
1721  *** SubScreen Screen Definition - Button Save Screen
1722    ICON_CREATE ICON_ALV_VARIANT_SAVE ' ' "ICON_SAVE_AS_TEMPLATE
1723      SSTXT_07 PUSHSAVE.  "'Save Selection Screen'(007)
1724
1725  *** SubScreen Screen Definition - Button Manage Screens
1726    ICON_CREATE ICON_WORKING_PLAN   ' '
1727      SSTXT_08  PUSHMANA.  "'Manage Selection Screens'(008)
1728
1729  *** SubScreen Screen Definition - Button Change Table
1730    ICON_CREATE ICON_FENCING   ' '
1731      SSTXT_06  PUSHTABL. " Change table name
1732
1733  *** SubScreen Screen Definition - Button Choose Fields
1734    ICON_CREATE ICON_ALV_VARIANTS SSTXT_16 "'Selection Criteria'(016) "ICO
      N_VIEW_FORM
1735      SSTXT_16 PUSHSLCR. " 'Selection Criteria'(016)
1736
1737    TRY.
1738  *** Determine table description
1739
1740      TAB_DESC =
1741        CL_KESS_FREE_SELECTION_INT=>GET_TABLE_DESCRIPTION( SS_GR_INT->S_SC
      R-TABNAME ).
1742  **Table group = no description.
1743
1744    ENDTRY.
1745
1746  ENDFORM.                    " SS_INIT_ICONS_AND_BUTTONS
1747
1748  *&---------------------------------------------------------------------*
1749  *&      Form  SS_BUTTON_STATUS_PUSHTNAM
1750  *&---------------------------------------------------------------------*
1751  *&      status button technical names
1752  *&---------------------------------------------------------------------*
1753
1754  FORM SS_BUTTON_STATUS_PUSHTNAM .
1755  *** Technical names button
1756    IF TECHNAME = ABAP_FALSE.
1757
1758      ICON_CREATE ICON_VIEW_SWITCH ' '    " ICON_DETAIL
1759        SSTXT_20 PUSHTNAM. "
1760
1761  **
1762    ELSE.
1763
1764      ICON_CREATE  ICON_VIEW_SWITCH ' '    "ICON_WD_CAPTION
1765        SSTXT_05 PUSHTNAM. "
1766
1767    ENDIF.
```

```
1768
1769  ENDFORM.                    " SS_BUTTON_STATUS_PUSHTNAM
1770  *&---------------------------------------------------------------------*
1771  *&      Form  SS_SCREEN_UPDATE_FROM_VARIANT
1772  *&---------------------------------------------------------------------*
1773  FORM SS_SCREEN_UPDATE_FROM_VARIANT
1774    USING I_VARIANT LIKE  RSVAR-VARIANT.
1775
1776    DATA:
1777      S_SS_SF  LIKE LINE OF T_SS_SF,
1778      S_SS_EF  LIKE LINE OF T_SS_EF,
1779      EXISTS   TYPE SAP_BOOL,
1780      S_SEQ       LIKE LINE OF SS_GR_INT->T_SS_SF,
1781      L_KESSTABL  LIKE KESSTABL,
1782      LT_T_SS_TAB LIKE TABLE OF RSDSSELOPT.
1783
1784    L_KESSTABL = KESSTABL.
1785    APPEND LINES OF T_SS_TAB TO LT_T_SS_TAB.
1786
1787  *** there is variant to be uploaded => do refresh
1788    PERFORM SS_SCREEN_REFRESH_ASSIGNMENT USING ABAP_TRUE.
1789  ****?
1790  *  DELETE FROM MEMORY ID SCREEN_DATA.
1791    HIT_FOR_SCREEN_UPDATE.
1792
1793  *** Get/load variant
1794  ** inspired by function RS_VARIANT_FETCH, keep everything the same
1795  **INCLUDE:    RSDBCSTY.
1796  *  DATA:
1797  *    RKEY      LIKE  RSVARKEY,
1798  *    T_SELCTAB TYPE TABLE OF RSSCR,
1799  *    T_VARI    TYPE TABLE OF RVARI,
1800  *    IMP_SUBRC LIKE SY-SUBRC,
1801  *    SSC_SUBRC LIKE SY-SUBRC VALUE 0.
1802  *
1803  *  RKEY-REPORT  = SY-CPROG.
1804  *  RKEY-VARIANT = I_VARIANT.
1805  *
1806  *  PERFORM IMPORT_VAR_SELC(SAPLSVAR)
1807  *    TABLES T_SELCTAB  T_VARI
1808  *    USING  SY-CPROG RKEY
1809  *    CHANGING IMP_SUBRC SSC_SUBRC.
1810  *
1811  *  IF IMP_SUBRC = 8.                " Variante veraltet
1812  *    IF SY-SUBTY Z SUBTY_FOREIGN_VARIS. " 40 = SUBTY_FOREIGN_VARIS in in
     clude RSDBCSTY
1813  *
1814  *      MESSAGE E634(DB)
1815  *        WITH RKEY-VARIANT RKEY-REPORT
1816  *        RAISING VARIANT_INCONSISTENT.
1817  *
1818  *     ELSE.
1819  *
1820  *       MESSAGE E775(DB)
1821  *         WITH RKEY-VARIANT RKEY-REPORT
1822  *         RAISING VARIANT_INCONSISTENT.
1823  *         ENDIF.
1824  *
1825  *     ENDIF.
1826  *
1827  *  PERFORM %_IMPORT_VARI_CLNT IN PROGRAM (SY-CPROG)
```

```
1828  *                              USING RKEY IMP_SUBRC SY-MANDT
1829  *                              CHANGING IMP_SUBRC
1830  *                              IF FOUND.
1831
1832    SS_GR_INT->VARIANT_NAME = I_VARIANT.
1833
1834  *  CALL FUNCTION 'RS_SUPPORT_SELECTIONS'
1835  *    EXPORTING
1836  *      REPORT                     = SY-CPROG
1837  *      VARIANT                    = I_VARIANT
1838  *    EXCEPTIONS
1839  *      VARIANT_NOT_EXISTENT       = 1
1840  *      VARIANT_OBSOLETE           = 2
1841  *      OTHERS                     = 3.
1842  *
1843  *  IF SY-SUBRC <> 0.
1844  *    CASE SY-SUBRC.
1845  *      WHEN 1.
1846  *        MESSAGE I612(DB) WITH I_VARIANT SY-CPROG.
1847  *      WHEN 2.
1848  *        MESSAGE I634(DB) WITH I_VARIANT SY-CPROG.
1849  *      WHEN 3.
1850  *        MESSAGE X612(DB) WITH I_VARIANT SY-CPROG.
1851  *    ENDCASE.
1852  *  ENDIF.
1853
1854  ************************************************************************
1855
1856  *** selection screen internal data determination from screen
1857    REFRESH SS_GR_INT->T_FCAT.
1858
1859    IF KESSTABL IS INITIAL.
1860  ** Safety assignment: in case of old variants, which were adjusted
1861  ** automatically by report, KESSTABL and T_SS_TAB are part of variant
1862  ** definition but filled with initial values.
1863  ** This leads into dump during check for table name - parameter KESSTABL
1864  ** later on by call of method set_table due to empty table name
1865      REFRESH T_SS_TAB.
1866      KESSTABL = L_KESSTABL.
1867      APPEND LINES OF LT_T_SS_TAB TO T_SS_TAB.
1868
1869    ENDIF.
1870
1871    IF KESSTABL <> '$'.
1872      SS_GR_INT->SET_TABLE( KESSTABL ).
1873    ELSE.
1874      LOOP AT T_SS_TAB.
1875        SS_GR_INT->SET_TABLE( I_TABLENAME     = T_SS_TAB-LOW
1876                              I_AD_HOC_GROUP  = ABAP_TRUE ).
1877      ENDLOOP.
1878
1879    ENDIF.
1880
1881    SS_GR_INT->DETERMINE_FCAT( ).
1882    SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_FIELDCAT_ADJUST ).
1883  *** Clearing of remaining values is not necessary and must be not perfor
      med
1884  *** because it will clear values obtained from variant.
1885    REFRESH SS_GR_INT->T_SS_CLEAR.
1886
1887  *** selected fields
```

```
1888    LOOP AT T_SS_SF INTO S_SS_SF.
1889  ** check whether field (still) exists in the table/structure def
1890      PERFORM SS_CHECK_FIELD_EXISTS
1891        USING
1892          S_SS_SF-HIGH
1893        CHANGING
1894          EXISTS.
1895
1896      IF EXISTS = ABAP_TRUE.
1897
1898        S_SEQ-TFNAME   = S_SS_SF-HIGH.
1899        S_SEQ-SEQUENCE = S_SS_SF-LOW.
1900
1901        APPEND S_SEQ TO SS_GR_INT->T_SS_SF.
1902
1903      ENDIF.
1904    ENDLOOP.
1905
1906    SORT SS_GR_INT->T_SS_SF BY SEQUENCE.
1907    SORT T_SS_SF BY LOW.
1908
1909  *** excluded fields
1910    LOOP AT T_SS_EF INTO S_SS_EF.
1911  ** check whether field (still) exists in the table/structure def
1912      PERFORM SS_CHECK_FIELD_EXISTS
1913        USING
1914          S_SS_SF-LOW
1915        CHANGING
1916          EXISTS.
1917
1918      IF EXISTS = ABAP_TRUE.
1919        APPEND S_SS_EF-LOW TO SS_GR_INT->T_SS_EF.
1920      ENDIF.
1921    ENDLOOP.
1922
1923  ***???
1924    REFRESH T_SS_TAB.
1925    APPEND LINES OF SS_GR_INT->T_SS_TAB TO T_SS_TAB.
1926
1927    SS_GD-FIRST_INIT = ABAP_FALSE.
1928
1929    PERFORM SS_SYNC_PAR_TO_GS.
1930
1931  ENDFORM.                    " SS_SCREEN_UPDATE_FROM_VARIANT
1932
1933  *&---------------------------------------------------------------------*
1934  *&      Form  SS_EVENT_SY_UCOMM_PUSHSLCR
1935  *&---------------------------------------------------------------------*
1936  ***       Popup to choose selected fields
1937  *----------------------------------------------------------------------*
1938  FORM SS_EVENT_SY_UCOMM_PUSHSLCR.
1939
1940    DATA:
1941      T_FIELDS  TYPE  RKE_YT_FIELD_SELECTION,
1942      S_FIELD   LIKE  LINE OF T_FIELDS,
1943      T_MARKED  TYPE  RKE_YT_FIELD_SELECTION,
1944      TITLE     TYPE TEXTPOOL-ENTRY,
1945      CHANGED   TYPE FLAG,
1946      S_SEQ         LIKE LINE OF SS_GR_INT->T_SS_SF,
1947      T_F       TYPE TABLE OF RSSCR_DBFI WITH DEFAULT KEY.
1948
```

```
1949  LOG-POINT ID fco_mse_op.
1950
1951  *** show fields, which can be used as select option in field popup
1952
1953  ** check groups provided by caller
1954    LOOP AT SS_GR_INT->T_FCAT TRANSPORTING NO FIELDS
1955      WHERE EXCLUDED = ABAP_FALSE AND GROUP IS NOT INITIAL.
1956      CHANGED = ABAP_TRUE.
1957      EXIT.
1958    ENDLOOP.
1959
1960  ** map into fieldcatalog for field popup
1961    LOOP AT SS_GR_INT->T_FCAT INTO SS_S_FCAT
1962      WHERE EXCLUDED = ABAP_FALSE.
1963
1964      S_FIELD-TABNAME    = SS_S_FCAT-TABNAME.
1965      S_FIELD-FNAM         = SS_S_FCAT-FIELDNAME.
1966      S_FIELD-TEXT         = SS_S_FCAT-SCRTEXT_M.
1967      S_FIELD-IS_MANDATORY = SS_S_FCAT-OBLIGATORY.
1968
1969  * given groups
1970      IF CHANGED = ABAP_TRUE.
1971        S_FIELD-GROUP     = SS_S_FCAT-GROUP.
1972        S_FIELD-GROUP_TXT = SS_S_FCAT-GROUP_TXT.
1973
1974  * default groups
1975      ELSE.
1976        IF SS_S_FCAT-DATATYPE = 'CURR' OR SS_S_FCAT-DATATYPE = 'QUAN' .
1977        S_FIELD-GROUP     = 'KEYF'.
1978        S_FIELD-GROUP_TXT = SSTXT_03.
1979      ELSE.
1980        S_FIELD-GROUP     = 'CHAR'.
1981        S_FIELD-GROUP_TXT = SSTXT_02.
1982      ENDIF.
1983      ENDIF.
1984
1985      APPEND S_FIELD TO T_FIELDS.
1986      CLEAR S_FIELD.
1987
1988    ENDLOOP.
1989
1990  ** Create list of selected fields = T_MARKED
1991    LOOP AT SS_GR_INT->T_SS_SF INTO S_SEQ.
1992
1993      SPLIT S_SEQ-TFNAME AT '-' INTO SS_TABLENAME SS_FIELDNAME.
1994
1995      READ TABLE T_FIELDS INTO S_FIELD
1996        WITH KEY
1997          FNAM = SS_FIELDNAME.
1998      IF SY-SUBRC = 0.
1999        DELETE T_FIELDS INDEX SY-TABIX.
2000        APPEND S_FIELD TO T_MARKED.
2001      ENDIF.
2002
2003    ENDLOOP.
2004
2005    CONCATENATE T_SS_TAB-LOW ' ' TAB_DESC INTO TITLE.
2006
2007  ** Show field popup
2008    CALL FUNCTION 'RKE_FIELD_SELECTION_POPUP'
2009      EXPORTING
```

```
2010        IT_FIELDLIST            = T_FIELDS
2011        I_MIN_COLUMNS           = SS_C_SO_MIN
2012        I_MAX_COLUMNS           = SS_C_SO_MAX
2013      CHANGING
2014        XT_COLUMNS              = T_MARKED.
2015
2016  ** Collect all fields defined by user to be used for selection
2017    LOOP AT T_MARKED INTO S_FIELD.
2018      CLEAR SS_S_FCAT.
2019      READ TABLE SS_GR_INT->T_FCAT INTO SS_S_FCAT
2020        WITH KEY
2021        TABNAME = S_FIELD-TABNAME
2022          FIELDNAME = S_FIELD-FNAM.
2023
2024  * something went wrong, field isn't in field catalogue
2025      IF SY-SUBRC <> 0.
2026        MESSAGE x899(KG).
2027      ENDIF.
2028
2029      CONCATENATE S_FIELD-TABNAME '-' S_FIELD-FNAM INTO SS_TFNAME.
2030      APPEND SS_TFNAME TO T_F.
2031
2032    ENDLOOP.
2033
2034  ** Fields
2035  ** 1. step determine fields selected before but not selected now
2036  **    and unassign relevant param and select option.
2037        LOOP AT SS_GR_INT->T_SS_SF INTO S_SEQ.
2038
2039          READ TABLE T_F
2040            WITH KEY S_SEQ-TFNAME
2041            TRANSPORTING NO FIELDS.
2042
2043          IF SY-SUBRC <> 0.
2044
2045            PERFORM SS_SO_UNASSIGN
2046              USING S_SEQ-TFNAME.
2047  ** Screen changed
2048            CHANGED = ABAP_TRUE.
2049          ENDIF.
2050
2051        ENDLOOP.
2052
2053        PERFORM SS_SO_TO_SEL USING PAR_C01  SO_C01[].
2054        PERFORM SS_SO_TO_SEL USING PAR_C02  SO_C02[].
2055        PERFORM SS_SO_TO_SEL USING PAR_C03  SO_C03[].
2056        PERFORM SS_SO_TO_SEL USING PAR_C04  SO_C04[].
2057        PERFORM SS_SO_TO_SEL USING PAR_C05  SO_C05[].
2058        PERFORM SS_SO_TO_SEL USING PAR_C06  SO_C06[].
2059        PERFORM SS_SO_TO_SEL USING PAR_C07  SO_C07[].
2060        PERFORM SS_SO_TO_SEL USING PAR_C08  SO_C08[].
2061        PERFORM SS_SO_TO_SEL USING PAR_C09  SO_C09[].
2062        PERFORM SS_SO_TO_SEL USING PAR_C10  SO_C10[].
2063        PERFORM SS_SO_TO_SEL USING PAR_C11  SO_C11[].
2064        PERFORM SS_SO_TO_SEL USING PAR_C12  SO_C12[].
2065        PERFORM SS_SO_TO_SEL USING PAR_C13  SO_C13[].
2066        PERFORM SS_SO_TO_SEL USING PAR_C14  SO_C14[].
2067        PERFORM SS_SO_TO_SEL USING PAR_C15  SO_C15[].
2068        PERFORM SS_SO_TO_SEL USING PAR_C16  SO_C16[].
2069        PERFORM SS_SO_TO_SEL USING PAR_C17  SO_C17[].
2070        PERFORM SS_SO_TO_SEL USING PAR_C18  SO_C18[].
```

```
2071        PERFORM SS_SO_TO_SEL USING PAR_C19  SO_C19[].
2072        PERFORM SS_SO_TO_SEL USING PAR_C20  SO_C20[].
2073        PERFORM SS_SO_TO_SEL USING PAR_C21  SO_C21[].
2074        PERFORM SS_SO_TO_SEL USING PAR_C22  SO_C22[].
2075        PERFORM SS_SO_TO_SEL USING PAR_C23  SO_C23[].
2076        PERFORM SS_SO_TO_SEL USING PAR_C24  SO_C24[].
2077        PERFORM SS_SO_TO_SEL USING PAR_C25  SO_C25[].
2078
2079        PERFORM SS_SCREEN_REFRESH_ASSIGNMENT USING ABAP_FALSE.
2080
2081  ** 2. step find fields not selected so far.
2082        LOOP AT T_F INTO SS_TFNAME.
2083
2084          READ TABLE SS_GR_INT->T_SS_SF
2085            WITH KEY TFNAME = SS_TFNAME
2086            TRANSPORTING NO FIELDS.
2087
2088          IF SY-SUBRC <> 0.
2089
2090            PERFORM SS_SO_ASSIGN  ##PERF_GLOBAL_PAR_OK
2091                USING SS_TFNAME.
2092  ** Screen changed
2093            CHANGED = ABAP_TRUE.
2094          ENDIF.
2095
2096        ENDLOOP.
2097
2098  *** Store definition of changed screen into memory to not loose
2099  *** info about important parameters after screen refresh
2100    SS_GR_INT->EXPORT_INSTANCE( ).
2101  *** and do refresh to get dynamic sel-options to update accordingly
2102  *** if needed - based on content of variable ONLI
2103    IF CHANGED = ABAP_TRUE.
2104      SSCRFIELDS-UCOMM = 'ONLI'.
2105  *** "Simulated" execution
2106      SS_GD-SIMUL_EXEC    = ABAP_TRUE.
2107    ENDIF.
2108
2109  ENDFORM.                    " SS_EVENT_SY_UCOMM_PUSHSLCR
2110  *&---------------------------------------------------------------------*
2111  *&      Form  SS_SYNC_PAR_TO_GS
2112  *&---------------------------------------------------------------------*
2113  FORM SS_SYNC_PAR_TO_GS.
2114  ** Synchronize internal data (GR_SS_INT) from parameters (in case someth
      ing
2115  ** has changed)
2116
2117    SS_GR_INT->SHOW_TAB  = SHOW_TAB.
2118    SS_GR_INT->CHNG_TAB  = CHNG_TAB.
2119
2120    SS_GR_INT->NOSCRDEF  = NOSCRDEF.
2121    SS_GR_INT->NOSCRNAM  = NOSCRNAM.
2122    SS_GR_INT->EXPERT    = EXPERT.
2123
2124    SS_GR_INT->S_SCR-SCRNAME   = SCRNAME.
2125
2126    SS_GR_INT->EXPORT_INSTANCE( ).
2127
2128  ENDFORM.                    " SS_SYNC_PAR_TO_GS
2129  *&---------------------------------------------------------------------*
2130  *&      Form  SYNC_SCR_TO_PARAM
```

```
2131  *&---------------------------------------------------------------------*
2132
2133  FORM SS_SYNC_GS_TO_PARAM .
2134
2135    PRGNAME  = SS_GR_INT->S_SCR-PRGNAME.
2136    KESSTABL = SS_GR_INT->S_SCR-TABNAME.
2137    SCRNAME  = SS_GR_INT->S_SCR-SCRNAME.
2138
2139    EXPERT   = SS_GR_INT->EXPERT.
2140
2141    SHOW_TAB = SS_GR_INT->SHOW_TAB.
2142    NOSCRDEF = SS_GR_INT->NOSCRDEF.
2143    NOSCRNAM = SS_GR_INT->NOSCRNAM.
2144    CHNG_TAB = SS_GR_INT->CHNG_TAB.
2145
2146    PERFORM SS_SO_UPDATE_EXCLUDED.
2147
2148    REFRESH T_SS_TAB.
2149    APPEND LINES OF SS_GR_INT->T_SS_TAB TO T_SS_TAB.
2150
2151  ENDFORM.                    " SS_SYNC_SCR_TO_PARAM
2152
2153  *&---------------------------------------------------------------------*
2154  *&      Form  SS_CLEAR_VALUES
2155  *&---------------------------------------------------------------------*
2156  *&      Clear  remaining values of SO (if needed) after new assignment
2157  *&---------------------------------------------------------------------*
2158  FORM SS_SCREEN_CLEAR_VALUES.
2159
2160  DATA: SO_NAME TYPE FIELDNAME.
2161  DATA: T_SO_NAME TYPE STRING.
2162
2163  FIELD-SYMBOLS:
2164    <T_SO> TYPE ANY TABLE.
2165  *** SS_GR_INT->T_SS_CLEAR contains SO to be cleared because  otherwise
2166  *** old values remain on the screen (after change of assignment)
2167    CHECK SS_GR_INT->T_SS_CLEAR IS NOT INITIAL.
2168  ***
2169    LOOP AT SS_GR_INT->T_SS_CLEAR INTO SO_NAME.
2170  ** determine name
2171      CONCATENATE SO_NAME '[]' INTO T_SO_NAME.
2172  ** <T_SO> is the 'Value'.
2173      ASSIGN (T_SO_NAME) TO <T_SO>.
2174  ** Clear it
2175      REFRESH <T_SO>.
2176    ENDLOOP.
2177
2178    REFRESH SS_GR_INT->T_SS_CLEAR.
2179
2180  ENDFORM.                    " SS_CLEAR_VALUES
2181
2182
2183  *&---------------------------------------------------------------------*
2184  *&      Form  BUTTON_DEFINITION
2185  *&---------------------------------------------------------------------*
2186  FORM SS_EVENT_SY_UCOMM_PUSHDEFI.
2187
2188    IF SS_GR_INT->SCR_DEF = ABAP_FALSE.
2189      SS_GR_INT->SCR_DEF = ABAP_TRUE.
2190    ELSE.
2191      SS_GR_INT->SCR_DEF = ABAP_FALSE.
```

```
2192    ENDIF.
2193
2194  ENDFORM.                    " BUTTON_DEFINITION
2195  *&---------------------------------------------------------------------*
2196  *&      Form  READ_TEXPOOL
2197  *&---------------------------------------------------------------------*
2198
2199  FORM SS_INIT_READ_TEXPOOL .
2200
2201    DATA: T_TEXT  TYPE TABLE OF TEXTPOOL,
2202          S_TEXT  LIKE LINE OF T_TEXT.
2203
2204  *** read textpool of SAP standard include (template)
2205    READ TEXTPOOL SS_C_TEXTPOOL INTO T_TEXT LANGUAGE SY-LANGU.
2206    SORT T_TEXT BY KEY.
2207  *** Fill relevant internal global 'text' variables
2208  *** Variables can be changed if required
2209    LOOP AT T_TEXT INTO S_TEXT
2210        WHERE ID = 'I'.
2211      CASE S_TEXT-KEY.
2212        WHEN  1. SSTXT_01 = S_TEXT-ENTRY.
2213        WHEN  2. SSTXT_02 = S_TEXT-ENTRY.
2214        WHEN  3. SSTXT_03 = S_TEXT-ENTRY.
2215        WHEN  4. SSTXT_04 = S_TEXT-ENTRY.
2216        WHEN  5. SSTXT_05 = S_TEXT-ENTRY.
2217        WHEN  6. SSTXT_06 = S_TEXT-ENTRY.
2218        WHEN  7. SSTXT_07 = S_TEXT-ENTRY.
2219        WHEN  8. SSTXT_08 = S_TEXT-ENTRY.
2220        WHEN  9. SSTXT_09 = S_TEXT-ENTRY.
2221        WHEN 10. SSTXT_10 = S_TEXT-ENTRY.
2222        WHEN 11. SSTXT_11 = S_TEXT-ENTRY.
2223        WHEN 12. SSTXT_12 = S_TEXT-ENTRY.
2224        WHEN 13. SSTXT_13 = S_TEXT-ENTRY.
2225        WHEN 14. SSTXT_14 = S_TEXT-ENTRY.
2226        WHEN 15. SSTXT_15 = S_TEXT-ENTRY.
2227        WHEN 16. SSTXT_16 = S_TEXT-ENTRY.
2228        WHEN 17. SSTXT_17 = S_TEXT-ENTRY.
2229        WHEN 18. SSTXT_18 = S_TEXT-ENTRY.
2230        WHEN 19. SSTXT_19 = S_TEXT-ENTRY.
2231        WHEN 20. SSTXT_20 = S_TEXT-ENTRY.
2232        WHEN 21. SSTXT_21 = S_TEXT-ENTRY.
2233        WHEN 22. SSTXT_22 = S_TEXT-ENTRY.
2234        WHEN 23. SSTXT_23 = S_TEXT-ENTRY.
2235        WHEN 24. SSTXT_24 = S_TEXT-ENTRY.
2236        WHEN 25. SSTXT_25 = S_TEXT-ENTRY.
2237        WHEN 26. SSTXT_26 = S_TEXT-ENTRY.
2238        WHEN 27. SSTXT_27 = S_TEXT-ENTRY.
2239        WHEN 28. SSTXT_28 = S_TEXT-ENTRY.
2240        WHEN 29. SSTXT_29 = S_TEXT-ENTRY.
2241        WHEN 30. SSTXT_30 = S_TEXT-ENTRY.
2242        WHEN 31. SSTXT_31 = S_TEXT-ENTRY.
2243        WHEN 32. SSTXT_32 = S_TEXT-ENTRY.
2244        WHEN 33. SSTXT_33 = S_TEXT-ENTRY.
2245        WHEN 34. SSTXT_34 = S_TEXT-ENTRY.
2246        WHEN 35. SSTXT_35 = S_TEXT-ENTRY.
2247        WHEN 36. SSTXT_36 = S_TEXT-ENTRY.
2248        WHEN 37. SSTXT_37 = S_TEXT-ENTRY.
2249        WHEN OTHERS.
2250      ENDCASE.
2251    ENDLOOP.
2252
```

```
2253  ENDFORM.                    " READ_TEXPOOL
2254  *&---------------------------------------------------------------------*
2255  *&      Form  SS_SELCRIT_OUTPUT
2256  *&---------------------------------------------------------------------*
2257  *&      Determines whether parameters used for SO definition
2258  *&      and SOs are displayed and in which way
2259  *&---------------------------------------------------------------------*
2260  FORM SS_SO_1SET_OUTPUT
2261    CHANGING SCREEN LIKE SCREEN.
2262
2263    CHECK SCREEN-GROUP1 = 'SSC'.
2264  ** determine action/handling based on the element type
2265    CASE SCREEN-GROUP3.
2266  ** PAR - Parameter
2267      WHEN 'PAR'.
2268        PERFORM SS_SO_PAR_OUTPUT
2269          CHANGING SCREEN.
2270  ** SO OPTI_PUSH option icon before low value in case that option isn't E
      Q or BT
2271      WHEN 'OPU'.
2272  ** Do nothing!!! it's handled by system automatically.
2273
2274  ** COF - COMMENT of SO or PAR on the left side done by statement SELSCRE
      EN COMMENT
2275      WHEN 'COF'.
2276        PERFORM SS_SO_COF_OUTPUT
2277          CHANGING SCREEN.
2278  ** SO TEXT - Description of SO on the left side
2279      WHEN 'TXT'.
2280        PERFORM SS_SO_TXT_OUTPUT
2281          CHANGING SCREEN.
2282  ** SO LOW value of interval
2283      WHEN 'LOW'.
2284        PERFORM SS_SO_LOW_OUTPUT
2285          CHANGING SCREEN.
2286  ** SO 'To' text between LOW and HIGH
2287      WHEN 'TOT'.
2288        PERFORM SS_SO_TOT_OUTPUT
2289          CHANGING SCREEN.
2290  ** SO HIGH value of interval
2291      WHEN 'HGH'. " high value of interval
2292        PERFORM SS_SO_HGH_OUTPUT
2293          CHANGING SCREEN.
2294  ** SO VALU_PUSH push button on the righ side, which allows more select o
      ptions
2295      WHEN 'VPU'.
2296        PERFORM SS_SO_VPU_OUTPUT
2297          CHANGING SCREEN.
2298  ** Nothing else should be possible for selection criteria
2299      WHEN OTHERS.
2300    ENDCASE.
2301
2302  ENDFORM.                    " SS_SELCRIT_OUTPUT
2303
2304
2305  *&---------------------------------------------------------------------*
2306  *&      Form  SS_PAR_OUTPUT
2307  *&---------------------------------------------------------------------*
2308  FORM SS_SO_PAR_OUTPUT
2309    CHANGING SCREEN LIKE SCREEN.
2310
```

```
2311  ***  FIELD-SYMBOLS:
2312  ***    <NAME>   TYPE RSSCR_DBFI.
2313
2314  *** Visibility of parameters for dynamic definition of select-options
2315  *    ASSIGN  (SCREEN-NAME) TO <NAME>.
2316  *    IF <NAME> IS INITIAL AND SS_GR_INT->EXPERT = ABAP_TRUE.
2317  *      SCREEN-INPUT  = 1.   SCREEN-ACTIVE = 1.
2318  *    ELSE.
2319        SCREEN-INPUT  = 0.   SCREEN-ACTIVE = 0.
2320  *    ENDIF.
2321
2322  ENDFORM.                    " SS_PAR_OUTPUT
2323
2324  *&---------------------------------------------------------------------*
2325  *&      Form  SS_TXT_OUTPUT
2326  *&---------------------------------------------------------------------*
2327  FORM SS_SO_TXT_OUTPUT
2328    CHANGING SCREEN LIKE SCREEN.
2329
2330    DATA:
2331      PARAM      TYPE FIELDNAME.
2332
2333    FIELD-SYMBOLS:
2334      <NAME>   TYPE RSSCR_DBFI.
2335
2336
2337  ** display / hide or other attributes for PARAM
2338      IF SCREEN-NAME(7) = '%_PAR_C'.
2339        CONCATENATE 'PAR_C' SCREEN-NAME+7(2) INTO  PARAM.
2340      ENDIF.
2341  ** display / hide or other attributes for PARAM
2342      IF SCREEN-NAME(7) = '%_PAR_V'.
2343        CONCATENATE 'PAR_V' SCREEN-NAME+7(2) INTO  PARAM.
2344      ENDIF.
2345  ** display / hide or other attributes for SO
2346      IF SCREEN-NAME(6) = '%_SO_C'.
2347        CONCATENATE 'PAR_C' SCREEN-NAME+6(2) INTO  PARAM.
2348      ENDIF.
2349
2350      ASSIGN  (PARAM) TO <NAME>.
2351
2352      IF SCREEN-NAME(5) = '%_PAR'.
2353        IF <NAME> IS INITIAL AND SS_GR_INT->EXPERT = ABAP_TRUE.
2354          SCREEN-INPUT  = 1. SCREEN-ACTIVE = 1.
2355        ELSE.
2356          SCREEN-INPUT  = 0. SCREEN-ACTIVE = 0.
2357        ENDIF.
2358      ENDIF.
2359
2360      IF SCREEN-NAME(6) = '%_SO_C'.
2361        IF <NAME> IS INITIAL.
2362            SCREEN-INPUT  = 0.  SCREEN-ACTIVE = 0.
2363        ELSE.
2364            SCREEN-INPUT  = 1.  SCREEN-ACTIVE = 1.
2365        ENDIF.
2366      ENDIF.
2367
2368  ENDFORM.                    " SS_TXT_OUTPUT
2369
2370  *&---------------------------------------------------------------------*
2371  *&      Form  SS_LOW_OUTPUT
```

```
2372  *&---------------------------------------------------------------------*
2373  FORM SS_SO_LOW_OUTPUT
2374    CHANGING SCREEN LIKE SCREEN.
2375
2376    DATA:
2377      PARAM       TYPE RSSCR_DBFI,
2378      TXT_SO      TYPE FIELDNAME,
2379      NO_INPUT    TYPE FLAG,
2380      OBLIGATORY  TYPE FLAG,
2381      INTENSIFIED TYPE FLAG.
2382
2383    FIELD-SYMBOLS:
2384      <NAME>      TYPE ANY,
2385      <TXT_SO>    TYPE ANY.
2386  ** Visibility of dynamic of select-options
2387  ** if relevant parameter is empty then SO is not defined and hidden
2388  ** if relevant parameter is filled, then SO is defined and displayed
2389  ** FROM and TO value
2390    CASE SCREEN-NAME(4).
2391      WHEN 'SO_C'.
2392        CONCATENATE 'PAR_C' SCREEN-NAME+4(2) INTO  PARAM.
2393      WHEN 'SO_V'.
2394        CONCATENATE 'PAR_V' SCREEN-NAME+4(2) INTO  PARAM.
2395      WHEN 'SO_U'.
2396        CONCATENATE 'PAR_U' SCREEN-NAME+4(2) INTO  PARAM.
2397      WHEN OTHERS.
2398
2399    ENDCASE.
2400
2401    ASSIGN  (PARAM) TO <NAME>.
2402
2403    IF <NAME> IS INITIAL.
2404      SCREEN-INPUT       = 0.
2405      SCREEN-ACTIVE      = 0.
2406      SCREEN-REQUIRED    = 0.
2407      SCREEN-INTENSIFIED = 0.
2408
2409    ELSE.
2410      SCREEN-INPUT       = 1.
2411      SCREEN-ACTIVE      = 1.
2412      SCREEN-REQUIRED    = 0.
2413      SCREEN-INTENSIFIED = 0.
2414  ** is it display only field?
2415      NO_INPUT =
2416        SS_GR_INT->GET_SO_ATTRIBUTE( I_SO          =  <NAME>
2417                                     I_NO_INPUT = ABAP_TRUE ).
2418
2419      IF NO_INPUT = ABAP_TRUE.
2420        SCREEN-INPUT = 0.
2421      ENDIF.
2422  ** is it mandatory?
2423      OBLIGATORY =
2424        SS_GR_INT->GET_SO_ATTRIBUTE( I_SO          =  <NAME>
2425                                     I_OBLIGATORY = ABAP_TRUE ).
2426
2427      IF OBLIGATORY = ABAP_TRUE.
2428        SCREEN-REQUIRED = 1.
2429      ENDIF.
2430  ** intensified?
2431      INTENSIFIED =
2432        SS_GR_INT->GET_SO_ATTRIBUTE( I_SO          =  <NAME>
```

```
2433                                       I_INTENSIFIED = ABAP_TRUE ).
2434
2435      IF INTENSIFIED = ABAP_TRUE.
2436        SCREEN-INTENSIFIED = 1.
2437      ENDIF.
2438
2439    ENDIF.
2440
2441  ** Comment text e.g. field name for value SO
2442    IF SCREEN-NAME(3) = 'SO_' AND SCREEN-ACTIVE = 1.
2443
2444      SPLIT <NAME> AT '-' INTO SS_TABLENAME SS_FIELDNAME.
2445      CASE SCREEN-NAME(4).
2446        WHEN 'SO_V'.
2447          CONCATENATE 'TXT_V' SCREEN-NAME+4(2) INTO TXT_SO.
2448        WHEN 'SO_C'.
2449          CONCATENATE 'TXT_C' SCREEN-NAME+4(2) INTO TXT_SO.
2450        WHEN OTHERS.
2451          RETURN.
2452      ENDCASE.
2453
2454      ASSIGN (TXT_SO) TO <TXT_SO>.
2455
2456      IF TECHNAME IS INITIAL.
2457  **  display Label e.g. medium text
2458        READ TABLE SS_GR_INT->T_FCAT INTO SS_S_FCAT
2459          WITH KEY
2460            FIELDNAME = SS_FIELDNAME.
2461
2462        IF STRLEN( SS_S_FCAT-SCRTEXT_L ) <= 25. "See text on the screen le
     ngth
2463          <TXT_SO> = SS_S_FCAT-SCRTEXT_L.
2464        ELSE.
2465          <TXT_SO> = SS_S_FCAT-SCRTEXT_M.
2466        ENDIF.
2467  * in case there is no text for current langues display tech. name
2468        IF <TXT_SO> IS INITIAL.
2469  * display technical name
2470          <TXT_SO> = <NAME>.
2471        ENDIF.
2472      ELSE.
2473  * display technical name
2474        <TXT_SO> = <NAME>.
2475      ENDIF.
2476    ENDIF.
2477  ENDFORM.                    " SS_LOW_OUTPUT
2478
2479
2480  *&---------------------------------------------------------------------*
2481  *&      Form  SS_TOT_OUTPUT
2482  *&---------------------------------------------------------------------*
2483  FORM SS_SO_TOT_OUTPUT
2484    CHANGING SCREEN LIKE SCREEN.
2485
2486    DATA:
2487      PARAM        TYPE RSSCR_DBFI,
2488      NO_INTERVALS TYPE FLAG.
2489
2490    FIELD-SYMBOLS:
2491      <NAME>   TYPE ANY.
2492
```

```
2493  ** display / hide or other attributes for SO
2494        CASE SCREEN-NAME(6).
2495          WHEN '%_SO_V'.
2496            CONCATENATE 'PAR_V' SCREEN-NAME+6(2) INTO  PARAM.
2497          WHEN '%_SO_C'.
2498            CONCATENATE 'PAR_C' SCREEN-NAME+6(2) INTO  PARAM.
2499          WHEN '%_SO_U'.
2500            CONCATENATE 'PAR_U' SCREEN-NAME+6(2) INTO  PARAM.
2501          WHEN OTHERS.
2502        ENDCASE.
2503
2504        ASSIGN  (PARAM) TO <NAME>.
2505
2506        IF <NAME> IS INITIAL.
2507          SCREEN-INPUT  = 0.
2508          SCREEN-ACTIVE = 0.
2509        ELSE.
2510          SCREEN-INPUT  = 1.
2511          SCREEN-ACTIVE = 1.
2512  ** No intervals?
2513          NO_INTERVALS =
2514            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO           =  <NAME>
2515                                         I_NO_INTERVALS = ABAP_TRUE ).
2516
2517          IF NO_INTERVALS = ABAP_TRUE.
2518            SCREEN-ACTIVE = 0.
2519          ENDIF.
2520
2521        ENDIF.
2522
2523  ENDFORM.                    " SS_TOT_OUTPUT
2524
2525  *&---------------------------------------------------------------------*
2526  *&      Form  SS_HGH_OUTPUT
2527  *&---------------------------------------------------------------------*
2528  FORM SS_SO_HGH_OUTPUT
2529    CHANGING SCREEN LIKE SCREEN.
2530
2531    DATA:
2532      PARAM        TYPE RSSCR_DBFI,
2533      NO_INTERVALS TYPE FLAG,
2534      NO_INPUT     TYPE FLAG,
2535      INTENSIFIED  TYPE FLAG.
2536
2537    FIELD-SYMBOLS:
2538      <NAME>   TYPE ANY.
2539
2540  ** Visibility of dynamic of select-options
2541  ** if relevant parameter is empty then SO is not defined and hidden
2542  ** if relevant parameter is filled, then SO is defined and displayed
2543  ** FROM and TO value
2544        CASE SCREEN-NAME(4).
2545          WHEN 'SO_C'.
2546            CONCATENATE 'PAR_C' SCREEN-NAME+4(2) INTO  PARAM.
2547          WHEN 'SO_V'.
2548            CONCATENATE 'PAR_V' SCREEN-NAME+4(2) INTO  PARAM.
2549        ENDCASE.
2550
2551        ASSIGN  (PARAM) TO <NAME>.
2552
2553        IF <NAME> IS INITIAL.
```

```
2554          SCREEN-INPUT       = 0.
2555          SCREEN-ACTIVE      = 0.
2556          SCREEN-INTENSIFIED = 0.
2557        ELSE.
2558          SCREEN-INPUT       = 1.
2559          SCREEN-ACTIVE      = 1.
2560          SCREEN-INTENSIFIED = 0.
2561
2562          NO_INTERVALS =
2563            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO           =  <NAME>
2564                                         I_NO_INTERVALS = ABAP_TRUE ).
2565
2566
2567          IF NO_INTERVALS = ABAP_TRUE.
2568            SCREEN-ACTIVE = 0.
2569          ENDIF.
2570
2571    ** display only?
2572          NO_INPUT =
2573            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO       =  <NAME>
2574                                         I_NO_INPUT = ABAP_TRUE ).
2575
2576          IF NO_INPUT = ABAP_TRUE.
2577            SCREEN-INPUT = 0.
2578          ENDIF.
2579    ** intensified?
2580          INTENSIFIED =
2581            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO          =  <NAME>
2582                                         I_INTENSIFIED = ABAP_TRUE ).
2583
2584          IF INTENSIFIED = ABAP_TRUE.
2585            SCREEN-INTENSIFIED = 1.
2586          ENDIF.
2587
2588        ENDIF.
2589
2590    ENDFORM.                    " SS_HGH_OUTPUT
2591
2592    *&---------------------------------------------------------------------*
2593    *&      Form  SS_VPU_OUTPUT
2594    *&---------------------------------------------------------------------*
2595    *&      display of extension button
2596    *&---------------------------------------------------------------------*
2597
2598    FORM SS_SO_VPU_OUTPUT
2599      CHANGING SCREEN LIKE SCREEN.
2600
2601      DATA:
2602        PARAM        TYPE RSSCR_DBFI,
2603        NO_EXTENSION TYPE FLAG.
2604
2605      FIELD-SYMBOLS:
2606        <NAME>   TYPE ANY.
2607
2608    ** display / hide or other attributes for SO
2609        CASE SCREEN-NAME(6).
2610          WHEN '%_SO_V'.
2611            CONCATENATE 'PAR_V' SCREEN-NAME+6(2) INTO  PARAM.
2612          WHEN '%_SO_C'.
2613            CONCATENATE 'PAR_C' SCREEN-NAME+6(2) INTO  PARAM.
2614          WHEN  '%_SO_U'.
```

```
2615            CONCATENATE 'PAR_U' SCREEN-NAME+6(2) INTO  PARAM.
2616          WHEN OTHERS.
2617        ENDCASE.
2618        ASSIGN  (PARAM) TO <NAME>.
2619        IF <NAME> IS INITIAL.
2620          SCREEN-ACTIVE = 0.
2621        ELSE.
2622          SCREEN-ACTIVE = 1.
2623  ** no extension?
2624          NO_EXTENSION =
2625            SS_GR_INT->GET_SO_ATTRIBUTE( I_SO           =  <NAME>
2626                                         I_NO_EXTENSION = ABAP_TRUE ).
2627
2628          IF NO_EXTENSION = ABAP_TRUE.
2629            SCREEN-ACTIVE = 0.
2630          ENDIF.
2631
2632        ENDIF.
2633
2634  ENDFORM.                    " SS_VPU_OUTPUT
2635
2636  *&---------------------------------------------------------------------*
2637  *&      Form  SS_SO_COF_OUTPUT
2638  *&---------------------------------------------------------------------*
2639  *&      COF - COMMENT of SO or PAR e.g. name,
2640  *&      displayed on the left side done by statement SELSCREEN COMMENT
2641  *&---------------------------------------------------------------------*
2642
2643  FORM SS_SO_COF_OUTPUT
2644    CHANGING SCREEN LIKE SCREEN.
2645
2646    DATA:
2647      PARAM      TYPE RSSCR_DBFI.
2648
2649    FIELD-SYMBOLS:
2650      <NAME>   TYPE ANY.
2651
2652
2653  *** Description e.g. name of SO
2654   CASE SCREEN-NAME(5).
2655     WHEN 'TXT_V'.
2656      CONCATENATE 'PAR_V' SCREEN-NAME+5(2) INTO  PARAM.
2657     WHEN 'TXT_C'.
2658      CONCATENATE 'PAR_C' SCREEN-NAME+5(2) INTO  PARAM.
2659     WHEN OTHERS.
2660   ENDCASE.
2661
2662
2663    ASSIGN  (PARAM) TO <NAME>.
2664    IF <NAME> IS INITIAL.
2665      SCREEN-ACTIVE = 0.
2666    ELSE.
2667      SCREEN-ACTIVE = 1.
2668    ENDIF.
2669
2670  ENDFORM.                    " SS_SO_COF_OUTPUT
2671
2672  *&---------------------------------------------------------------------*
2673  *&      Form  SS_SO_UPDATE_EXCLUDED
2674  *&---------------------------------------------------------------------*
2675  *&      Update
```

```
2676  *&---------------------------------------------------------------------*
2677  FORM SS_SO_UPDATE_EXCLUDED.
2678
2679    DATA:
2680      S_FCAT LIKE LINE OF SS_GR_INT->T_FCAT.
2681
2682    REFRESH T_SS_EF.
2683
2684    LOOP AT SS_GR_INT->T_FCAT INTO S_FCAT
2685      WHERE EXCLUDED = ABAP_TRUE.
2686
2687        CONCATENATE S_FCAT-TABNAME '-' S_FCAT-FIELDNAME INTO T_SS_EF-LOW.
2688        COLLECT T_SS_EF.
2689
2690    ENDLOOP.
2691
2692  ENDFORM.                    " SS_SO_UPDATE_EXCLUDED
2693
2694  *&---------------------------------------------------------------------*
2695  *&      Form  SS_PRESEL_SET_TRANGE
2696  *&---------------------------------------------------------------------*
2697  *&      Display preselection on the beginning
2698  *&---------------------------------------------------------------------*
2699  FORM SS_PRESEL_SET_TRANGE
2700    USING    IT_PRESEL TYPE RSDS_TRANGE.
2701
2702  DATA: S_TRANGE TYPE RSDS_RANGE,
2703        S_FRANGE TYPE RSDS_FRANGE.
2704
2705    LOOP AT IT_PRESEL INTO S_TRANGE.
2706      LOOP AT S_TRANGE-FRANGE_T INTO S_FRANGE.
2707
2708        PERFORM SS_PRESEL_SET_FRANGE
2709          USING S_TRANGE-TABLENAME
2710                S_FRANGE.
2711      ENDLOOP.
2712    ENDLOOP.
2713
2714  ENDFORM.                    " SS_PRESEL_SET_TRANGE
2715
2716  *&---------------------------------------------------------------------*
2717  *&      Form  SS_SET_TPRESEL
2718  *&---------------------------------------------------------------------*
2719  *&      Display preselection for concrete field = SO
2720  *&---------------------------------------------------------------------*
2721  FORM SS_PRESEL_SET_FRANGE
2722    USING
2723      I_TABLENAME LIKE RSDSTABS-PRIM_TAB
2724      IS_FRANGE   TYPE RSDS_FRANGE.
2725
2726
2727  DATA: NAME LIKE RSSCR-DBFIELD,
2728        S_SELOPT   TYPE RSDSSELOPT.
2729
2730  CHECK IS_FRANGE-SELOPT_T IS NOT INITIAL.
2731
2732
2733  CONCATENATE I_TABLENAME '-' IS_FRANGE-FIELDNAME INTO NAME.
2734  ************************************************************************
2735  DEFINE SO_SET_PRESEL.
2736
```

```
2737    LOOP AT IS_FRANGE-SELOPT_T INTO S_SELOPT.
2738      APPEND S_SELOPT TO &1.
2739    ENDLOOP.
2740
2741  END-OF-DEFINITION.
2742  ************************************************************************
2743
2744    IF PAR_C01 = NAME. SO_SET_PRESEL SO_C01.  ENDIF.
2745    IF PAR_C02 = NAME. SO_SET_PRESEL SO_C02.  ENDIF.
2746    IF PAR_C03 = NAME. SO_SET_PRESEL SO_C03.  ENDIF.
2747    IF PAR_C04 = NAME. SO_SET_PRESEL SO_C04.  ENDIF.
2748    IF PAR_C05 = NAME. SO_SET_PRESEL SO_C05.  ENDIF.
2749    IF PAR_C06 = NAME. SO_SET_PRESEL SO_C06.  ENDIF.
2750    IF PAR_C07 = NAME. SO_SET_PRESEL SO_C07.  ENDIF.
2751    IF PAR_C08 = NAME. SO_SET_PRESEL SO_C08.  ENDIF.
2752    IF PAR_C09 = NAME. SO_SET_PRESEL SO_C09.  ENDIF.
2753    IF PAR_C10 = NAME. SO_SET_PRESEL SO_C10.  ENDIF.
2754    IF PAR_C11 = NAME. SO_SET_PRESEL SO_C11.  ENDIF.
2755    IF PAR_C12 = NAME. SO_SET_PRESEL SO_C12.  ENDIF.
2756    IF PAR_C13 = NAME. SO_SET_PRESEL SO_C13.  ENDIF.
2757    IF PAR_C14 = NAME. SO_SET_PRESEL SO_C14.  ENDIF.
2758    IF PAR_C15 = NAME. SO_SET_PRESEL SO_C15.  ENDIF.
2759    IF PAR_C16 = NAME. SO_SET_PRESEL SO_C16.  ENDIF.
2760    IF PAR_C17 = NAME. SO_SET_PRESEL SO_C17.  ENDIF.
2761    IF PAR_C18 = NAME. SO_SET_PRESEL SO_C18.  ENDIF.
2762    IF PAR_C19 = NAME. SO_SET_PRESEL SO_C19.  ENDIF.
2763    IF PAR_C20 = NAME. SO_SET_PRESEL SO_C20.  ENDIF.
2764    IF PAR_C21 = NAME. SO_SET_PRESEL SO_C21.  ENDIF.
2765    IF PAR_C22 = NAME. SO_SET_PRESEL SO_C22.  ENDIF.
2766    IF PAR_C23 = NAME. SO_SET_PRESEL SO_C23.  ENDIF.
2767    IF PAR_C24 = NAME. SO_SET_PRESEL SO_C24.  ENDIF.
2768    IF PAR_C25 = NAME. SO_SET_PRESEL SO_C25.  ENDIF.
2769
2770    IF PAR_V01 = NAME. SO_SET_PRESEL SO_V01.  ENDIF.
2771    IF PAR_V02 = NAME. SO_SET_PRESEL SO_V02.  ENDIF.
2772    IF PAR_V03 = NAME. SO_SET_PRESEL SO_V03.  ENDIF.
2773    IF PAR_V04 = NAME. SO_SET_PRESEL SO_V04.  ENDIF.
2774    IF PAR_V05 = NAME. SO_SET_PRESEL SO_V05.  ENDIF.
2775    IF PAR_V06 = NAME. SO_SET_PRESEL SO_V06.  ENDIF.
2776    IF PAR_V07 = NAME. SO_SET_PRESEL SO_V07.  ENDIF.
2777    IF PAR_V08 = NAME. SO_SET_PRESEL SO_V08.  ENDIF.
2778    IF PAR_V09 = NAME. SO_SET_PRESEL SO_V09.  ENDIF.
2779    IF PAR_V10 = NAME. SO_SET_PRESEL SO_V10.  ENDIF.
2780    IF PAR_V11 = NAME. SO_SET_PRESEL SO_V11.  ENDIF.
2781    IF PAR_V12 = NAME. SO_SET_PRESEL SO_V12.  ENDIF.
2782    IF PAR_V13 = NAME. SO_SET_PRESEL SO_V13.  ENDIF.
2783    IF PAR_V14 = NAME. SO_SET_PRESEL SO_V14.  ENDIF.
2784    IF PAR_V15 = NAME. SO_SET_PRESEL SO_V15.  ENDIF.
2785    IF PAR_V16 = NAME. SO_SET_PRESEL SO_V16.  ENDIF.
2786    IF PAR_V17 = NAME. SO_SET_PRESEL SO_V17.  ENDIF.
2787    IF PAR_V18 = NAME. SO_SET_PRESEL SO_V18.  ENDIF.
2788    IF PAR_V19 = NAME. SO_SET_PRESEL SO_V19.  ENDIF.
2789    IF PAR_V20 = NAME. SO_SET_PRESEL SO_V20.  ENDIF.
2790    IF PAR_V21 = NAME. SO_SET_PRESEL SO_V21.  ENDIF.
2791    IF PAR_V22 = NAME. SO_SET_PRESEL SO_V22.  ENDIF.
2792    IF PAR_V23 = NAME. SO_SET_PRESEL SO_V23.  ENDIF.
2793    IF PAR_V24 = NAME. SO_SET_PRESEL SO_V24.  ENDIF.
2794    IF PAR_V25 = NAME. SO_SET_PRESEL SO_V25.  ENDIF.
2795
2796    IF PAR_U01 = NAME. SO_SET_PRESEL SO_U01.  ENDIF.
2797    IF PAR_U02 = NAME. SO_SET_PRESEL SO_U02.  ENDIF.
```

```
2798    IF PAR_U03 = NAME. SO_SET_PRESEL SO_U03.  ENDIF.
2799    IF PAR_U04 = NAME. SO_SET_PRESEL SO_U04.  ENDIF.
2800    IF PAR_U05 = NAME. SO_SET_PRESEL SO_U05.  ENDIF.
2801    IF PAR_U06 = NAME. SO_SET_PRESEL SO_U06.  ENDIF.
2802    IF PAR_U07 = NAME. SO_SET_PRESEL SO_U07.  ENDIF.
2803    IF PAR_U08 = NAME. SO_SET_PRESEL SO_U08.  ENDIF.
2804    IF PAR_U09 = NAME. SO_SET_PRESEL SO_U09.  ENDIF.
2805    IF PAR_U10 = NAME. SO_SET_PRESEL SO_U10.  ENDIF.
2806    IF PAR_U11 = NAME. SO_SET_PRESEL SO_U11.  ENDIF.
2807    IF PAR_U12 = NAME. SO_SET_PRESEL SO_U12.  ENDIF.
2808    IF PAR_U13 = NAME. SO_SET_PRESEL SO_U13.  ENDIF.
2809    IF PAR_U14 = NAME. SO_SET_PRESEL SO_U14.  ENDIF.
2810    IF PAR_U15 = NAME. SO_SET_PRESEL SO_U15.  ENDIF.
2811    IF PAR_U16 = NAME. SO_SET_PRESEL SO_U16.  ENDIF.
2812    IF PAR_U17 = NAME. SO_SET_PRESEL SO_U17.  ENDIF.
2813    IF PAR_U18 = NAME. SO_SET_PRESEL SO_U18.  ENDIF.
2814    IF PAR_U19 = NAME. SO_SET_PRESEL SO_U19.  ENDIF.
2815    IF PAR_U20 = NAME. SO_SET_PRESEL SO_U20.  ENDIF.
2816    IF PAR_U21 = NAME. SO_SET_PRESEL SO_U21.  ENDIF.
2817    IF PAR_U22 = NAME. SO_SET_PRESEL SO_U22.  ENDIF.
2818    IF PAR_U23 = NAME. SO_SET_PRESEL SO_U23.  ENDIF.
2819    IF PAR_U24 = NAME. SO_SET_PRESEL SO_U24.  ENDIF.
2820    IF PAR_U25 = NAME. SO_SET_PRESEL SO_U25.  ENDIF.
2821
2822  ENDFORM.                    " SS_SET_FPRESEL
2823
2824  *&---------------------------------------------------------------------*
2825  *&      Form  SS_INIT_ADJUST_SO_TO_EQUAL
2826  *&---------------------------------------------------------------------*
2827  *       set only single values attribute for some screen fields
2828  *----------------------------------------------------------------------*
2829  FORM SS_INIT_ADJUST_SO_TO_EQUAL.
2830
2831  ***  selected, excluded fields and table names are single values only
2832    DATA:
2833      S_OPTLIST  TYPE SSCR_OPT_LIST,
2834      S_RESTRICT TYPE SSCR_RESTRICT,
2835      S_ASS      TYPE SSCR_ASS.
2836
2837  *** only single values
2838    S_OPTLIST-NAME       = 'ONLY_EQUAL'.
2839    S_OPTLIST-OPTIONS-EQ = ABAP_TRUE.
2840    APPEND S_OPTLIST TO S_RESTRICT-OPT_LIST_TAB.
2841
2842    S_ASS-KIND    = 'S'.
2843    S_ASS-NAME    = 'T_SS_TAB'.
2844    S_ASS-SG_MAIN = 'I'.
2845    S_ASS-OP_MAIN = 'ONLY_EQUAL'.
2846    S_ASS-OP_ADDY = 'ONLY_EQUAL'.
2847    APPEND S_ASS TO S_RESTRICT-ASS_TAB.
2848
2849  *  S_ASS-NAME    = 'T_SS_SF'.
2850  *  APPEND S_ASS TO S_RESTRICT-ASS_TAB.
2851
2852    S_ASS-NAME    = 'T_SS_EF'.
2853    APPEND S_ASS TO S_RESTRICT-ASS_TAB.
2854
2855
2856    CALL FUNCTION 'SELECT_OPTIONS_RESTRICT'
2857      EXPORTING
2858        RESTRICTION = S_RESTRICT
```

```
2859      EXCEPTIONS
2860        OTHERS      = 1.
2861
2862    IF SY-SUBRC <> 0.
2863  *    MESSAGE ID SY-MSGID TYPE SY-MSGTY NUMBER SY-MSGNO
2864  *      WITH SY-MSGV1 SY-MSGV2 SY-MSGV3 SY-MSGV4.
2865    ENDIF.
2866
2867  ENDFORM.                    "SS_INIT_ADJUST_SO_TO_EQUAL
2868
2869
2870  *&---------------------------------------------------------------------*
2871  *&      Form  SS_EVENT_AT_SELSCR_OUTPUT
2872  *&---------------------------------------------------------------------*
2873  *&      One from the most important forms.
2874  *&      This form determines what parameters and SOs have
2875  *&      to be displayed on the screen and in which way
2876  *&      Handling of dynamic selection screen is done in
2877  *&      form SS_SELCRIT_OUTPUT
2878  *&---------------------------------------------------------------------*
2879  FORM SS_EVENT_AT_SELSCR_OUTPUT .
2880
2881  *** Determine whether screen name was changed.
2882  *** If so this will trigger screen definition change
2883  *** within call of form SS_CHECK_SCRNAME_CHANGED
2884    IF SS_GR_INT->S_SCR-SCRNAME <> SCRNAME.
2885      SS_GR_INT->SCR_CHANGED = ABAP_TRUE.
2886    ENDIF.
2887  *** Synchronize content of GR_SS_INT according values from screen
2888  *** for the ones, which can be changed
2889    PERFORM SS_SYNC_PAR_TO_GS.
2890
2891    PERFORM SS_SYNC_SF.
2892
2893  *** determine text for current screen name
2894    SCRDESCR = SS_GR_INT->GET_SCREEN_DESCRIPTION( ).
2895
2896  *** button technical names
2897    PERFORM SS_BUTTON_STATUS_PUSHTNAM .
2898
2899  *** Clear values after any screen change
2900    PERFORM SS_SCREEN_CLEAR_VALUES.
2901
2902    DATA: LD_FIELDNAME TYPE RSSCR_DBFI.
2903    DATA: LD_TABNAME TYPE TABNAME.
2904
2905    IF PAR_C01 IS NOT INITIAL.
2906      SPLIT PAR_C01 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2907      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2908                                 LD_FIELDNAME
2909                           CHANGING SO_C01[].
2910    ENDIF.
2911    IF PAR_C02 IS NOT INITIAL.
2912      SPLIT PAR_C02 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2913      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2914                                 LD_FIELDNAME
2915                           CHANGING SO_C02[].
2916    ENDIF.
2917    IF PAR_C03 IS NOT INITIAL.
2918      SPLIT PAR_C03 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2919      PERFORM SS_SEL_TO_SO USING LD_TABNAME
```

```
2920                                LD_FIELDNAME
2921                           CHANGING SO_C03[].
2922    ENDIF.
2923    IF PAR_C04 IS NOT INITIAL.
2924      SPLIT PAR_C04 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2925      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2926                                LD_FIELDNAME
2927                           CHANGING SO_C04[].
2928    ENDIF.
2929    IF PAR_C05 IS NOT INITIAL.
2930      SPLIT PAR_C05 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2931      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2932                                LD_FIELDNAME
2933                           CHANGING SO_C05[].
2934    ENDIF.
2935    IF PAR_C06 IS NOT INITIAL.
2936      SPLIT PAR_C06 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2937      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2938                                LD_FIELDNAME
2939                           CHANGING SO_C06[].
2940    ENDIF.
2941    IF PAR_C07 IS NOT INITIAL.
2942      SPLIT PAR_C07 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2943      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2944                                LD_FIELDNAME
2945                           CHANGING SO_C07[].
2946    ENDIF.
2947    IF PAR_C08 IS NOT INITIAL.
2948      SPLIT PAR_C08 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2949      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2950                                LD_FIELDNAME
2951                           CHANGING SO_C08[].
2952    ENDIF.
2953    IF PAR_C09 IS NOT INITIAL.
2954      SPLIT PAR_C09 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2955      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2956                                LD_FIELDNAME
2957                           CHANGING SO_C09[].
2958    ENDIF.
2959    IF PAR_C10 IS NOT INITIAL.
2960      SPLIT PAR_C10 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2961      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2962                                LD_FIELDNAME
2963                           CHANGING SO_C10[].
2964    ENDIF.
2965    IF PAR_C11 IS NOT INITIAL.
2966      SPLIT PAR_C11 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2967      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2968                                LD_FIELDNAME
2969                           CHANGING SO_C11[].
2970    ENDIF.
2971    IF PAR_C12 IS NOT INITIAL.
2972      SPLIT PAR_C12 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2973      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2974                                LD_FIELDNAME
2975                           CHANGING SO_C12[].
2976    ENDIF.
2977    IF PAR_C13 IS NOT INITIAL.
2978      SPLIT PAR_C13 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2979      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2980                                LD_FIELDNAME
```

```
2981                          CHANGING SO_C13[].
2982    ENDIF.
2983    IF PAR_C14 IS NOT INITIAL.
2984      SPLIT PAR_C14 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2985      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2986                                 LD_FIELDNAME
2987                          CHANGING SO_C14[].
2988    ENDIF.
2989    IF PAR_C15 IS NOT INITIAL.
2990      SPLIT PAR_C15 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2991      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2992                                 LD_FIELDNAME
2993                          CHANGING SO_C15[].
2994    ENDIF.
2995    IF PAR_C16 IS NOT INITIAL.
2996      SPLIT PAR_C16 AT '-' INTO LD_TABNAME LD_FIELDNAME.
2997      PERFORM SS_SEL_TO_SO USING LD_TABNAME
2998                                 LD_FIELDNAME
2999                          CHANGING SO_C16[].
3000    ENDIF.
3001    IF PAR_C17 IS NOT INITIAL.
3002      SPLIT PAR_C17 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3003      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3004                                 LD_FIELDNAME
3005                          CHANGING SO_C17[].
3006    ENDIF.
3007    IF PAR_C18 IS NOT INITIAL.
3008      SPLIT PAR_C18 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3009      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3010                                 LD_FIELDNAME
3011                          CHANGING SO_C18[].
3012    ENDIF.
3013    IF PAR_C19 IS NOT INITIAL.
3014      SPLIT PAR_C19 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3015      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3016                                 LD_FIELDNAME
3017                          CHANGING SO_C19[].
3018    ENDIF.
3019    IF PAR_C20 IS NOT INITIAL.
3020      SPLIT PAR_C20 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3021      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3022                                 LD_FIELDNAME
3023                          CHANGING SO_C20[].
3024    ENDIF.
3025    IF PAR_C21 IS NOT INITIAL.
3026      SPLIT PAR_C21 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3027      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3028                                 LD_FIELDNAME
3029                          CHANGING SO_C21[].
3030    ENDIF.
3031    IF PAR_C22 IS NOT INITIAL.
3032      SPLIT PAR_C22 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3033      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3034                                 LD_FIELDNAME
3035                          CHANGING SO_C22[].
3036    ENDIF.
3037    IF PAR_C23 IS NOT INITIAL.
3038      SPLIT PAR_C23 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3039      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3040                                 LD_FIELDNAME
3041                          CHANGING SO_C23[].
```

```
3042    ENDIF.
3043    IF PAR_C24 IS NOT INITIAL.
3044      SPLIT PAR_C24 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3045      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3046                                 LD_FIELDNAME
3047                           CHANGING SO_C24[].
3048    ENDIF.
3049    IF PAR_C25 IS NOT INITIAL.
3050      SPLIT PAR_C25 AT '-' INTO LD_TABNAME LD_FIELDNAME.
3051      PERFORM SS_SEL_TO_SO USING LD_TABNAME
3052                                 LD_FIELDNAME
3053                           CHANGING SO_C25[].
3054    ENDIF.
3055
3056  *** Set initial/predefined selection
3057    IF SS_GD-FIRST_OUTPUT = ABAP_TRUE.
3058  *   PERFORM SS_PRESEL_SET_TRANGE USING SS_GR_INT->T_TRANGE.
3059  *   REFRESH SS_GR_INT->T_TRANGE.
3060     SS_GD-FIRST_OUTPUT = ABAP_FALSE.
3061    ENDIF.
3062
3063    IF SS_GR_INT->T_TRANGE IS NOT INITIAL.
3064      REFRESH SS_GR_INT->T_TRANGE.
3065    ENDIF.
3066
3067  *** Determine outlook of the screen definition button
3068    IF SS_GR_INT->SCR_DEF = ABAP_FALSE.
3069      ICON_CREATE ICON_DATA_AREA_EXPAND   ' ' SSTXT_18 PUSHDEFI.
3070    ELSE.
3071      ICON_CREATE ICON_DATA_AREA_COLLAPSE ' ' SSTXT_18 PUSHDEFI.
3072    ENDIF.
3073
3074  *** Hide display fields on the screen
3075    LOOP AT SCREEN.
3076
3077      IF SCREEN-GROUP1 = 'SYS'.
3078        IF SS_GR_INT->EXPERT = ABAP_TRUE.
3079          SCREEN-ACTIVE = 1.
3080        ELSE.
3081          SCREEN-ACTIVE = 0.
3082        ENDIF.
3083      ENDIF.
3084
3085      IF SCREEN-GROUP1 = 'SYT'.
3086        IF SS_GR_INT->EXPERT = ABAP_TRUE AND SS_GR_INT->SHOW_TAB = ABAP_TR
      UE.
3087          SCREEN-ACTIVE = 1.
3088        ELSE.
3089          SCREEN-ACTIVE = 0.
3090        ENDIF.
3091      ENDIF.
3092
3093      IF SCREEN-GROUP1 = 'SYD'.
3094        IF SS_GR_INT->EXPERT = ABAP_TRUE.
3095          IF SCREEN-GROUP3 <> 'VPU'.
3096            SCREEN-INPUT = 0.
3097          ELSE.
3098            SCREEN-INPUT = 1.
3099          ENDIF.
3100        ELSE.
3101          SCREEN-ACTIVE = 0.
```

```
3102        ENDIF.
3103      ENDIF.
3104
3105  ** in expert mode is always everything displayed
3106      IF NOSCRDEF = ABAP_TRUE.
3107
3108        IF SCREEN-GROUP1 = 'TBS' OR
3109           SCREEN-GROUP1 = 'TBC' OR
3110           SCREEN-GROUP1 = 'DEF' OR
3111           SCREEN-GROUP1 = 'DEG' OR
3112           SCREEN-GROUP1 = 'BDF'.
3113             SCREEN-ACTIVE = 0.
3114        ENDIF.
3115
3116      ELSE.
3117  ** Display/hide tabname
3118        IF SCREEN-GROUP1 = 'BDF'.
3119           SCREEN-ACTIVE = 1.
3120        ENDIF.
3121
3122        IF  SCREEN-GROUP1 = 'DEG'.
3123          IF SS_GR_INT->SCR_DEF = ABAP_TRUE.
3124            SCREEN-ACTIVE = 1.
3125          ELSE.
3126            SCREEN-ACTIVE = 0.
3127          ENDIF.
3128        ENDIF.
3129
3130        IF SCREEN-GROUP1 = 'DEF'.
3131          IF SS_GR_INT->SCR_DEF = ABAP_TRUE AND
3132             SS_GR_INT->NOSCRNAM = ABAP_FALSE.
3133
3134            SCREEN-ACTIVE = 1.
3135          ELSE.
3136            SCREEN-ACTIVE = 0.
3137          ENDIF.
3138        ENDIF.
3139  ** Table/structure value can't be changed? in simple way
3140  ** display mode only for the table name
3141        IF SCREEN-GROUP1 = 'TBS'.
3142          SCREEN-INPUT = 0.
3143          IF SS_GR_INT->SCR_DEF = ABAP_TRUE AND
3144             SS_GR_INT->SHOW_TAB <> ABAP_FALSE.
3145            SCREEN-ACTIVE = 1.
3146          ELSE.
3147            SCREEN-ACTIVE = 0.
3148          ENDIF.
3149        ENDIF.
3150  ** There is button GROUP1 = 'TBC', which allows change of table name
3151        IF SCREEN-GROUP1 = 'TBC'.
3152          IF SS_GR_INT->SCR_DEF = ABAP_TRUE AND
3153             SS_GR_INT->CHNG_TAB = ABAP_TRUE AND
3154             SS_GR_INT->SHOW_TAB = ABAP_TRUE.
3155
3156            SCREEN-ACTIVE = 1.
3157            SCREEN-INPUT  = 1.
3158          ELSE.
3159            SCREEN-ACTIVE = 0.
3160          ENDIF.
3161        ENDIF.
3162
```

```
3163      ENDIF.
3164
3165  ************************************************************************
3166  *** Selection Criteria - handling of dynamic definition and options
3167     PERFORM SS_SO_1SET_OUTPUT
3168       CHANGING SCREEN.
3169
3170    MODIFY SCREEN.
3171
3172    ENDLOOP.
3173
3174  ENDFORM.                    " SS_EVENT_AT_SELSCR_OUTPUT
3175
3176  *&---------------------------------------------------------------------*
3177  *&      Form  SS_VARIANTS_GET
3178  *&---------------------------------------------------------------------*
3179  *&      Get variants
3180  *&---------------------------------------------------------------------*
3181  FORM SS_VARIANTS_GET
3182    CHANGING   XT_VARIANT TYPE KESS_YT_RSVARTXT.
3183
3184    APPEND LINES OF SS_GD-T_VARIANT TO XT_VARIANT.
3185
3186  ENDFORM.                    " SS_VARIANTS_GET
3187
3188  *&---------------------------------------------------------------------*
3189  *&      Form  SS_VARIANTS_SET
3190  *&---------------------------------------------------------------------*
3191  *&      Get variants
3192  *&---------------------------------------------------------------------*
3193  FORM SS_VARIANTS_SET
3194    USING   IT_VARIANT TYPE KESS_YT_RSVARTXT.
3195
3196    REFRESH SS_GD-T_VARIANT.
3197    APPEND LINES OF IT_VARIANT TO SS_GD-T_VARIANT.
3198
3199  ENDFORM.                    " SS_VARIANTS_SET
3200
3201  *&---------------------------------------------------------------------*
3202  *&      Form  SS_SCREENS_GET
3203  *&---------------------------------------------------------------------*
3204  *&      Get variants
3205  *&---------------------------------------------------------------------*
3206  FORM SS_SCREENS_GET
3207    CHANGING   XT_SCREEN TYPE KESS_YT_SCREEN.
3208
3209    APPEND LINES OF SS_GD-T_SCREEN TO XT_SCREEN.
3210
3211  ENDFORM.                    " SS_SCREENS_GET
3212
3213  *&---------------------------------------------------------------------*
3214  *&      Form  SS_SCREENS_SET
3215  *&---------------------------------------------------------------------*
3216  *&      Get variants
3217  *&---------------------------------------------------------------------*
3218  FORM SS_SCREENS_SET
3219    USING   IT_SCREEN TYPE KESS_YT_SCREEN.
3220
3221    REFRESH SS_GD-T_SCREEN.
3222    APPEND LINES OF IT_SCREEN TO SS_GD-T_SCREEN.
3223
```

```
3224  ENDFORM.                    " SS_SCREENS_SET
3225
3226  *&---------------------------------------------------------------------*
3227  *&      Form  CHECK_FIELD_EXIST
3228  *&---------------------------------------------------------------------*
3229  *       text
3230  *----------------------------------------------------------------------*
3231  FORM SS_CHECK_FIELD_EXISTS
3232    USING
3233      I_SO TYPE RSSCR_DBFI
3234    CHANGING
3235      X_EXISTS TYPE SAP_BOOL.
3236
3237    X_EXISTS = ABAP_FALSE.
3238
3239    SPLIT I_SO AT '-' INTO SS_TABLENAME SS_FIELDNAME.
3240
3241    READ TABLE SS_GR_INT->T_FCAT TRANSPORTING NO FIELDS
3242      WITH KEY
3243        TABNAME   = SS_TABLENAME
3244        FIELDNAME = SS_FIELDNAME.
3245
3246    IF SY-SUBRC = 0.
3247      X_EXISTS = ABAP_TRUE.
3248    ENDIF.
3249
3250
3251  ENDFORM.
3252
3253  *&---------------------------------------------------------------------*
3254  *&      Form  SS_EVENT_SY_UCOMM_GET
3255  *&---------------------------------------------------------------------*
3256  *&      Get variant
3257  *&---------------------------------------------------------------------*
3258  FORM SS_EVENT_SY_UCOMM_GET.
3259
3260    IF SS_GR_INT->VARIANT_STANDARD IS INITIAL.
3261  ** KESS variants handling
3262      PERFORM SS_VARIANT_GET_KESS.
3263
3264    ELSE.
3265  ** almost standard (display) variants handling
3266      PERFORM SS_VARIANT_GET_STANDARD.
3267
3268    ENDIF.
3269
3270  ENDFORM.                    " SS_EVENT_SY_UCOMM_GET
3271
3272  *&---------------------------------------------------------------------*
3273  *&      Form  SS_VARIANT_GET_KESS
3274  *&---------------------------------------------------------------------*
3275  *&      Adjusted get variant function
3276  *&---------------------------------------------------------------------*
3277  FORM SS_VARIANT_GET_KESS.
3278  *** Get variant
3279    DATA:
3280      S_VARIANT LIKE RSVARIINFO,
3281      T_VALUE   TYPE TABLE OF RSPARAMS,
3282      S_VALUE   LIKE RSPARAMS.
3283
3284    DATA:
```

```
3285      T_ROWS       TYPE SALV_T_ROW,
3286      TABIX        LIKE SY-TABIX,
3287      ROWS         TYPE I,
3288      R_DS         TYPE REF TO CL_SALV_DISPLAY_SETTINGS,
3289      R_COLUMNS    TYPE REF TO CL_SALV_COLUMNS_TABLE,
3290      R_COLUMN     TYPE REF TO CL_SALV_COLUMN,
3291      R_SELECTIONS TYPE REF TO CL_SALV_SELECTIONS,
3292  *    R_ALV_FUNC   TYPE REF TO CL_SALV_FUNCTIONS_LIST,
3293  ***  register to the events of cl_salv_table
3294      R_EVENTS     TYPE REF TO CL_SALV_EVENTS_TABLE.
3295
3296    DATA:
3297      T_SCREENS     TYPE STANDARD TABLE OF RSDYNNR,
3298      T_DYNNR       TYPE STANDARD TABLE OF RSDYNNR,
3299      END_COLUMN    TYPE I VALUE 65,
3300      END_LINE      TYPE I VALUE 15.
3301
3302    DATA:
3303      S_VARINFO     TYPE RSVARIINFO,
3304      S_PRORANGE    TYPE RSPRORANGE,
3305      T_PRORANGE    LIKE STANDARD TABLE OF S_PRORANGE,
3306      T_VARINFO     LIKE STANDARD TABLE OF S_VARINFO,
3307      T_VAR_RANGE   TYPE STANDARD TABLE OF RSVARRANGE,
3308      T_TEXT_RANGE  TYPE STANDARD TABLE OF RSTEXRANGE,
3309      T_CREATED_BY  TYPE STANDARD TABLE OF RSNAMRANGE,
3310      T_CHANGED_BY  TYPE STANDARD TABLE OF RSNAMRANGE,
3311      T_CREADATE    TYPE STANDARD TABLE OF RSDATRANGE,
3312      T_CHANGEDATE  TYPE STANDARD TABLE OF RSDATRANGE,
3313      TEXT_M        TYPE SCRTEXT_M,
3314      TEXT_L        TYPE SCRTEXT_L,
3315      OUTPUT_LENGTH TYPE LVC_OUTLEN,
3316      DDIC_O_LENGTH TYPE OUTPUTLEN.
3317
3318    S_PRORANGE-SIGN   = 'I'.
3319    S_PRORANGE-OPTION = 'EQ'.
3320    S_PRORANGE-LOW    = SY-CPROG.
3321    APPEND S_PRORANGE TO T_PRORANGE.
3322
3323    REFRESH  SS_GD-T_VARIANT.
3324  ** GET ALL VARIANTS FOR CURRENT PROGRAM
3325    CALL FUNCTION 'RS_VARIANT_INFO'
3326      TABLES
3327        PROG_RANGE                 = T_PRORANGE
3328        VAR_RANGE                  = T_VAR_RANGE
3329        TEXT_RANGE                 = T_TEXT_RANGE
3330        CREATED_BY                 = T_CREATED_BY
3331        CHANGED_BY                 = T_CHANGED_BY
3332        CREADATE                   = T_CREADATE
3333        CHANGEDATE                 = T_CHANGEDATE
3334        VARIANT_INFO               = SS_GD-T_VARIANT
3335      EXCEPTIONS
3336        OTHERS                     = 1.
3337  ** In case of error, there is nothing to do
3338    IF SY-SUBRC <> 0.
3339      RETURN.
3340    ENDIF.
3341
3342  * filter variants by transport-flag
3343    IF SS_GD-T_VARIANT[] IS NOT INITIAL.
3344      SELECT * FROM VARID INTO CORRESPONDING FIELDS OF TABLE SS_GD-T_VARIA
      NT
```

```
3345        FOR ALL ENTRIES IN SS_GD-T_VARIANT
3346        WHERE REPORT  = SS_GD-T_VARIANT-REPORT  AND
3347              VARIANT = SS_GD-T_VARIANT-VARIANT AND
3348              TRANSPORT <> 'X'                  AND
3349              TRANSPORT <> 'N'.
3350    ENDIF.
3351
3352    DESCRIBE TABLE SS_GD-T_VARIANT LINES ROWS.
3353    IF ROWS > SS_C_VARLIST.
3354      CLEAR SS_GD-T_VARIANT.
3355      DATA: LD_CONTINUE TYPE FLAG.
3356
3357      CALL FUNCTION 'KESS_FILTER_VARIANTS'
3358        EXPORTING
3359          ID_REPORT           = SY-CPROG
3360        TABLES
3361          CT_RSVARIINFO       = SS_GD-T_VARIANT
3362        CHANGING
3363          C_CONTINUE          = LD_CONTINUE.
3364
3365      IF LD_CONTINUE IS INITIAL.
3366        EXIT.
3367      ENDIF.
3368    ENDIF.
3369
3370  *** keep only variants for current selection screen (SY-DYNNR)
3371    LOOP AT SS_GD-T_VARIANT INTO S_VARIANT.
3372
3373      REFRESH T_SCREENS.
3374
3375      CALL FUNCTION 'RS_GET_SCREENS_4_1_VARIANT'
3376        EXPORTING
3377          PROGRAM                     =  SY-CPROG
3378          VARIANT                     =  S_VARIANT-VARIANT
3379        TABLES
3380          DYNNR                       =  T_DYNNR
3381          VARISCREENS                 =  T_SCREENS
3382        EXCEPTIONS
3383          NO_SCREENS                  = 1
3384          VARIANT_NOT_EXISTENT        = 2
3385          OTHERS                      = 3.
3386
3387      IF SY-SUBRC <> 0.
3388  * Implement suitable error handling here
3389      ENDIF.
3390  ** is it 'general' variant? means DYNNR = '*'
3391      READ TABLE T_SCREENS
3392        WITH KEY DYNNR = '*'
3393        TRANSPORTING NO FIELDS.
3394  ** if it's variant not for screen 1000 e.g. DYNNR <> '*'
3395      IF SY-SUBRC <> 0.
3396  * only variants for current selection screen
3397        READ TABLE T_SCREENS
3398          WITH KEY DYNNR = SY-DYNNR
3399          TRANSPORTING NO FIELDS.
3400        IF SY-SUBRC <> 0.
3401          DELETE SS_GD-T_VARIANT.
3402        ENDIF.
3403      ENDIF.
3404
3405    ENDLOOP.
```

```
3406
3407  *** display variants only for current table?
3408    IF SS_GR_INT->VARIANT_KESS_TABLE = ABAP_TRUE.
3409  ** loop over all variants
3410      LOOP AT SS_GD-T_VARIANT INTO S_VARIANT.
3411  * determine variant definition
3412        CALL FUNCTION 'RS_VARIANT_CONTENTS'
3413          EXPORTING
3414            REPORT                    = SY-REPID
3415            VARIANT                   = S_VARIANT-VARIANT
3416          TABLES
3417            VALUTAB                   = T_VALUE
3418         EXCEPTIONS
3419           VARIANT_NON_EXISTENT       = 1
3420           VARIANT_OBSOLETE           = 2
3421           OTHERS                     = 3.
3422
3423  * In case of error, exclude variant from the list
3424        IF SY-SUBRC <> 0.
3425          CONTINUE.
3426        ENDIF.
3427  * Is it variant for current table name
3428        READ TABLE T_VALUE INTO S_VALUE
3429          WITH KEY SELNAME = 'KESSTABL'.
3430
3431        IF SY-SUBRC = 0.
3432  * No, it isn't remove variant from the list of variants
3433          IF S_VALUE-LOW <> KESSTABL.
3434  * remove from the list variants not defined for current table name
3435            DELETE SS_GD-T_VARIANT.
3436          ENDIF.
3437        ENDIF.
3438
3439      ENDLOOP.
3440
3441    ENDIF.
3442
3443    SS_GR_EXT->RAISE( SS_GR_EXT->EVENT_ALLOWED_VARIANTS ).
3444
3445  *** No variant exists for current PRGNAME and table
3446    IF SS_GD-T_VARIANT IS INITIAL.
3447      MESSAGE s114(KB). "List contains no data
3448      RETURN.
3449    ELSE.
3450      DESCRIBE TABLE SS_GD-T_VARIANT LINES ROWS.
3451    ENDIF.
3452
3453    TRY.
3454        CALL METHOD CL_SALV_TABLE=>FACTORY
3455          IMPORTING
3456            R_SALV_TABLE = SS_GD-R_ALV
3457          CHANGING
3458            T_TABLE      = SS_GD-T_VARIANT.
3459
3460      CATCH CX_SALV_MSG . "#EC NO_HANDLER
3461
3462    ENDTRY.
3463  ********************************************************************
3464  DEFINE HIDE_COLUMN.
3465      R_COLUMN = R_COLUMNS->GET_COLUMN( &1 ).
3466      R_COLUMN->SET_VISIBLE( ' ' ).
```

```
3467  END-OF-DEFINITION.
3468  ************************************************************************
3469  ************************************************************************
3470  DEFINE REMOVE_COLUMN.
3471      R_COLUMN = R_COLUMNS->GET_COLUMN( &1 ).
3472      R_COLUMN->SET_TECHNICAL(  ABAP_TRUE ).
3473  END-OF-DEFINITION.
3474  ************************************************************************
3475
3476    TRY.
3477  *** Set Optimized
3478      R_COLUMNS = SS_GD-R_ALV->GET_COLUMNS( ).
3479      R_COLUMNS->SET_OPTIMIZE( ABAP_FALSE ).
3480
3481  ** exclude from the list technical fields
3482      REMOVE_COLUMN 'MANDT'.
3483      REMOVE_COLUMN 'REPORT'.
3484      REMOVE_COLUMN 'ENVIRONMNT'.
3485      REMOVE_COLUMN 'PROTECTED'.
3486  ** if number of variants is less than 10 hide user name
3487      IF ROWS < SS_C_VARLIST.
3488        HIDE_COLUMN 'ENAME'.
3489        HIDE_COLUMN 'EDAT'.
3490
3491      ELSE.
3492  ** there are more than 10 variants user name is displayed
3493  ** increase variant list popup size
3494        END_LINE   = 25.
3495      ENDIF.
3496  ** Hide not relevant columns (optionaly available to choose later)
3497      HIDE_COLUMN 'AENAME'.
3498      HIDE_COLUMN 'AEDAT'.
3499
3500  ************************************************************************
3501  DEFINE SET_TEXT.
3502  ** short text = technical name
3503      R_COLUMN = R_COLUMNS->GET_COLUMN( &1 ).
3504      R_COLUMN->SET_SHORT_TEXT( &1 ).
3505  ** medium text = text element
3506      TEXT_M = &2.
3507      R_COLUMN->SET_MEDIUM_TEXT( TEXT_M ).
3508  ** long text = medium text = text element
3509      TEXT_L = &2.
3510      R_COLUMN->SET_LONG_TEXT( TEXT_L ).
3511      DDIC_O_LENGTH = R_COLUMN->GET_DDIC_OUTPUTLEN( ).
3512  ** do always use medium text as field label
3513      R_COLUMN->SET_FIXED_HEADER_TEXT( 'M' ).
3514      OUTPUT_LENGTH = STRLEN( TEXT_L ).
3515  ** minimum output length determination
3516      IF OUTPUT_LENGTH < DDIC_O_LENGTH.
3517            OUTPUT_LENGTH = DDIC_O_LENGTH.
3518      ENDIF.
3519
3520      R_COLUMN->SET_OUTPUT_LENGTH( OUTPUT_LENGTH ).
3521
3522      IF ( &1 = 'ENAME' OR &1 = 'EDAT' ) AND ( ROWS > SS_C_VARLIST ).
3523  ** extend output width in case of extended display
3524        END_COLUMN = END_COLUMN + OUTPUT_LENGTH.
3525      ENDIF.
3526
3527  END-OF-DEFINITION.
```

```
3528  ************************************************************************
3529
3530  **  define missing text (data elements text isn't maintained)
3531      SET_TEXT 'VTEXT'  SSTXT_37. "'Description'.
3532      SET_TEXT 'ENAME'  SSTXT_33. "'Created by'.
3533      SET_TEXT 'AENAME' SSTXT_34. "'Changed by'.
3534      SET_TEXT 'EDAT'   SSTXT_35.  "'Created at'.
3535      SET_TEXT 'AEDAT'  SSTXT_36.  "'Changed at'.
3536
3537      CATCH CX_SALV_NOT_FOUND.   "#EC NO_HANDLER
3538
3539    ENDTRY.
3540  *** Set Zebra Pattern
3541    R_DS = SS_GD-R_ALV->GET_DISPLAY_SETTINGS( ).
3542    R_DS->SET_STRIPED_PATTERN( ABAP_TRUE ).
3543
3544    SS_GD-R_ALV->SET_SCREEN_STATUS(
3545        PFSTATUS      = 'SALV_POPUP'
3546        REPORT        = 'SAPLKESS'
3547        SET_FUNCTIONS = SS_GD-R_ALV->C_FUNCTIONS_DEFAULT ).
3548
3549  *** Display list of variants as popup
3550    SS_GD-R_ALV->SET_SCREEN_POPUP(
3551      START_COLUMN = 20
3552      END_COLUMN   = END_COLUMN
3553      START_LINE   = 5
3554      END_LINE     = END_LINE
3555                           ).
3556  **** Set Selection Mode is not needed
3557    R_SELECTIONS = SS_GD-R_ALV->GET_SELECTIONS( ).
3558
3559    R_EVENTS = SS_GD-R_ALV->GET_EVENT( ).
3560    CREATE OBJECT SS_GD-R_HANDLER_VARI.
3561
3562  *** register to the event USER_COMMAND
3563    SET HANDLER SS_GD-R_HANDLER_VARI->ADDED_FUNCTION FOR R_EVENTS.
3564    SET HANDLER SS_GD-R_HANDLER_VARI->DOUBLE_CLICK FOR R_EVENTS.
3565
3566  *** display list
3567    SS_GD-R_ALV->DISPLAY( ).
3568
3569  *** in case that double click was performed reference isn't valid
3570  *** and any further must not be done as it will lead into loading
3571  *** of an random variant (usually the last one in t_rows)
3572    CHECK SS_GD-R_ALV IS BOUND.
3573  *** determine selected rows
3574    T_ROWS = R_SELECTIONS->GET_SELECTED_ROWS( ).
3575    CLEAR S_VARIANT.
3576
3577  *** release not necessary data
3578    FREE SS_GD-R_HANDLER_VARI.
3579    FREE SS_GD-R_ALV.
3580  *** check, whether some variant was selected
3581    IF T_ROWS IS NOT INITIAL.
3582
3583      READ TABLE T_ROWS INTO TABIX INDEX 1.
3584
3585      READ TABLE SS_GD-T_VARIANT INTO S_VARIANT INDEX TABIX.
3586      IF SY-SUBRC <> 0.
3587        REFRESH SS_GD-T_VARIANT.
3588        RETURN.
```

```
3589      ENDIF.
3590
3591    ENDIF.
3592
3593    CHECK S_VARIANT-VARIANT IS NOT INITIAL.
3594
3595  *** new variant selected, determine content of GR_SS_INT from variant
3596  *** parameter and sel-option values.
3597    PERFORM SS_SCREEN_UPDATE_FROM_VARIANT
3598      USING S_VARIANT-VARIANT.
3599
3600  ENDFORM.                    " SS_VARIANT_GET_KESS
3601
3602  *&---------------------------------------------------------------------*
3603  *&      Form  SS_VARIANT_GET_STANDARD
3604  *&---------------------------------------------------------------------*
3605  *&      Get variant function similar to RS_VARIANT_FETCH function
3606  *&---------------------------------------------------------------------*
3607  FORM SS_VARIANT_GET_STANDARD.
3608  *** Get variant
3609    DATA:
3610      S_VARIANT LIKE RSVARTXT,
3611      T_VALUE   TYPE TABLE OF RSPARAMS,
3612      S_VALUE   LIKE RSPARAMS.
3613
3614  *** Display variant list and get variant
3615        CALL FUNCTION 'RS_VARIANT_CATALOG'
3616             EXPORTING
3617                  REPORT              = SY-CPROG
3618                  NEW_TITLE           = ''
3619                  DYNNR               = SY-DYNNR
3620                  INTERNAL_CALL       = ABAP_FALSE
3621                  POP_UP              = 'X'
3622             IMPORTING
3623                  SEL_VARIANT         = S_VARIANT-VARIANT
3624             EXCEPTIONS
3625                  NO_REPORT           = 01
3626                  REPORT_NOT_EXISTENT = 02
3627                  REPORT_NOT_SUPPLIED = 03
3628                  NO_VARIANTS         = 04
3629                  VARIANT_NOT_EXISTENT = 05
3630                  NO_VARIANT_SELECTED  = 06
3631                  OTHERS              = 07.
3632      IF SY-SUBRC EQ 4.
3633        MESSAGE I030(DB) WITH SY-CPROG.
3634        EXIT.
3635      ELSEIF SY-SUBRC EQ 5.
3636        MESSAGE I612(DB) WITH S_VARIANT-VARIANT SY-CPROG.
3637        EXIT.
3638      ELSEIF SY-SUBRC EQ 6.
3639        MESSAGE S610(DB) RAISING S_VARIANT-VARIANT.
3640        EXIT.
3641      ENDIF.
3642  *** any variant chosen?
3643    CHECK S_VARIANT-VARIANT IS NOT INITIAL.
3644
3645  *** new variant selected, determine content of GR_SS_INT from variant
3646  *** parameter and sel-option values.
3647    PERFORM SS_SCREEN_UPDATE_FROM_VARIANT
3648      USING S_VARIANT-VARIANT.
3649
```

```
3650  ENDFORM.                    " SS_VARIANT_GET_STANDARD
3651
3652  *&---------------------------------------------------------------------*
3653  *&      Form  SS_EVENT_ON_VALUE_REQUEST
3654  *&---------------------------------------------------------------------*
3655  *&      Run KESS or application specific search help
3656  *&---------------------------------------------------------------------*
3657  FORM SS_EVENT_ON_VALUE_REQUEST
3658       USING
3659         I_CHARACTERISTIC TYPE RSSCR_DBFI.
3660
3661    IF SS_GR_EXT->GET_KESS_SEARCH_HELP( ) = ABAP_TRUE.
3662      SS_GR_EXT->SEARCH_HELP( EXPORTING I_CHARACTERISTIC = I_CHARACTERISTI
      C ).
3663    ELSE.
3664      SS_GR_EXT->RAISE( I_EVENT          = SS_GR_EXT->EVENT_ON_VALUE_REQUE
      ST
3665                        I_CHARACTERISTIC = I_CHARACTERISTIC ).
3666    ENDIF.
3667
3668    <FS> = SS_GR_EXT->GET_SEARCH_HELP_VALUE( ).
3669
3670    SS_GR_EXT->SET_SEARCH_HELP_VALUE( '' ).
3671  ENDFORM.
3672  FORM SS_SEL_TO_SO
3673    USING
3674      I_TABNAME   TYPE TABNAME
3675      I_FIELDNAME TYPE RSSCR_DBFI
3676    CHANGING
3677      C_SO        TYPE ANY TABLE.
3678
3679    DATA: LS_TRANGE TYPE RSDS_RANGE.
3680    DATA: LT_FRANGE TYPE RSDS_FRANGE_T.
3681    DATA: LS_FRANGE LIKE LINE OF LT_FRANGE.
3682
3683    READ TABLE SS_GR_INT->T_TRANGE INTO LS_TRANGE WITH KEY TABLENAME = I_T
      ABNAME.
3684
3685    LT_FRANGE[] = LS_TRANGE-FRANGE_T[].
3686
3687    READ TABLE LT_FRANGE INTO LS_FRANGE WITH KEY FIELDNAME = I_FIELDNAME.
3688
3689    IF SY-SUBRC = 0.
3690      C_SO[] = LS_FRANGE-SELOPT_T[].
3691    ENDIF.
3692  ENDFORM.
3693
3694  *&---------------------------------------------------------------------*
3695  *&      Form  SS_GET_SELOPT_NAME
3696  *&---------------------------------------------------------------------*
3697  *&      Get name of select-option
3698  *&---------------------------------------------------------------------*
3699  FORM SS_GET_SELOPT_NAME
3700      USING
3701        I_TABNAME   TYPE TABNAME
3702        I_FIELDNAME TYPE FIELDNAME
3703      CHANGING
3704        C_SELOPT_NAME TYPE FIELDNAME.
3705
3706    DATA:
3707      I  TYPE I,
```

```
3708      N2 TYPE NUMC2.
3709
3710    CLEAR C_SELOPT_NAME.
3711
3712  *** get number of select-option
3713    DATA(KEY) = |{ I_TABNAME }-{ I_FIELDNAME }|.
3714    LOOP AT T_SS_SF ASSIGNING FIELD-SYMBOL(<S_SF>) WHERE HIGH CS KEY.
3715      EXIT.
3716    ENDLOOP.
3717
3718    CHECK <S_SF> IS ASSIGNED.
3719
3720  ** transform number into name
3721    TRY.
3722      I = <S_SF>-LOW.
3723      CATCH CX_ROOT.
3724    ENDTRY.
3725
3726    IF I > 100.
3727      N2 = I - 100.
3728      C_SELOPT_NAME = |SO_V{ N2 }|.
3729    ELSEIF I > 0.
3730      N2 = I.
3731      C_SELOPT_NAME = |SO_C{ N2 }|.
3732    ENDIF.
3733
3734  ENDFORM.
3735
3736  FORM SS_AUTH_CHECK_GLOBAL_SCREEN
3737     USING    ID_ACTVT  TYPE XUVAL
3738              ID_PROG   TYPE PROGRAMM
3739              ID_TAB    TYPE TABNAME
3740     CHANGING CD_RETURN TYPE SY-SUBRC.
3741
3742     DATA: LD_VALUE_1 TYPE XUVAL.
3743     DATA: LD_VALUE_2 TYPE XUVAL.
3744     DATA: LD_VALUE_3 TYPE XUVAL.
3745
3746     LD_VALUE_1 = ID_ACTVT.
3747     LD_VALUE_2 = ID_PROG.
3748     LD_VALUE_3 = ID_TAB.
3749
3750     TRY.
3751       CALL METHOD
3752         ('CL_SACF')=>('AUTH_CHECK_SPEC')
3753           EXPORTING
3754             ID_NAME   = 'COPA_KESS_SCR'
3755             ID_SUSO   = 'K_KESS_SCR'
3756             ID_FLD1   = 'ACTVT'
3757             ID_VAL1   = LD_VALUE_1
3758             ID_FLD2   = 'PROGRAM'
3759             ID_VAL2   = LD_VALUE_2
3760             ID_FLD3   = 'TABLE'
3761             ID_VAL3   = LD_VALUE_3
3762           RECEIVING
3763             ED_RETURN = CD_RETURN.
3764       CATCH CX_SY_DYN_CALL_ERROR.
3765  * Return success if the framework does not exist
3766         CD_RETURN = 0.
3767     ENDTRY.
3768  ENDFORM.
```

```
3769
3770  FORM SS_SYNC_SF.
3771    DATA: S_SS_SF  LIKE LINE OF T_SS_SF.
3772    DATA: EXISTS   TYPE SAP_BOOL.
3773    DATA: S_SEQ    LIKE LINE OF SS_GR_INT->T_SS_SF.
3774    REFRESH SS_GR_INT->T_SS_SF.
3775    LOOP AT T_SS_SF INTO S_SS_SF.
3776  ** check whether field (still) exists in the table/structure def
3777      PERFORM SS_CHECK_FIELD_EXISTS
3778        USING
3779          S_SS_SF-HIGH
3780        CHANGING
3781          EXISTS.
3782
3783      IF EXISTS = ABAP_TRUE.
3784
3785        S_SEQ-TFNAME   = S_SS_SF-HIGH.
3786        S_SEQ-SEQUENCE = S_SS_SF-LOW.
3787
3788        APPEND S_SEQ TO SS_GR_INT->T_SS_SF.
3789
3790      ENDIF.
3791    ENDLOOP.
3792
3793    SORT SS_GR_INT->T_SS_SF BY SEQUENCE.
3794    SORT T_SS_SF BY LOW.
3795   ENDFORM.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           RKESS_GENENERIC_SCREEN
3  *&---------------------------------------------------------------------*
4
5  ************************************************************************
6  ***   GlOBAL DEFINITION              ***********************************
7  ************************************************************************
8  INCLUDE RKESS_TOP.
9
10 ************************************************************************
11 ***   SELECTION SCREEN DEFINITION   ***********************************
12 ************************************************************************
13
14 ************************************************************************
15 *** Application Bar Buttons  ********************************************
16 SELECTION-SCREEN: FUNCTION KEY 1.
17
18 ************************************************************************
19 ***Selection Screen Parameters and Select-Options  *********************
20
21 ************************************************************************
22 *** Advanced (expert) settings  ***************************************
23
24 SELECTION-SCREEN BEGIN OF BLOCK EXPERT WITH FRAME TITLE SSTXT_21.
25
26 SELECTION-SCREEN BEGIN OF LINE.
27   SELECTION-SCREEN COMMENT  1(40)
28     SSTXT_22  FOR FIELD EXPERT MODIF ID SYS.
29   SELECTION-SCREEN POSITION 41.
30 ** Expert Mode Switch
31   PARAMETERS: EXPERT TYPE FLAG USER-COMMAND CBOXEXPT MODIF ID SYS.
32 SELECTION-SCREEN END OF LINE.
33
34 SELECTION-SCREEN BEGIN OF LINE.
35   SELECTION-SCREEN COMMENT  1(40)
36     SSTXT_23  FOR FIELD PRGNAME MODIF ID SYS.
37   SELECTION-SCREEN POSITION 41.
38 ** Calling program
39   PARAMETERS: PRGNAME   LIKE SYST-CPROG  MODIF ID SYD.
40 SELECTION-SCREEN END OF LINE.
41
42
43 SELECTION-SCREEN BEGIN OF LINE.
44   SELECTION-SCREEN COMMENT  1(40)
45     SSTXT_25  FOR FIELD NOSCRDEF MODIF ID SYS.
46 ** NOSCRDEF = ABAP_TRUE => no change of sel. screen definition is possib
   le
47 ** Definition subscreen isn't accessible
48   SELECTION-SCREEN POSITION 41.
49   PARAMETERS: NOSCRDEF TYPE FLAG DEFAULT ABAP_FALSE USER-COMMAND CBOXNOD
   F
50     MODIF ID SYS.
51 ** selection screen can't changed / defined
52   SELECTION-SCREEN COMMENT  47(40)
53     SSTXT_11  FOR FIELD NOSCRNAM MODIF ID SYS.
54 ** Screen definition can't be saved
55   PARAMETERS: NOSCRNAM TYPE FLAG DEFAULT ABAP_FALSE USER-COMMAND CBOXNOS
   D
56     MODIF ID SYS.
57 SELECTION-SCREEN END OF LINE.
58
```

```
 59  SELECTION-SCREEN BEGIN OF LINE.
 60    SELECTION-SCREEN COMMENT  1(40)
 61      SSTXT_26  FOR FIELD SHOW_TAB MODIF ID SYS.
 62    SELECTION-SCREEN POSITION 41.
 63  ** Empty value means that list of table name isn't displayed
 64    PARAMETERS: SHOW_TAB   TYPE FLAG DEFAULT ABAP_FALSE USER-COMMAND CBOXS
    TAB
 65      VISIBLE LENGTH 2 MODIF ID SYS.
 66    SELECTION-SCREEN COMMENT  47(40)
 67      SSTXT_27  FOR FIELD CHNG_TAB MODIF ID SYT.
 68  ** Table/structure name can be changed
 69    PARAMETERS: CHNG_TAB   TYPE FLAG DEFAULT ABAP_FALSE USER-COMMAND CBOXC
    TAB
 70      MODIF ID SYT.
 71  SELECTION-SCREEN END OF LINE.
 72
 73  SELECTION-SCREEN SKIP.
 74
 75  SELECTION-SCREEN BEGIN OF LINE.
 76    SELECTION-SCREEN COMMENT  1(40)
 77      SSTXT_28  FOR FIELD T_SS_SF MODIF ID SYD.
 78    SELECTION-SCREEN POSITION 38.
 79  ** List of fields to be used for entering of selection criteria
 80    SELECT-OPTIONS T_SS_SF FOR RSSCR-DBFIELD NO INTERVALS MODIF ID SYD.
 81  SELECTION-SCREEN END OF LINE.
 82
 83  SELECTION-SCREEN BEGIN OF LINE.
 84    SELECTION-SCREEN COMMENT  1(40)
 85      SSTXT_29  FOR FIELD T_SS_EF MODIF ID SYD.
 86  ** Fields, which can't be used for entering of selection (for example cl
    ient)
 87  ** e.g. excluded from selection criteria
 88    SELECTION-SCREEN POSITION 38.
 89    SELECT-OPTIONS T_SS_EF FOR RSSCR-DBFIELD NO INTERVALS MODIF ID SYD.
 90  SELECTION-SCREEN END OF LINE.
 91
 92  SELECTION-SCREEN BEGIN OF LINE.
 93    SELECTION-SCREEN COMMENT  1(40)
 94      SSTXT_30  FOR FIELD T_SS_TAB MODIF ID SYD.
 95  ** Tables/structures/view used for SO definition
 96    SELECTION-SCREEN POSITION 38.
 97    SELECT-OPTIONS
 98      T_SS_TAB     FOR TKESS_SCR-TABNAME NO INTERVALS MODIF ID SYD.
 99  SELECTION-SCREEN END OF LINE.
100
101
102  SELECTION-SCREEN END OF BLOCK EXPERT.
103
104  ************************************************************************
105  *** Selection Screen Definition ***************************************
106
107  SELECTION-SCREEN BEGIN OF BLOCK SEL WITH FRAME TITLE SSTXT_01.
108  ** Table name .
109  SELECTION-SCREEN BEGIN OF LINE.
110
111    SELECTION-SCREEN PUSHBUTTON  1(40) PUSHDEFI USER-COMMAND PUSHDEFI MODI
    F ID BDF
112      VISIBLE LENGTH 3.
113    SELECTION-SCREEN COMMENT  5(40)  SSTXT_18 MODIF ID BDF.
114
115    SELECTION-SCREEN PUSHBUTTON 75(40)
```

```
116       PUSHTNAM USER-COMMAND PUSHTNAM MODIF ID BDF VISIBLE LENGTH 3.
117
118     PARAMETERS  TECHNAME TYPE FLAG  MODIF ID BDF   NO-DISPLAY.
119
120   SELECTION-SCREEN END OF LINE.
121
122   SELECTION-SCREEN BEGIN OF BLOCK SELDEF WITH FRAME TITLE SSTXT_31.
123
124   * Table Name
125   SELECTION-SCREEN BEGIN OF LINE.
126     SELECTION-SCREEN COMMENT  1(27)
127       SSTXT_04  FOR FIELD KESSTABL MODIF ID TBS.
128     SELECTION-SCREEN POSITION 31.
129   ** Table Name or Table Group Name or Generic Tables ( value '$' )
130     PARAMETERS:
131       KESSTABL LIKE TKESS_SCR-TABNAME VISIBLE LENGTH 28 MODIF ID TBS.
132   ** Button Change Table Name
133     SELECTION-SCREEN PUSHBUTTON  61(40) PUSHTABL USER-COMMAND PUSHTABL MOD
      IF ID TBC
134       VISIBLE LENGTH 7.
135   ** Table Description
136     SELECTION-SCREEN COMMENT  69(40)
137       TAB_DESC  FOR FIELD KESSTABL MODIF ID TBS.
138   SELECTION-SCREEN END OF LINE.
139
140   SELECTION-SCREEN BEGIN OF LINE.
141
142     SELECTION-SCREEN COMMENT  1(29) SSTXT_19 FOR FIELD SCRNAME MODIF ID DE
      G.
143
144   ** Popup Choose Screen Fields
145     SELECTION-SCREEN PUSHBUTTON 31(50) PUSHSLCR
146       USER-COMMAND PUSHSLCR MODIF ID DEG
147       VISIBLE LENGTH 28.
148
149   ** Button Save Screen Definition
150     SELECTION-SCREEN PUSHBUTTON 61(40)
151       PUSHSAVE USER-COMMAND PUSHSAVE MODIF ID DEF VISIBLE LENGTH 7.
152   ** Button Delete Selection Screens
153     SELECTION-SCREEN PUSHBUTTON 69(40)
154       PUSHMANA USER-COMMAND PUSHMANA MODIF ID DEF VISIBLE LENGTH 7.
155
156   SELECTION-SCREEN END OF LINE.
157
158   SELECTION-SCREEN BEGIN OF LINE.
159     SELECTION-SCREEN COMMENT  1(27)
160       SSTXT_14  FOR FIELD SCRNAME MODIF ID DEF.
161     SELECTION-SCREEN POSITION 31.
162   ** Screen Name
163     PARAMETERS:
164       SCRNAME LIKE TKESS_SCR-SCRNAME AS LISTBOX
165         VISIBLE LENGTH 28
166         USER-COMMAND SCR
167         MODIF ID DEF.
168
169     SELECTION-SCREEN COMMENT  61(40)
170       SCRDESCR FOR FIELD SCRNAME MODIF ID DEF.
171   SELECTION-SCREEN END OF LINE.
172
173   SELECTION-SCREEN END OF BLOCK SELDEF.
174
```

```
175 **********************************************************************
176 *** Dynamic Selection Criteria       ********************************
177 *** Characteristics and Key Figures  ********************************
178
179 *** 'Characteristics' select options
180 SELECTION-SCREEN  BEGIN OF BLOCK SS_FIELDS  WITH FRAME TITLE SSTXT_02.
181   INCLUDE RKESS_CHARACTERISTICS.
182 SELECTION-SCREEN END OF BLOCK SS_FIELDS.
183
184 ***** 'Key figures' select options
185 SELECTION-SCREEN  BEGIN OF BLOCK SS_VFIELDS WITH FRAME TITLE SSTXT_03.
186   INCLUDE RKESS_KEY_FIGURES.
187 SELECTION-SCREEN END OF BLOCK SS_VFIELDS.
188
189 SELECTION-SCREEN END OF BLOCK SEL.
190
191 **********************************************************************
192 ***   ABAP EVENTS HANDLING *****************************************
193
194 INCLUDE RKESS_EVENTS.
195
196 **********************************************************************
197 ***   FORMS.            ********************************************
198
199 INCLUDE RKESS_FORMS.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           RKESS_KEY_FIGURES.
3  *&---------------------------------------------------------------------*
4
5  SELECTION-SCREEN BEGIN OF LINE.
6    SELECTION-SCREEN COMMENT 1(25) TXT_V01 FOR FIELD SO_V01 MODIF ID SSC.
7    SELECTION-SCREEN POSITION 28.
8    SELECT-OPTIONS SO_V01     FOR (PAR_V01) MODIF ID SSC.
9    SELECTION-SCREEN POSITION 75.
10   SELECT-OPTIONS SO_U01     FOR (PAR_U01) MODIF ID SSC NO INTERVALS.
11 SELECTION-SCREEN END OF LINE.
12
13 SELECTION-SCREEN BEGIN OF LINE.
14   SELECTION-SCREEN COMMENT 1(25) TXT_V02 FOR FIELD SO_V02 MODIF ID SSC.
15   SELECTION-SCREEN POSITION 28.
16   SELECT-OPTIONS SO_V02     FOR (PAR_V02) MODIF ID SSC.
17   SELECTION-SCREEN POSITION 75.
18   SELECT-OPTIONS SO_U02     FOR (PAR_U02) MODIF ID SSC NO INTERVALS.
19 SELECTION-SCREEN END OF LINE.
20
21 SELECTION-SCREEN BEGIN OF LINE.
22   SELECTION-SCREEN COMMENT 1(25) TXT_V03 FOR FIELD SO_V03 MODIF ID SSC.
23   SELECTION-SCREEN POSITION 28.
24   SELECT-OPTIONS SO_V03     FOR (PAR_V03) MODIF ID SSC.
25   SELECTION-SCREEN POSITION 75.
26   SELECT-OPTIONS SO_U03     FOR (PAR_U03) MODIF ID SSC NO INTERVALS.
27 SELECTION-SCREEN END OF LINE.
28
29 SELECTION-SCREEN BEGIN OF LINE.
30   SELECTION-SCREEN COMMENT 1(25) TXT_V04 FOR FIELD SO_V04 MODIF ID SSC.
31   SELECTION-SCREEN POSITION 28.
32   SELECT-OPTIONS SO_V04     FOR (PAR_V04) MODIF ID SSC.
33   SELECTION-SCREEN POSITION 75.
34   SELECT-OPTIONS SO_U04     FOR (PAR_U04) MODIF ID SSC NO INTERVALS.
35 SELECTION-SCREEN END OF LINE.
36
37 SELECTION-SCREEN BEGIN OF LINE.
38   SELECTION-SCREEN COMMENT 1(25) TXT_V05 FOR FIELD SO_V05 MODIF ID SSC.
39   SELECTION-SCREEN POSITION 28.
40   SELECT-OPTIONS SO_V05     FOR (PAR_V05) MODIF ID SSC.
41   SELECTION-SCREEN POSITION 75.
42   SELECT-OPTIONS SO_U05     FOR (PAR_U05) MODIF ID SSC NO INTERVALS.
43 SELECTION-SCREEN END OF LINE.
44
45 SELECTION-SCREEN BEGIN OF LINE.
46   SELECTION-SCREEN COMMENT 1(25) TXT_V06 FOR FIELD SO_V06 MODIF ID SSC.
47   SELECTION-SCREEN POSITION 28.
48   SELECT-OPTIONS SO_V06     FOR (PAR_V06) MODIF ID SSC.
49   SELECTION-SCREEN POSITION 75.
50   SELECT-OPTIONS SO_U06     FOR (PAR_U06) MODIF ID SSC NO INTERVALS.
51 SELECTION-SCREEN END OF LINE.
52
53 SELECTION-SCREEN BEGIN OF LINE.
54   SELECTION-SCREEN COMMENT 1(25) TXT_V07 FOR FIELD SO_V07 MODIF ID SSC.
55   SELECTION-SCREEN POSITION 28.
56   SELECT-OPTIONS SO_V07     FOR (PAR_V07) MODIF ID SSC.
57   SELECTION-SCREEN POSITION 75.
58   SELECT-OPTIONS SO_U07     FOR (PAR_U07) MODIF ID SSC NO INTERVALS.
59 SELECTION-SCREEN END OF LINE.
60
61 SELECTION-SCREEN BEGIN OF LINE.
```

```
  SELECTION-SCREEN COMMENT 1(25) TXT_V08 FOR FIELD SO_V08 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V08     FOR (PAR_V08) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U08     FOR (PAR_U08) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V09 FOR FIELD SO_V09 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V09     FOR (PAR_V09) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U09     FOR (PAR_U09) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V10 FOR FIELD SO_V10 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V10     FOR (PAR_V10) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U10     FOR (PAR_U10) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V11 FOR FIELD SO_V11 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V11     FOR (PAR_V11) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U11     FOR (PAR_U11) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V12 FOR FIELD SO_V12 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V12     FOR (PAR_V12) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U12     FOR (PAR_U12) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V13 FOR FIELD SO_V13 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V13     FOR (PAR_V13) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U13     FOR (PAR_U13) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V14 FOR FIELD SO_V14 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V14     FOR (PAR_V14) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U14     FOR (PAR_U14) MODIF ID SSC NO INTERVALS.
SELECTION-SCREEN END OF LINE.

SELECTION-SCREEN BEGIN OF LINE.
  SELECTION-SCREEN COMMENT 1(25) TXT_V15 FOR FIELD SO_V15 MODIF ID SSC.
  SELECTION-SCREEN POSITION 28.
  SELECT-OPTIONS SO_V15     FOR (PAR_V15) MODIF ID SSC.
  SELECTION-SCREEN POSITION 75.
  SELECT-OPTIONS SO_U15     FOR (PAR_U15) MODIF ID SSC NO INTERVALS.
```

```
123  SELECTION-SCREEN END OF LINE.
124
125  SELECTION-SCREEN BEGIN OF LINE.
126    SELECTION-SCREEN COMMENT 1(25) TXT_V16 FOR FIELD SO_V16 MODIF ID SSC.
127    SELECTION-SCREEN POSITION 28.
128    SELECT-OPTIONS SO_V16     FOR (PAR_V16) MODIF ID SSC.
129    SELECTION-SCREEN POSITION 75.
130    SELECT-OPTIONS SO_U16     FOR (PAR_U16) MODIF ID SSC NO INTERVALS.
131  SELECTION-SCREEN END OF LINE.
132
133  SELECTION-SCREEN BEGIN OF LINE.
134    SELECTION-SCREEN COMMENT 1(25) TXT_V17 FOR FIELD SO_V17 MODIF ID SSC.
135    SELECTION-SCREEN POSITION 28.
136    SELECT-OPTIONS SO_V17     FOR (PAR_V17) MODIF ID SSC.
137    SELECTION-SCREEN POSITION 75.
138    SELECT-OPTIONS SO_U17     FOR (PAR_U17) MODIF ID SSC NO INTERVALS.
139  SELECTION-SCREEN END OF LINE.
140
141  SELECTION-SCREEN BEGIN OF LINE.
142    SELECTION-SCREEN COMMENT 1(25) TXT_V18 FOR FIELD SO_V18 MODIF ID SSC.
143    SELECTION-SCREEN POSITION 28.
144    SELECT-OPTIONS SO_V18     FOR (PAR_V18) MODIF ID SSC.
145    SELECTION-SCREEN POSITION 75.
146    SELECT-OPTIONS SO_U18     FOR (PAR_U18) MODIF ID SSC NO INTERVALS.
147  SELECTION-SCREEN END OF LINE.
148
149  SELECTION-SCREEN BEGIN OF LINE.
150    SELECTION-SCREEN COMMENT 1(25) TXT_V19 FOR FIELD SO_V19 MODIF ID SSC.
151    SELECTION-SCREEN POSITION 28.
152    SELECT-OPTIONS SO_V19     FOR (PAR_V19) MODIF ID SSC.
153    SELECTION-SCREEN POSITION 75.
154    SELECT-OPTIONS SO_U19     FOR (PAR_U19) MODIF ID SSC NO INTERVALS.
155  SELECTION-SCREEN END OF LINE.
156
157  SELECTION-SCREEN BEGIN OF LINE.
158    SELECTION-SCREEN COMMENT 1(25) TXT_V20 FOR FIELD SO_V20 MODIF ID SSC.
159    SELECTION-SCREEN POSITION 28.
160    SELECT-OPTIONS SO_V20     FOR (PAR_V20) MODIF ID SSC.
161    SELECTION-SCREEN POSITION 75.
162    SELECT-OPTIONS SO_U20     FOR (PAR_U20) MODIF ID SSC NO INTERVALS.
163  SELECTION-SCREEN END OF LINE.
164
165  SELECTION-SCREEN BEGIN OF LINE.
166    SELECTION-SCREEN COMMENT 1(25) TXT_V21 FOR FIELD SO_V21 MODIF ID SSC.
167    SELECTION-SCREEN POSITION 28.
168    SELECT-OPTIONS SO_V21     FOR (PAR_V21) MODIF ID SSC.
169    SELECTION-SCREEN POSITION 75.
170    SELECT-OPTIONS SO_U21     FOR (PAR_U21) MODIF ID SSC NO INTERVALS.
171  SELECTION-SCREEN END OF LINE.
172
173  SELECTION-SCREEN BEGIN OF LINE.
174    SELECTION-SCREEN COMMENT 1(25) TXT_V22 FOR FIELD SO_V22 MODIF ID SSC.
175    SELECTION-SCREEN POSITION 28.
176    SELECT-OPTIONS SO_V22     FOR (PAR_V22) MODIF ID SSC.
177    SELECTION-SCREEN POSITION 75.
178    SELECT-OPTIONS SO_U22     FOR (PAR_U22) MODIF ID SSC NO INTERVALS.
179  SELECTION-SCREEN END OF LINE.
180
181  SELECTION-SCREEN BEGIN OF LINE.
182    SELECTION-SCREEN COMMENT 1(25) TXT_V23 FOR FIELD SO_V23 MODIF ID SSC.
183    SELECTION-SCREEN POSITION 28.
```

```
184    SELECT-OPTIONS SO_V23     FOR (PAR_V23) MODIF ID SSC.
185    SELECTION-SCREEN POSITION 75.
186    SELECT-OPTIONS SO_U23     FOR (PAR_U23) MODIF ID SSC NO INTERVALS.
187  SELECTION-SCREEN END OF LINE.
188
189  SELECTION-SCREEN BEGIN OF LINE.
190    SELECTION-SCREEN COMMENT 1(25) TXT_V24 FOR FIELD SO_V24 MODIF ID SSC.
191    SELECTION-SCREEN POSITION 28.
192    SELECT-OPTIONS SO_V24     FOR (PAR_V24) MODIF ID SSC.
193    SELECTION-SCREEN POSITION 75.
194    SELECT-OPTIONS SO_U24     FOR (PAR_U24) MODIF ID SSC NO INTERVALS.
195  SELECTION-SCREEN END OF LINE.
196
197  SELECTION-SCREEN BEGIN OF LINE.
198    SELECTION-SCREEN COMMENT 1(25) TXT_V25 FOR FIELD SO_V25 MODIF ID SSC.
199    SELECTION-SCREEN POSITION 28.
200    SELECT-OPTIONS SO_V25     FOR (PAR_V25) MODIF ID SSC.
201    SELECTION-SCREEN POSITION 75.
202    SELECT-OPTIONS SO_U25     FOR (PAR_U25) MODIF ID SSC NO INTERVALS.
203  SELECTION-SCREEN END OF LINE.
204
205  ***Definition of dynamic SELECT-OPTIONS, by default 'not defined'
206  SELECTION-SCREEN BEGIN OF LINE.
207  PARAMETERS:
208      PAR_C01    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
209      PAR_V01    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
210      PAR_U01    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
211  SELECTION-SCREEN END OF LINE.
212
213  SELECTION-SCREEN BEGIN OF LINE.
214  PARAMETERS:
215      PAR_C02    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
216      PAR_V02    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
217      PAR_U02    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
218  SELECTION-SCREEN END OF LINE.
219
220  SELECTION-SCREEN BEGIN OF LINE.
221  PARAMETERS:
222      PAR_C03    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
223      PAR_V03    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
224      PAR_U03    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
225  SELECTION-SCREEN END OF LINE.
226
227  SELECTION-SCREEN BEGIN OF LINE.
228  PARAMETERS:
229      PAR_C04    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
230      PAR_V04    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
231      PAR_U04    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
232  SELECTION-SCREEN END OF LINE.
233
234  SELECTION-SCREEN BEGIN OF LINE.
235  PARAMETERS:
236      PAR_C05    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
237      PAR_V05    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
238      PAR_U05    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
239  SELECTION-SCREEN END OF LINE.
240
241  SELECTION-SCREEN BEGIN OF LINE.
242  PARAMETERS:
243      PAR_C06    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
244      PAR_V06    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
```

```
245      PAR_U06    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
246  SELECTION-SCREEN END OF LINE.
247
248  SELECTION-SCREEN BEGIN OF LINE.
249  PARAMETERS:
250      PAR_C07    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
251      PAR_V07    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
252      PAR_U07    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
253  SELECTION-SCREEN END OF LINE.
254
255  SELECTION-SCREEN BEGIN OF LINE.
256  PARAMETERS:
257      PAR_C08    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
258      PAR_V08    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
259      PAR_U08    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
260  SELECTION-SCREEN END OF LINE.
261
262  SELECTION-SCREEN BEGIN OF LINE.
263  PARAMETERS:
264      PAR_C09    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
265      PAR_V09    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
266      PAR_U09    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
267  SELECTION-SCREEN END OF LINE.
268
269  SELECTION-SCREEN BEGIN OF LINE.
270  PARAMETERS:
271      PAR_C10    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
272      PAR_V10    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
273      PAR_U10    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
274  SELECTION-SCREEN END OF LINE.
275
276  SELECTION-SCREEN BEGIN OF LINE.
277  PARAMETERS:
278      PAR_C11    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
279      PAR_V11    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
280      PAR_U11    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
281  SELECTION-SCREEN END OF LINE.
282
283  SELECTION-SCREEN BEGIN OF LINE.
284  PARAMETERS:
285      PAR_C12    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
286      PAR_V12    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
287      PAR_U12    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
288  SELECTION-SCREEN END OF LINE.
289
290  SELECTION-SCREEN BEGIN OF LINE.
291  PARAMETERS:
292      PAR_C13    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
293      PAR_V13    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
294      PAR_U13    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
295  SELECTION-SCREEN END OF LINE.
296
297  SELECTION-SCREEN BEGIN OF LINE.
298  PARAMETERS:
299      PAR_C14    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
300      PAR_V14    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
301      PAR_U14    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
302  SELECTION-SCREEN END OF LINE.
303
304  SELECTION-SCREEN BEGIN OF LINE.
305  PARAMETERS:
```

```
306       PAR_C15    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
307       PAR_V15    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
308       PAR_U15    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
309   SELECTION-SCREEN END OF LINE.
310
311   SELECTION-SCREEN BEGIN OF LINE.
312   PARAMETERS:
313       PAR_C16    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
314       PAR_V16    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
315       PAR_U16    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
316   SELECTION-SCREEN END OF LINE.
317
318   SELECTION-SCREEN BEGIN OF LINE.
319   PARAMETERS:
320       PAR_C17    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
321       PAR_V17    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
322       PAR_U17    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
323   SELECTION-SCREEN END OF LINE.
324
325   SELECTION-SCREEN BEGIN OF LINE.
326   PARAMETERS:
327       PAR_C18    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
328       PAR_V18    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
329       PAR_U18    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
330   SELECTION-SCREEN END OF LINE.
331
332   SELECTION-SCREEN BEGIN OF LINE.
333   PARAMETERS:
334       PAR_C19    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
335       PAR_V19    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
336       PAR_U19    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
337   SELECTION-SCREEN END OF LINE.
338
339   SELECTION-SCREEN BEGIN OF LINE.
340   PARAMETERS:
341       PAR_C20    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
342       PAR_V20    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
343       PAR_U20    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
344   SELECTION-SCREEN END OF LINE.
345
346   SELECTION-SCREEN BEGIN OF LINE.
347   PARAMETERS:
348       PAR_C21    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
349       PAR_V21    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
350       PAR_U21    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
351   SELECTION-SCREEN END OF LINE.
352
353   SELECTION-SCREEN BEGIN OF LINE.
354   PARAMETERS:
355       PAR_C22    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
356       PAR_V22    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
357       PAR_U22    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
358   SELECTION-SCREEN END OF LINE.
359
360   SELECTION-SCREEN BEGIN OF LINE.
361   PARAMETERS:
362       PAR_C23    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
363       PAR_V23    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
364       PAR_U23    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
365   SELECTION-SCREEN END OF LINE.
366
```

```
367  SELECTION-SCREEN BEGIN OF LINE.
368  PARAMETERS:
369      PAR_C24    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
370      PAR_V24    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
371      PAR_U24    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
372  SELECTION-SCREEN END OF LINE.
373
374  SELECTION-SCREEN BEGIN OF LINE.
375  PARAMETERS:
376      PAR_C25    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
377      PAR_V25    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY,
378      PAR_U25    TYPE RSSCR_DBFI MODIF ID SSC NO-DISPLAY.
379  SELECTION-SCREEN END OF LINE.
```

```
1  *&---------------------------------------------------------------------*
2  *&  Include           RKESS_TOP
3  *&---------------------------------------------------------------------*
4
5  ************************************************************************
6  ***   GlOBAL DEFINITION              ***********************************
7  ************************************************************************
8  TABLES:     SSCRFIELDS, TKESS_SCR_FIELD, RSSCR, DD02V, RSRD1, TKESS_SCR.
9
10 TYPE-POOLS: VRM, ABAP, KESS, SSCR.
11
12 INCLUDE:    <ICON>. "RSDBCSTY.
13
14 CONSTANTS:
15   SS_C_SO_MAX    TYPE I        VALUE 25,    " max number of select option
   s on the screen
16   SS_C_SO_MIN    TYPE I        VALUE 1,     " min number of select option
   s on the screen
17   SS_C_VARLIST   TYPE I        VALUE 10,    " border/switch for variant l
   ist popup
18   SS_C_TEXTPOOL  LIKE SY-REPID VALUE 'SAPLKESS'. " name of "template' PR
   GNAME to get texts
19
20 CONSTANTS: SS_C_MAINTAIN  TYPE XUVAL VALUE '23'.
21 CONSTANTS: SS_C_TRANSPORT TYPE XUVAL VALUE '21'.
22 CONSTANTS: SS_C_DELETE    TYPE XUVAL VALUE '06'.
23
24 DATA: " text used on selection screen filled from template but can be ch
   anged during initialization
25 *    SSTXT_01 LIKE TEXTPOOL-ENTRY,
26 *    SSTXT_02 LIKE TEXTPOOL-ENTRY,
27 *    SSTXT_03 LIKE TEXTPOOL-ENTRY,
28 *    SSTXT_04 LIKE TEXTPOOL-ENTRY,
29      SSTXT_05 LIKE TEXTPOOL-ENTRY,
30      SSTXT_06 LIKE TEXTPOOL-ENTRY,
31      SSTXT_07 LIKE TEXTPOOL-ENTRY,
32      SSTXT_08 LIKE TEXTPOOL-ENTRY,
33      SSTXT_09 LIKE TEXTPOOL-ENTRY,
34      SSTXT_10 LIKE TEXTPOOL-ENTRY,
35 *    SSTXT_11 LIKE TEXTPOOL-ENTRY,
36      SSTXT_12 LIKE TEXTPOOL-ENTRY,
37      SSTXT_13 LIKE TEXTPOOL-ENTRY,
38 *    SSTXT_14 LIKE TEXTPOOL-ENTRY,
39      SSTXT_15 LIKE TEXTPOOL-ENTRY,
40      SSTXT_16 LIKE TEXTPOOL-ENTRY,
41      SSTXT_17 LIKE TEXTPOOL-ENTRY,
42 *    SSTXT_18 LIKE TEXTPOOL-ENTRY,
43 *    SSTXT_19 LIKE TEXTPOOL-ENTRY,
44      SSTXT_20 LIKE TEXTPOOL-ENTRY,
45 *    SSTXT_21 LIKE TEXTPOOL-ENTRY,
46 *    SSTXT_22 LIKE TEXTPOOL-ENTRY,
47 *    SSTXT_23 LIKE TEXTPOOL-ENTRY,
48      SSTXT_24 LIKE TEXTPOOL-ENTRY,
49 *    SSTXT_25 LIKE TEXTPOOL-ENTRY,
50 *    SSTXT_26 LIKE TEXTPOOL-ENTRY,
51 *    SSTXT_27 LIKE TEXTPOOL-ENTRY,
52 *    SSTXT_28 LIKE TEXTPOOL-ENTRY,
53 *    SSTXT_29 LIKE TEXTPOOL-ENTRY,
54 *    SSTXT_30 LIKE TEXTPOOL-ENTRY,
55 *    SSTXT_31 LIKE TEXTPOOL-ENTRY,
56      SSTXT_32 LIKE TEXTPOOL-ENTRY,
```

```
57        SSTXT_33 LIKE TEXTPOOL-ENTRY,
58        SSTXT_34 LIKE TEXTPOOL-ENTRY,
59        SSTXT_35 LIKE TEXTPOOL-ENTRY,
60        SSTXT_36 LIKE TEXTPOOL-ENTRY,
61        SSTXT_37 LIKE TEXTPOOL-ENTRY
62        .
63
64  *** event handler used in popups
65  CLASS: SS_LCL_HANDLER_MANA DEFINITION DEFERRED,
66         SS_LCL_HANDLER_VARI DEFINITION DEFERRED.
67
68  DATA:
69    BEGIN OF SS_GD,    " global data not stored (exported) in memory
70      T_FCAT            TYPE TABLE OF DFIES,  " field catalogue, which con
    tains possible SO definition
71      OK_CODE           LIKE SY-PFKEY,        " OK code variable to handle
     response from screens
72      FIRST_INIT        TYPE FLAG VALUE ABAP_TRUE, " first call of event I
    NITIALIZATION
73      FIRST_OUTPUT      TYPE FLAG VALUE ABAP_TRUE, " event AT SELECTION-SC
    REEN OUTPUT, used to show preselection T_TRANGE
74  * ALV output variables, used in popups
75      R_ALV             TYPE REF TO   CL_SALV_TABLE,
76      R_HANDLER_MANA    TYPE REF TO   SS_LCL_HANDLER_MANA,
77      R_HANDLER_VARI    TYPE REF TO   SS_LCL_HANDLER_VARI,
78      T_SCR_MANAGE      TYPE TABLE OF TKESS_YS_SCR_MANAGE,  " manage scree
    ns list
79      T_VARIANT         TYPE TABLE OF RSVARIINFO,    "get variant - list o
    f variants
80      T_SCREEN          TYPE KESS_YT_SCREEN,
81      T_ROWS            TYPE SALV_T_ROW,
82      SIMUL_EXEC        TYPE FLAG,    " "Simulated" execution
83    END OF SS_GD.
84
85  DATA: " 'local' variables used very often in subroutines
86    SS_S_FCAT            TYPE KESS_YS_FCAT,
87    SS_FIELDNAME         TYPE FIELDNAME,
88    SS_TABLENAME         TYPE TABNAME,
89    SS_TFNAME            TYPE RSSCR_DBFI.
90
91  DATA:
92    SS_GR_INT            TYPE REF TO CL_KESS_FREE_SELECTION_INT,
93    SS_GR_EXT            TYPE REF TO CL_KESS_FREE_SELECTION.
94
95  FIELD-SYMBOLS:
96    <FS>                 TYPE ANY.
97
98  *---------------------------------------------------------------------*
99  *       CLASS lcl_handle_events DEFINITION
100 *---------------------------------------------------------------------*
101 * define a local class for handling events of cl_salv_table
102 *---------------------------------------------------------------------*
103 CLASS SS_LCL_HANDLER_MANA DEFINITION.
104
105   PUBLIC SECTION.
106     METHODS:
107
108       ADDED_FUNCTION FOR EVENT ADDED_FUNCTION OF CL_SALV_EVENTS
109         IMPORTING
110           E_SALV_FUNCTION,
111
```

```
112         LINK_CLICK FOR EVENT LINK_CLICK OF CL_SALV_EVENTS_TABLE
113           IMPORTING
114             ROW
115             COLUMN.
116
117   ENDCLASS.                    "lcl_handle_events DEFINITION
118
119
120   CLASS SS_LCL_HANDLER_VARI DEFINITION.
121
122     PUBLIC SECTION.
123       METHODS:
124
125         ADDED_FUNCTION FOR EVENT ADDED_FUNCTION OF CL_SALV_EVENTS
126           IMPORTING
127             E_SALV_FUNCTION,
128
129         DOUBLE_CLICK FOR EVENT DOUBLE_CLICK OF CL_SALV_EVENTS_TABLE
130           IMPORTING
131             ROW.
132   ***           COLUMN.
133
134   ENDCLASS.                    "lcl_handle_events DEFINITION
135
136
137   ************************************************************************
138   ** macro to simulate hit of any key to get screen updated.
139   DEFINE HIT_FOR_SCREEN_UPDATE.
140   *** 'Hit' enter key for update
141     IF SY-BATCH IS INITIAL.
142       CALL FUNCTION 'SAPGUI_SET_FUNCTIONCODE'.
143   *       EXCEPTIONS
144   *         FUNCTION_NOT_SUPPORTED = 1
145   *         OTHERS                 = 2.
146     ENDIF.
147
148   END-OF-DEFINITION.
149   ************************************************************************
150
151   ************************************************************************
152   *** Macro to define screen push button icon, text and info text
153   DEFINE ICON_CREATE.
154
155     CALL FUNCTION 'ICON_CREATE'
156       EXPORTING
157         NAME   = &1
158         TEXT   = &2
159         INFO   = &3
160         ADD_STDINF = ' '
161       IMPORTING
162         RESULT = &4.
163
164   END-OF-DEFINITION.
165   ************************************************************************
```

Title:
G/L Account Line Item Browser (G/L View)

Text elements:

001 Dynamic Selections
002 Display Document
003 Display Original Document
004 Display Accounting Documents
005 Display Document in New Window...
006 Document
007 Line Item Report
008 Continue
009 Save as User Parameter
010 Layout Changed Manually
011 You selected too many rows (more than &1).
012 Only the first &1 rows will be considered.
013 Do you want to continue?
014 You did not select any rows.
015 The first &1 rows will be considered for the current data selection.
016 Invalid selection
017 Always
018 More than 100.000 data records were selected.
019 Formatting this number of data records for display will take some time.
020 More than 10.000 document numbers are contained in the current selection.
021 Selecting and formatting this number of data records for display will take
022 Call Report...
023 Assign Report...
024 G/L Account Line Item Browser (G/L View)
025 G/L Account Line Item Browser
026 G/L Account Line Item Browser (Entry View)
027 Customer Line Item Browser (G/L View)
028 Customer Line Item Browser (Entry View)
029 Customer Line Item Browser
030 Vendor Line Item Browser (G/L View)
031 Vendor Line Item Browser (Entry View)
032 Vendor Line Item Browser
033 Careful when specifying year and period
034 Choose Ledger
035 Entry View
036 G/L View
037 Call Line Item Report
038 Select at least one entry
039 Key information incomplete
040 Display Original Document...
041 Display Accounting Documents...
042 Hide ALV Standard Functions
043 Show ALV Standard Functions
044 Download first result list into file
045 Also include items from accounts without open item management
B05 General Restrictions
B10 Line Item Selection
B15 Additional Restrictions
B20 Output
B25 File Output Details
B30 Group Selections
B31 Profit Center Groups
B32 Account Groups
COR or

Selection texts:

P_ACGRP
D .
P_AI
D .
P_APPL
D .
P_CI
D .
P_DAPPL
D .
P_DFILE
D .
P_DPRES
D .
P_KEYDC
D .
P_KEYDO
D .
P_LAYOUT
D .
P_LEDGER
D .
P_OI
D .
P_OUTFI
D .
P_OUTLI
D .
P_PCGRP
D .
P_SETBUK
Or Company Code Set
P_SETCUS
Or Customer Set
P_SETRAC
Or G/L Account Set
P_SETVEN
Or Vendor Set
P_TY_NIT
D .
P_TY_NOR
D .
P_TY_PIT
D .
P_TY_SPG
D .
P_WLBUK
Or Company Code Worklist
P_WLCUS
Or Customer Worklist
P_WLRAC
Or G/L Account Worklist
P_WLVEN
Or Vendor Worklist
P_XOIM
D .
S_ACCTP
D .

```
S_CCODE
D       .
S_CDATE
D       .
S_COAREA
D       .
S_CUST
D       .
S_PDATE
D       .
S_PERIOD
D       .
S_RACCT
D       .
S_RPRCTR
D       .
S_RYEAR
D       .
S_VEND
D       .
```

Owner..... SAP
Short text..... Meldungen für logische Datenbanken und Batch-Verarbeitung
Edit Language DE
Status 07.02.22

DB030 **Report & does not have any variants**
DB610 **"Select Variant" was canceled by user**
DB612 **Variant &1 of report &2 does not exist**
Diagnosis

System Response

Procedure

Procedure for System Administration

DB634 **Variant &1 of program &2 cannot be imported (see long te**
Diagnosis

System Response

Procedure

Procedure for System Administration

Owner..... SAP
Short text..... Verwaltung von Zahlungsavisen
Edit Language DE
Status 01.04.22

FA001 **Company code & is not defined**
FA005 **Last payment advice item reached**
FA006 **Payment advice & does not exist for account & &**
FA009 **Position the cursor**
FA016 **Payment advice item & copied to payment advice item &**
FA017
FA022
FA026 **No authorization for changing pmnt advice data in comp.c &**

System Response
You cannot access the requested data.
Procedure for System Administration
If necessary, include an entry in the user's authorization profile for the authorization object and parameters specified below.
Authorization object:
Parameters:
Company code:
Activity:

Owner..... SAP
Short text..... Fehlernachrichten zum Customizing RF
Edit Language DE
Status 16.05.23

FC101 **Company code & deleted**

Owner..... SAP
Short text..... Messages FI-Reporting
Edit Language DE
Status 04.06.26

FR503 Specify valid ledger and press "ENTER"

Owner..... SAP
Short text..... Nachrichtenklasse Merkmalsableitung etc.
Edit Language DE
Status 21.07.25

K/030 You do not have authorization for this function

Owner..... SAP
Short text..... Kostenrechnung: Berichtswesen
Edit Language DE
Status 31.05.13

KB016 Select one of the alternatives specified

Diagnosis
The options specified are alternatives. You are only permitted to select one of these alternatives.
System Response
Processing is terminated.
Procedure
Mark only one of the alternatives. Use the F4 key to determine what the alternatives are used for.

KB019 No controlling area found.

KB114 The list contains no data

Diagnosis
No database records exist corresponding to the selection criteria
Or you do not have the relevant authorization in your user master record.
System Response
The list does not appear.
Procedure
Check your selection criteria and your authorizations.

Owner..... SAP
Short text..... COPA - Planung
Edit Language DE
Status 30.07.24

KG899 **Program is inconsistent -> see long text**

Diagnosis

System Response

Procedure

Procedure for System Administration

Owner..... SAP
Short text..... Nachrichten Tabellenpflege RK
Edit Language DE
Status 17.12.18

KT201 The changes have been saved

Owner..... SAP
Short text..... Nachrichten Transaktionsvarianten, Batchinput Aufzeichnung
Edit Language DE
Status 28.04.23

MS020 Transaction variant & is client-specific (manual transpo
Diagnosis

System Response

Procedure

Procedure for System Administration

MS033 Test
Diagnosis

System Response

Procedure

Procedure for System Administration

MS040 Variant group &1 is not used in transactions

Owner..... SAP
Short text..... Anbindungen CTS an externe Tools (K-Anträge etc.)
Edit Language DE
Status 06.04.21

PI000	*** Messages for WBO interface to correction requests
PI012	Request & cannot be released in the background
PI013	
PI014	&1 &2 has created this test transport for request &3.

Owner..... SAP
Short text..... Promotion management messages
Edit Language EN
Status 26.05.25

WU101 "PP conds to" date must not be earlier than "PP conds fr

Diagnosis
The validity date "purchase price conditions to " should not be before the date "purchase price conditions from ".
Procedure
Correct the date.

Subroutines:		Line	Page
ADD_PCA_SELECTIONS.....	FAGL_LINE_ITEM_BROWSER_P03	26	123
	FAGL_LINE_ITEM_BROWSER_P03	**127**	125
ADD_PRCTR_GROUPS.....	FAGL_LINE_ITEM_BROWSER_P03	20	123
	FAGL_LINE_ITEM_BROWSER_P03	**157**	125
ADD_RACCT_GROUPS.....	FAGL_LINE_ITEM_BROWSER_P03	23	123
	FAGL_LINE_ITEM_BROWSER_P03	**174**	126
ADD_SL_SELECTIONS.....	FAGL_LINE_ITEM_BROWSER_P03	30	123
	FAGL_LINE_ITEM_BROWSER_P03	**148**	125
ALV_LIST_DISPLAY.....	FAGL_LINE_ITEM_BROWSER_F27	**7**	80
APAR_BRANCH_EXTENSION.....	FAGL_LINE_ITEM_BROWSER_F50	**4**	106
AUTH_GROUPS.....	FAGL_LINE_ITEM_BROWSER_F03	505	32
	FAGL_LINE_ITEM_BROWSER_F03	**563**	33
CALL_HDBC_RESTRICTED.....	FAGL_LINE_ITEM_BROWSER_F04	37	38
	FAGL_LINE_ITEM_BROWSER_F23	**7**	75
CHECK_BEFORE_START.....	FAGL_LINE_ITEM_BROWSER_F04	113	39
	FAGL_LINE_ITEM_BROWSER_F08	**7**	58
CHECK_COAREA.....	FAGL_LINE_ITEM_BROWSER_GPC	17	110
	FAGL_LINE_ITEM_BROWSER_GPC	38	110
	FAGL_LINE_ITEM_BROWSER_GPC	**50**	110
CHOOSE_LEDGER.....	FAGL_CHOOSE_LEDGER	**7**	4
	FAGL_LINE_ITEM_BROWSER_F20	17	73
CONVERT_TO_SELTAB.....	FAGL_LINE_ITEM_BROWSER_P02	**5**	116
	FAGL_LINE_ITEM_BROWSER_P02	36	116
CONVERT_TO_SELTAB_DYN.....	FAGL_LINE_ITEM_BROWSER_P02	**25**	116
DBCON_GET.....	FAGL_LINE_ITEM_BROWSER_F05	**7**	41
	FAGL_LINE_ITEM_BROWSER_F08	310	63
DISPLAY_DATA.....	FAGL_LINE_ITEM_BROWSER_P01	26	112
	FAGL_LINE_ITEM_BROWSER_P03	**7**	123
DISVAR_VALUE_REQUEST.....	FAGL_LINE_ITEM_BROWSER	20	2
	FAGL_LINE_ITEM_BROWSER_P02	**47**	116
F4_LEDGER.....	FAGL_CHOOSE_LEDGER	**80**	5
F4_LEDGER_BROWSER.....	FAGL_LINE_ITEM_BROWSER_F20	13	73
	FAGL_LINE_ITEM_BROWSER_F44	**7**	101
	FAGL_LINE_ITEM_BROWSER_P02	125	118
	FAGL_LINE_ITEM_BROWSER_PCL3	81	129
FILENAME_VALUE_REQUEST.....	FAGL_LINE_ITEM_BROWSER	29	2
	FAGL_LINE_ITEM_BROWSER_F25	**7**	78
FILL_FIELDLIST.....	FAGL_LINE_ITEM_BROWSER_F06	**10**	44
FIND_RELEVANT_LEDGER.....	FAGL_LINE_ITEM_BROWSER_F02	349	17
	FIND_RELEVANT_LEDGER	**7**	152
FREE_SELECTIONS.....	FAGL_LINE_ITEM_BROWSER_F04	82	39
	FAGL_LINE_ITEM_BROWSER_F09	**7**	64
GET_CONTEXT.....	FAGL_LINE_ITEM_BROWSER_F34	**54**	94
GET_CURTP_INFO.....	FAGL_LINE_ITEM_BROWSER_F06	166	46
	FAGL_LINE_ITEM_BROWSER_F09	137	66
	FAGL_LINE_ITEM_BROWSER_F34	**7**	94
	FAGL_LINE_ITEM_BROWSER_F44	157	103
	FAGL_LINE_ITEM_BROWSER_P02	207	119
	FAGL_LINE_ITEM_BROWSER_PCL3	161	130
GET_LAYOUT.....	FAGL_LINE_ITEM_BROWSER_P01	23	112
	FAGL_LINE_ITEM_BROWSER_P01	**40**	112
GET_TEXT.....	FAGL_LINE_ITEM_BROWSER_F13	**24**	72
GROUP_VALUE_REQUEST.....	FAGL_LINE_ITEM_BROWSER	35	2
	FAGL_LINE_ITEM_BROWSER	44	2
	FAGL_LINE_ITEM_BROWSER_F36	**7**	96
HR_ONLY_CHECK.....	FAGL_HR_ONLY_CHECK	**7**	7
INITIALIZATION.....	FAGL_LINE_ITEM_BROWSER_F02	**7**	12
	FAGL_LINE_ITEM_BROWSER_PCL3	119	129
	FAGL_LINE_ITEM_BROWSER_PCL4	9	133

LAYOUTS_CHECK.....	FAGL_LINE_ITEM_BROWSER_F02	354	17
	FAGL_LINE_ITEM_BROWSER_F02	**571**	21
LEDGER_FROM_SELSCREEN.....	FAGL_LINE_ITEM_BROWSER_F45	**7**	105
LEDGER_VALUE_REQUEST.....	FAGL_LINE_ITEM_BROWSER_F04	35	38
	FAGL_LINE_ITEM_BROWSER_F20	**7**	73
MAIN.....	FAGL_LINE_ITEM_BROWSER_CL5	6	8
	FAGL_LINE_ITEM_BROWSER_P01	**4**	112
MESSAGES_SHOW.....	FAGL_LINE_ITEM_BROWSER_F24	**7**	76
REPORT_ASSIGN.....	FAGL_LINE_ITEM_BROWSER_F13	**7**	72
RRI_INIT.....	FAGL_LINE_ITEM_BROWSER_F04	16	38
	FAGL_LINE_ITEM_BROWSER_F27	**44**	80
SELECTION_SCREEN.....	FAGL_LINE_ITEM_BROWSER_F04	**7**	38
	FAGL_LINE_ITEM_BROWSER_PCL6	24	134
SELECTION_SCREEN_OUTPUT.....	FAGL_LINE_ITEM_BROWSER_CL7	5	9
	FAGL_LINE_ITEM_BROWSER_F03	**7**	24
SELECTION_SCREEN_PRCTR.....	FAGL_LINE_ITEM_BROWSER	81	3
	FAGL_LINE_ITEM_BROWSER_GPC	**8**	110
SELECTION_SCREEN_RACCT.....	FAGL_LINE_ITEM_BROWSER	84	3
	FAGL_LINE_ITEM_BROWSER_GPC	**29**	110
SEL_VIEW_CHECK_GET.....	FAGL_LINE_ITEM_BROWSER_CL8	16	10
	FAGL_LINE_ITEM_BROWSER_F02	551	21
	FAGL_LINE_ITEM_BROWSER_F06	176	46
	FAGL_LINE_ITEM_BROWSER_F06	432	51
	FAGL_LINE_ITEM_BROWSER_F09	73	65
	FAGL_LINE_ITEM_BROWSER_F28	**8**	90
	FAGL_LINE_ITEM_BROWSER_F44	114	102
SETVAL_FROM_GROUP.....	FAGL_LINE_ITEM_BROWSER_F37	**7**	98
	FAGL_LINE_ITEM_BROWSER_GPC	20	110
	FAGL_LINE_ITEM_BROWSER_GPC	41	110
	FAGL_LINE_ITEM_BROWSER_P03	133	125
	FAGL_LINE_ITEM_BROWSER_P03	140	125
SET_VALUE_REQUEST.....	FAGL_LINE_ITEM_BROWSER	53	2
	FAGL_LINE_ITEM_BROWSER	60	2
	FAGL_LINE_ITEM_BROWSER	67	3
	FAGL_LINE_ITEM_BROWSER	74	3
	FAGL_LINE_ITEM_BROWSER_F25	**69**	79
SS_AUTH_CHECK_GLOBAL_SCREEN...	RKESS_FORMS	82	164
	RKESS_FORMS	155	165
	RKESS_FORMS	297	168
	RKESS_FORMS	**3736**	226
SS_BUTTON_STATUS_PUSHTNAM.....	RKESS_FORMS	1718	193
	RKESS_FORMS	**1754**	193
	RKESS_FORMS	2897	212
SS_CHECK_FIELD_EXISTS.....	RKESS_EVENTS	160	158
	RKESS_FORMS	1890	196
	RKESS_FORMS	1912	196
	RKESS_FORMS	**3231**	218
	RKESS_FORMS	3777	227
SS_EVENT_AT_SELSCR_OUTPUT.....	RKESS_EVENTS	192	159
	RKESS_FORMS	**2879**	212
SS_EVENT_INITIALIZATION.....	RKESS_EVENTS	35	156
	RKESS_FORMS	**411**	169
	RKESS_FORMS	1696	192
SS_EVENT_ON_VALUE_REQUEST.....	RKESS_EVENTS	224	159
	RKESS_EVENTS	228	159
	RKESS_EVENTS	232	159
	RKESS_EVENTS	236	159
	RKESS_EVENTS	240	160
	RKESS_EVENTS	244	160
	RKESS_EVENTS	248	160
	RKESS_EVENTS	252	160

	RKESS_EVENTS	256	160
	RKESS_EVENTS	260	160
	RKESS_EVENTS	264	160
	RKESS_EVENTS	268	160
	RKESS_EVENTS	272	160
	RKESS_EVENTS	276	160
	RKESS_EVENTS	280	160
	RKESS_EVENTS	284	160
	RKESS_EVENTS	288	160
	RKESS_EVENTS	292	160
	RKESS_EVENTS	296	160
	RKESS_EVENTS	300	160
	RKESS_EVENTS	304	161
	RKESS_EVENTS	308	161
	RKESS_EVENTS	312	161
	RKESS_EVENTS	316	161
	RKESS_EVENTS	320	161
	RKESS_EVENTS	324	161
	RKESS_EVENTS	328	161
	RKESS_EVENTS	332	161
	RKESS_EVENTS	336	161
	RKESS_EVENTS	340	161
	RKESS_EVENTS	344	161
	RKESS_EVENTS	348	161
	RKESS_EVENTS	352	161
	RKESS_EVENTS	356	161
	RKESS_EVENTS	360	161
	RKESS_EVENTS	364	162
	RKESS_EVENTS	368	162
	RKESS_EVENTS	372	162
	RKESS_EVENTS	376	162
	RKESS_EVENTS	380	162
	RKESS_EVENTS	384	162
	RKESS_EVENTS	388	162
	RKESS_EVENTS	392	162
	RKESS_EVENTS	396	162
	RKESS_EVENTS	400	162
	RKESS_EVENTS	404	162
	RKESS_EVENTS	408	162
	RKESS_EVENTS	412	162
	RKESS_EVENTS	416	162
	RKESS_EVENTS	420	162
	RKESS_FORMS	**3657**	225
SS_EVENT_SY_UCOMM_GET.....	RKESS_EVENTS	60	157
	RKESS_EVENTS	106	157
	RKESS_FORMS	**3258**	218
SS_EVENT_SY_UCOMM_PUSHDEFI....	RKESS_EVENTS	76	157
	RKESS_FORMS	**2186**	200
SS_EVENT_SY_UCOMM_PUSHMANA....	RKESS_EVENTS	82	157
	RKESS_FORMS	**1132**	183
SS_EVENT_SY_UCOMM_PUSHSAVE....	RKESS_EVENTS	79	157
	RKESS_FORMS	**1380**	187
SS_EVENT_SY_UCOMM_PUSHSLCR....	RKESS_EVENTS	85	157
	RKESS_FORMS	**1938**	196
SS_EVENT_SY_UCOMM_PUSHTABL....	RKESS_EVENTS	88	157
	RKESS_FORMS	**1637**	191
SS_GET_SELOPT_NAME.....	RKESS_FORMS	**3699**	225
SS_INIT_ADJUST_SO_TO_EQUAL....	RKESS_FORMS	440	170
	RKESS_FORMS	**2829**	211
SS_INIT_ICONS_AND_BUTTONS.....	RKESS_FORMS	436	170
	RKESS_FORMS	**1706**	192

SS_INIT_LISTBOX_SCRNAME.....	RKESS_FORMS	438	170
	RKESS_FORMS	1370	187
	RKESS_FORMS	1397	187
	RKESS_FORMS	**1435**	188
SS_INIT_READ_TEXPOOL.....	RKESS_EVENTS	22	156
	RKESS_FORMS	**2199**	201
SS_PRESEL_SET_FRANGE.....	RKESS_FORMS	2708	209
	RKESS_FORMS	**2721**	209
SS_PRESEL_SET_TRANGE.....	RKESS_FORMS	**2699**	209
SS_RECEIVE_CLASS_INSTANCE.....	RKESS_FORMS	**396**	169
SS_SCREENS_GET.....	RKESS_FORMS	**3206**	217
SS_SCREENS_SET.....	RKESS_FORMS	**3218**	217
SS_SCREEN_CHECK_CHANGED.....	RKESS_EVENTS	220	159
	RKESS_FORMS	**1407**	188
SS_SCREEN_CLEAR_VALUES.....	RKESS_FORMS	**2158**	200
	RKESS_FORMS	2900	212
SS_SCREEN_DELETE.....	RKESS_FORMS	121	165
	RKESS_FORMS	**1566**	190
SS_SCREEN_GET_SELTAB.....	RKESS_FORMS	**1043**	182
SS_SCREEN_REFRESH_ASSIGNMENT..	RKESS_FORMS	**569**	172
	RKESS_FORMS	1510	189
	RKESS_FORMS	1691	192
	RKESS_FORMS	1788	194
	RKESS_FORMS	2079	199
SS_SCREEN_SET.....	RKESS_FORMS	539	172
	RKESS_FORMS	1415	188
	RKESS_FORMS	**1485**	189
SS_SCREEN_TABLE_CHANGED.....	RKESS_FORMS	1656	192
	RKESS_FORMS	**1671**	192
SS_SCREEN_UPDATE_FROM_VARIANT.	RKESS_FORMS	39	163
	RKESS_FORMS	**1773**	194
	RKESS_FORMS	3597	224
	RKESS_FORMS	3647	224
SS_SEL_TO_SO.....	RKESS_FORMS	2907	212
	RKESS_FORMS	2913	212
	RKESS_FORMS	2919	212
	RKESS_FORMS	2925	213
	RKESS_FORMS	2931	213
	RKESS_FORMS	2937	213
	RKESS_FORMS	2943	213
	RKESS_FORMS	2949	213
	RKESS_FORMS	2955	213
	RKESS_FORMS	2961	213
	RKESS_FORMS	2967	213
	RKESS_FORMS	2973	213
	RKESS_FORMS	2979	213
	RKESS_FORMS	2985	214
	RKESS_FORMS	2991	214
	RKESS_FORMS	2997	214
	RKESS_FORMS	3003	214
	RKESS_FORMS	3009	214
	RKESS_FORMS	3015	214
	RKESS_FORMS	3021	214
	RKESS_FORMS	3027	214
	RKESS_FORMS	3033	214
	RKESS_FORMS	3039	214
	RKESS_FORMS	3045	215
	RKESS_FORMS	3051	215
	RKESS_FORMS	**3672**	225
SS_SO_1SET_OUTPUT.....	RKESS_FORMS	**2260**	202
	RKESS_FORMS	3167	217

SS_SO_ASSIGN.....	RKESS_FORMS	**881**	178
	RKESS_FORMS	1529	190
	RKESS_FORMS	2090	199
SS_SO_COF_OUTPUT.....	RKESS_FORMS	2276	202
	RKESS_FORMS	**2643**	208
SS_SO_HGH_OUTPUT.....	RKESS_FORMS	2292	202
	RKESS_FORMS	**2528**	206
SS_SO_LOW_OUTPUT.....	RKESS_FORMS	2284	202
	RKESS_FORMS	**2373**	204
SS_SO_PAR_OUTPUT.....	RKESS_FORMS	2268	202
	RKESS_FORMS	**2308**	202
SS_SO_TOT_OUTPUT.....	RKESS_FORMS	2288	202
	RKESS_FORMS	**2483**	205
SS_SO_TO_SEL.....	RKESS_FORMS	**997**	181
	RKESS_FORMS	1048	182
	RKESS_FORMS	1049	182
	RKESS_FORMS	1050	182
	RKESS_FORMS	1051	182
	RKESS_FORMS	1052	182
	RKESS_FORMS	1053	182
	RKESS_FORMS	1054	182
	RKESS_FORMS	1055	182
	RKESS_FORMS	1056	182
	RKESS_FORMS	1057	182
	RKESS_FORMS	1058	182
	RKESS_FORMS	1059	182
	RKESS_FORMS	1060	182
	RKESS_FORMS	1061	182
	RKESS_FORMS	1062	182
	RKESS_FORMS	1063	182
	RKESS_FORMS	1064	182
	RKESS_FORMS	1065	182
	RKESS_FORMS	1066	182
	RKESS_FORMS	1067	182
	RKESS_FORMS	1068	182
	RKESS_FORMS	1069	182
	RKESS_FORMS	1070	182
	RKESS_FORMS	1071	182
	RKESS_FORMS	1072	182
	RKESS_FORMS	1075	182
	RKESS_FORMS	1076	182
	RKESS_FORMS	1077	182
	RKESS_FORMS	1078	182
	RKESS_FORMS	1079	182
	RKESS_FORMS	1080	182
	RKESS_FORMS	1081	182
	RKESS_FORMS	1082	182
	RKESS_FORMS	1083	182
	RKESS_FORMS	1084	182
	RKESS_FORMS	1085	182
	RKESS_FORMS	1086	182
	RKESS_FORMS	1087	182
	RKESS_FORMS	1088	182
	RKESS_FORMS	1089	182
	RKESS_FORMS	1090	182
	RKESS_FORMS	1091	182
	RKESS_FORMS	1092	182
	RKESS_FORMS	1093	182
	RKESS_FORMS	1094	182
	RKESS_FORMS	1095	182
	RKESS_FORMS	1096	182

	RKESS_FORMS	1097	182
	RKESS_FORMS	1098	182
	RKESS_FORMS	1099	182
	RKESS_FORMS	1100	183
	RKESS_FORMS	1101	183
	RKESS_FORMS	1102	183
	RKESS_FORMS	1103	183
	RKESS_FORMS	1104	183
	RKESS_FORMS	1105	183
	RKESS_FORMS	1106	183
	RKESS_FORMS	1107	183
	RKESS_FORMS	1108	183
	RKESS_FORMS	1109	183
	RKESS_FORMS	1110	183
	RKESS_FORMS	1111	183
	RKESS_FORMS	1112	183
	RKESS_FORMS	1113	183
	RKESS_FORMS	1114	183
	RKESS_FORMS	1115	183
	RKESS_FORMS	1116	183
	RKESS_FORMS	1117	183
	RKESS_FORMS	1118	183
	RKESS_FORMS	1119	183
	RKESS_FORMS	1120	183
	RKESS_FORMS	1121	183
	RKESS_FORMS	1122	183
	RKESS_FORMS	1123	183
	RKESS_FORMS	2053	198
	RKESS_FORMS	2054	198
	RKESS_FORMS	2055	198
	RKESS_FORMS	2056	198
	RKESS_FORMS	2057	198
	RKESS_FORMS	2058	198
	RKESS_FORMS	2059	198
	RKESS_FORMS	2060	198
	RKESS_FORMS	2061	198
	RKESS_FORMS	2062	198
	RKESS_FORMS	2063	198
	RKESS_FORMS	2064	198
	RKESS_FORMS	2065	198
	RKESS_FORMS	2066	198
	RKESS_FORMS	2067	198
	RKESS_FORMS	2068	198
	RKESS_FORMS	2069	198
	RKESS_FORMS	2070	198
	RKESS_FORMS	2071	199
	RKESS_FORMS	2072	199
	RKESS_FORMS	2073	199
	RKESS_FORMS	2074	199
	RKESS_FORMS	2075	199
	RKESS_FORMS	2076	199
	RKESS_FORMS	2077	199
SS_SO_TXT_OUTPUT.....	RKESS_FORMS	2280	202
	RKESS_FORMS	**2327**	203
SS_SO_UNASSIGN.....	RKESS_EVENTS	155	158
	RKESS_FORMS	**693**	174
	RKESS_FORMS	2045	198
SS_SO_UPDATE_EXCLUDED.....	RKESS_FORMS	2146	200
	RKESS_FORMS	**2677**	209
SS_SO_VPU_OUTPUT.....	RKESS_FORMS	2296	202
	RKESS_FORMS	**2598**	207

SS_SYNC_GS_TO_PARAM.....	RKESS_FORMS	560	172
	RKESS_FORMS	**2133**	200
SS_SYNC_PAR_TO_GS.....	RKESS_EVENTS	180	158
	RKESS_FORMS	1929	196
	RKESS_FORMS	**2113**	199
	RKESS_FORMS	2889	212
SS_SYNC_SF.....	RKESS_FORMS	2891	212
	RKESS_FORMS	**3770**	227
SS_VARIANTS_GET.....	RKESS_FORMS	**3181**	217
SS_VARIANTS_SET.....	RKESS_FORMS	**3193**	217
SS_VARIANT_GET_KESS.....	RKESS_FORMS	3262	218
	RKESS_FORMS	**3277**	218
SS_VARIANT_GET_STANDARD.....	RKESS_FORMS	3266	218
	RKESS_FORMS	**3607**	224
SUBMIT_RESTART.....	FAGL_LINE_ITEM_BROWSER_F04	31	38
	FAGL_LINE_ITEM_BROWSER_F20	**31**	73
SYNC_CHECK_FLD_ON_KESS.....	FAGL_LINE_ITEM_BROWSER_F03	642	34
	FAGL_LINE_ITEM_BROWSER_F03	**666**	35
SYNC_ITEMS_TO_SELECTION_SCREEN	FAGL_LINE_ITEM_BROWSER_F03	514	32
	FAGL_LINE_ITEM_BROWSER_F03	524	32
	FAGL_LINE_ITEM_BROWSER_F03	**698**	35
	FAGL_LINE_ITEM_BROWSER_F04	95	39
	FAGL_LINE_ITEM_BROWSER_F04	110	39
	FAGL_LINE_ITEM_BROWSER_F04	143	40
	FAGL_LINE_ITEM_BROWSER_F27	594	89
SYNC_KESS_TO_ITEMS.....	FAGL_LINE_ITEM_BROWSER_F03	519	32
	FAGL_LINE_ITEM_BROWSER_F03	**619**	34
	FAGL_LINE_ITEM_BROWSER_F04	75	39
	FAGL_LINE_ITEM_BROWSER_F04	105	39
	FAGL_LINE_ITEM_BROWSER_F04	137	40
SYNC_SELECTIONS_TO_BADI.....	FAGL_LINE_ITEM_BROWSER_F03	521	32
	FAGL_LINE_ITEM_BROWSER_F03	**597**	34
	FAGL_LINE_ITEM_BROWSER_F04	78	39
	FAGL_LINE_ITEM_BROWSER_F04	91	39
	FAGL_LINE_ITEM_BROWSER_F04	107	39
	FAGL_LINE_ITEM_BROWSER_F04	139	40
SYNC_SELECTION_SCREEN_TO_KESS.	FAGL_LINE_ITEM_BROWSER_F03	629	34
	FAGL_LINE_ITEM_BROWSER_F03	**753**	36
	FAGL_LINE_ITEM_BROWSER_F27	595	89
UPDATE_SCREEN.....	FAGL_LINE_ITEM_BROWSER_P02	338	121
	FAGL_LINE_ITEM_BROWSER_P02	343	121
	FAGL_LINE_ITEM_BROWSER_P02	**351**	121

Screens:

		Line	Page
'0000'.....	RKESS_EVENTS	43	156
	RKESS_EVENTS	206	159

Messages:

		Line	Page
?.....	FAGL_CHOOSE_LEDGER	67	5
?.....	FAGL_CHOOSE_LEDGER	128	6
?.....	FAGL_LINE_ITEM_BROWSER_F02	168	14
?.....	FAGL_LINE_ITEM_BROWSER_F05	75	42
?.....	FAGL_LINE_ITEM_BROWSER_F05	128	43
?.....	FAGL_LINE_ITEM_BROWSER_F08	300	62
?.....	FAGL_LINE_ITEM_BROWSER_F27	37	80

?.....	FAGL_LINE_ITEM_BROWSER_F36	45	96
?.....	FAGL_LINE_ITEM_BROWSER_F37	89	99
?.....	FAGL_LINE_ITEM_BROWSER_F37	116	99
?.....	FAGL_LINE_ITEM_BROWSER_F44	82	102
?.....	FAGL_LINE_ITEM_BROWSER_F44	106	102
?.....	RKESS_FORMS	274	167
DB030.....	RKESS_FORMS	3633	224
DB610.....	RKESS_FORMS	3639	224
DB612.....	RKESS_EVENTS	125	158
	RKESS_EVENTS	129	158
	RKESS_FORMS	3636	224
DB634.....	RKESS_EVENTS	127	158
FAGL_ACCOUNT_BALANCE026.....	FAGL_LINE_ITEM_BROWSER_F08	268	62
FAGL_REPORTING_EN001.....	FAGL_LINE_ITEM_BROWSER_F04	129	40
FAGL_REPORTING_EN005.....	FAGL_LINE_ITEM_BROWSER_F09	380	70
FAGL_REPORTING_EN006.....	FAGL_LINE_ITEM_BROWSER_F08	324	63
FAGL_REPORTING_EN009.....	FAGL_LINE_ITEM_BROWSER_F08	333	63
FAGL_REPORTING_EN016.....	FAGL_LINE_ITEM_BROWSER_F36	75	97
FAGL_REPORTING_EN017.....	FAGL_LINE_ITEM_BROWSER_F37	67	99
	FAGL_LINE_ITEM_BROWSER_GPC	66	111
	FAGL_LINE_ITEM_BROWSER_PCL6	38	134
FAGL_REPORTING_EN022.....	FAGL_LINE_ITEM_BROWSER_F08	352	63
FCO_COPA101.....	RKESS_EVENTS	205	159
FR503.....	FAGL_LINE_ITEM_BROWSER_F45	32	105
K/030.....	RKESS_FORMS	88	164
	RKESS_FORMS	161	165
	RKESS_FORMS	316	168
	RKESS_FORMS	333	168
KB016.....	FAGL_LINE_ITEM_BROWSER_GPC	14	110
	FAGL_LINE_ITEM_BROWSER_GPC	35	110
KB019.....	FAGL_LINE_ITEM_BROWSER_GPC	59	110
KB114.....	RKESS_FORMS	1173	184
	RKESS_FORMS	3447	221
KG899.....	RKESS_FORMS	492	171
	RKESS_FORMS	500	171
	RKESS_FORMS	712	174
	RKESS_FORMS	916	179
	RKESS_FORMS	1505	189
	RKESS_FORMS	2026	198
KT201.....	RKESS_FORMS	1373	187
MSITEM020.....	FAGL_LINE_ITEM_BROWSER_F08	344	63
MSITEM033.....	FAGL_LINE_ITEM_BROWSER_P03	122	125
MSITEM040.....	FAGL_LINE_ITEM_BROWSER_F08	53	58
	FAGL_LINE_ITEM_BROWSER_F08	99	59
PIVB000.....	FAGL_LINE_ITEM_BROWSER_P01	60	112
PIVB012.....	FAGL_LINE_ITEM_BROWSER_P02	342	121
PIVB013.....	FAGL_LINE_ITEM_BROWSER_P02	336	121
PIVB014.....	FAGL_LINE_ITEM_BROWSER_P02	334	121
WUSL101.....	RKESS_FORMS	277	167

External calls

Function Modules		Line	Page
?.....	FAGL_LINE_ITEM_BROWSER_F28	96	91
ADDR_GET.....	FAGL_LINE_ITEM_BROWSER_F50	70	107
	FAGL_LINE_ITEM_BROWSER_F50	88	107
	FAGL_LINE_ITEM_BROWSER_F50	147	108
	FAGL_LINE_ITEM_BROWSER_F50	165	108
BAL_CNTL_CREATE.....	FAGL_LINE_ITEM_BROWSER_F24	76	77
BAL_DSP_LOG_DISPLAY.....	FAGL_LINE_ITEM_BROWSER_F24	82	77
BAL_DSP_PROFILE_NO_TREE_GET...	FAGL_LINE_ITEM_BROWSER_F24	53	76
BAL_LOG_CREATE.....	FAGL_LINE_ITEM_BROWSER_F24	27	76
BAL_LOG_MSG_ADD.....	FAGL_LINE_ITEM_BROWSER_F24	43	76
DB_COMMIT.....	FAGL_LINE_ITEM_BROWSER_F02	699	23
DDIF_FIELDINFO_GET.....	FAGL_LINE_ITEM_BROWSER_F02	236	16
	FAGL_LINE_ITEM_BROWSER_F02	383	18
	FAGL_LINE_ITEM_BROWSER_F02	392	18
	FAGL_LINE_ITEM_BROWSER_F02	401	18
	FAGL_LINE_ITEM_BROWSER_F02	410	18
	FAGL_LINE_ITEM_BROWSER_F02	419	19
	FAGL_LINE_ITEM_BROWSER_F02	428	19
	FAGL_LINE_ITEM_BROWSER_F02	437	19
	FAGL_LINE_ITEM_BROWSER_F02	446	19
	FAGL_LINE_ITEM_BROWSER_F02	455	19
	FAGL_LINE_ITEM_BROWSER_F02	464	19
	FAGL_LINE_ITEM_BROWSER_F02	473	19
	FAGL_LINE_ITEM_BROWSER_F02	482	20
	FAGL_LINE_ITEM_BROWSER_F02	491	20
	FAGL_LINE_ITEM_BROWSER_F06	157	46
	FAGL_LINE_ITEM_BROWSER_F27	181	82
	FAGL_LINE_ITEM_BROWSER_F27	241	83
	FAGL_LINE_ITEM_BROWSER_PCL3	201	131
DDIF_NAMETAB_GET.....	FAGL_LINE_ITEM_BROWSER_F44	165	103
	FAGL_LINE_ITEM_BROWSER_P02	215	119
	FAGL_LINE_ITEM_BROWSER_PCL3	169	130
DDIF_VIEW_GET.....	FAGL_LINE_ITEM_BROWSER_F06	102	45
	FAGL_LINE_ITEM_BROWSER_F28	55	91
DYNP_VALUES_READ.....	FAGL_LINE_ITEM_BROWSER_F36	35	96
	FAGL_LINE_ITEM_BROWSER_F45	17	105
DYNP_VALUES_UPDATE.....	FAGL_LINE_ITEM_BROWSER_P02	365	122
F4IF_FIELD_VALUE_REQUEST.....	FAGL_CHOOSE_LEDGER	100	5
F4_DD_ALLTYPES.....	RKESS_FORMS	476	171
	RKESS_FORMS	1645	191
F4_DXFILENAME_TOPRECURSION....	FAGL_LINE_ITEM_BROWSER_F25	56	78
FAGL_CHECK_GLFLEX_ACTIVE.....	FAGL_LINE_ITEM_BROWSER_F08	262	62
FAGL_CHECK_REP_AUTH_SEL_SCREEN	FAGL_LINE_ITEM_BROWSER_F05	116	43
FAGL_DBCON_GET_APPL.....	FAGL_LINE_ITEM_BROWSER_F02	195	15
	FAGL_LINE_ITEM_BROWSER_F05	62	42
FAGL_FISL_VIEW_FOR_RLDNR_GET..	FAGL_LINE_ITEM_BROWSER_F02	157	14
	FAGL_LINE_ITEM_BROWSER_F02	332	17
	FAGL_LINE_ITEM_BROWSER_F08	289	62
	FAGL_LINE_ITEM_BROWSER_F44	95	102
	FAGL_LINE_ITEM_BROWSER_P02	113	117
	FAGL_LINE_ITEM_BROWSER_PCL3	69	129
FAGL_GET_FAGL_SETTINGS.....	FAGL_LINE_ITEM_BROWSER_F02	136	14
	FAGL_LINE_ITEM_BROWSER_F02	248	16
	FAGL_LINE_ITEM_BROWSER_F02	560	21
	FAGL_LINE_ITEM_BROWSER_F03	223	27
	FAGL_LINE_ITEM_BROWSER_F27	107	81

	FAGL_LINE_ITEM_BROWSER_PCL3	127	130
FAGL_GET_LEADING_LEDGER.....	FAGL_LINE_ITEM_BROWSER_F02	594	21
	FIND_RELEVANT_LEDGER	36	152
FAGL_HDB_CUST_BRW_SELVIEW_CHCK	FAGL_LINE_ITEM_BROWSER_F28	87	91
FAGL_HDB_CUST_BRW_SELVIEW_GET.	FAGL_LINE_ITEM_BROWSER_F28	76	91
FAGL_HDB_CUST_BRW_TABLES_GET..	FAGL_LINE_ITEM_BROWSER_F05	42	41
	FAGL_LINE_ITEM_BROWSER_F05	51	41
FAGL_HDB_CUST_SVIEW_EXCL_FLDS.	FAGL_LINE_ITEM_BROWSER_CL8	23	10
	FAGL_LINE_ITEM_BROWSER_F06	440	51
	FAGL_LINE_ITEM_BROWSER_F09	111	65
	FAGL_LINE_ITEM_BROWSER_F44	122	102
	FAGL_LINE_ITEM_BROWSER_P02	172	118
FAGL_VIEWS_GENERATE_ALL.....	FAGL_LINE_ITEM_BROWSER_F02	366	18
FAGL_VIEWS_GET_VIEWNAME_FISL..	FAGL_LINE_ITEM_BROWSER_P02	151	118
	FAGL_LINE_ITEM_BROWSER_PCL3	107	129
FILE_GET_NAME.....	FAGL_LINE_ITEM_BROWSER_F25	45	78
FI_ITEMS_BRANCH_CENTRAL.....	FAGL_LINE_ITEM_BROWSER_F50	99	107
	FAGL_LINE_ITEM_BROWSER_F50	176	108
FREE_SELECTIONS_DIALOG.....	FAGL_LINE_ITEM_BROWSER_F09	401	70
FREE_SELECTIONS_INIT.....	FAGL_LINE_ITEM_BROWSER_F09	359	70
	FAGL_LINE_ITEM_BROWSER_F28	156	92
FREE_SELECTIONS_RANGE_2_EX....	FAGL_LINE_ITEM_BROWSER_F09	319	69
FREE_SELECTIONS_RANGE_2_WHERE.	FAGL_LINE_ITEM_BROWSER_F09	325	69
GL_USER_DATA_GET.....	FIND_RELEVANT_LEDGER	22	152
G_DISPLAY_LEDGERS_FOR_TABLE...	FAGL_LINE_ITEM_BROWSER_F44	65	102
G_GET_LEDGER_INFO.....	FAGL_LINE_ITEM_BROWSER_F06	122	46
	FAGL_LINE_ITEM_BROWSER_F44	38	101
	FAGL_LINE_ITEM_BROWSER_F44	140	103
	FAGL_LINE_ITEM_BROWSER_P02	139	118
	FAGL_LINE_ITEM_BROWSER_P02	190	119
	FAGL_LINE_ITEM_BROWSER_PCL3	95	129
	FAGL_LINE_ITEM_BROWSER_PCL3	144	130
G_GET_TABLE_INFO.....	FAGL_LINE_ITEM_BROWSER_F06	130	46
	FAGL_LINE_ITEM_BROWSER_F44	44	101
	FAGL_LINE_ITEM_BROWSER_F44	88	102
	FAGL_LINE_ITEM_BROWSER_F44	148	103
	FAGL_LINE_ITEM_BROWSER_P02	145	118
	FAGL_LINE_ITEM_BROWSER_P02	198	119
	FAGL_LINE_ITEM_BROWSER_PCL3	101	129
	FAGL_LINE_ITEM_BROWSER_PCL3	152	130
G_RW_SET_SELECT.....	FAGL_LINE_ITEM_BROWSER_F25	79	79
G_SET_ENCRYPT_SETID.....	FAGL_LINE_ITEM_BROWSER_F37	77	99
G_SET_GET_ALL_VALUES.....	FAGL_LINE_ITEM_BROWSER_F08	145	60
	FAGL_LINE_ITEM_BROWSER_F08	215	61
G_SET_GET_ID_FROM_NAME.....	FAGL_LINE_ITEM_BROWSER_F08	132	60
	FAGL_LINE_ITEM_BROWSER_F08	172	60
	FAGL_LINE_ITEM_BROWSER_F08	185	61
	FAGL_LINE_ITEM_BROWSER_F08	198	61
G_SUMTABLE_AND_MODE_GIVE.....	FAGL_LINE_ITEM_BROWSER_F44	53	101
HDB_RANGE_READ.....	FAGL_LINE_ITEM_BROWSER_F03	80	25
	FAGL_LINE_ITEM_BROWSER_F03	96	25
	FAGL_LINE_ITEM_BROWSER_F03	107	25
	FAGL_LINE_ITEM_BROWSER_F03	123	26
	FAGL_LINE_ITEM_BROWSER_F09	168	66
	FAGL_LINE_ITEM_BROWSER_PCL3	267	132
HDB_RANGE_SAVE.....	FAGL_LINE_ITEM_BROWSER_F09	187	67
HDB_SETT_AUTHORITY_CHECK.....	FAGL_LINE_ITEM_BROWSER_F02	225	15
HDB_SETT_MAINTAIN.....	FAGL_LINE_ITEM_BROWSER_F23	36	75
ICON_CREATE.....	FAGL_LINE_ITEM_BROWSER_F02	373	18
	ICON_CREATE	0	
	ICON_CREATE	0	

	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
	ICON_CREATE	0	
KESS_FILTER_VARIANTS.....	RKESS_FORMS	3357	220
KESS_SAVE_SCREEN.....	RKESS_FORMS	1387	187
K_GROUP_SELECT.....	FAGL_LINE_ITEM_BROWSER_F36	61	96
K_HIERARCHY_TABLES_READ.....	FAGL_LINE_ITEM_BROWSER_F37	100	99
K_KOKRS_SET.....	FAGL_LINE_ITEM_BROWSER_PCL4	20	133
LVC_FIELDCATALOG_MERGE.....	FAGL_LINE_ITEM_BROWSER_F06	140	46
	FAGL_LINE_ITEM_BROWSER_F06	149	46
	FAGL_LINE_ITEM_BROWSER_P01	120	114
LVC_VARIANT_EXISTENCE_CHECK...	FAGL_LINE_ITEM_BROWSER_P01	75	113
LVC_VARIANT_SAVE.....	FAGL_LINE_ITEM_BROWSER_P01	142	114
LVC_VARIANT_SELECT.....	FAGL_LINE_ITEM_BROWSER_F06	458	51
PIVB_CONV_RANGE_TO_SELTAB.....	FAGL_LINE_ITEM_BROWSER_P02	12	116
PIVB_F4.....	FAGL_LINE_ITEM_BROWSER_P02	306	121
PIVB_SELECT_AND_DISPLAY.....	FAGL_LINE_ITEM_BROWSER_P03	105	124
PIVB_SELECT_AND_RETURN.....	FAGL_LINE_ITEM_BROWSER_P03	66	124
POPUP_GET_VALUES_USER_BUTTONS.	FAGL_CHOOSE_LEDGER	37	4
POPUP_TO_CONFIRM.....	RKESS_FORMS	101	164
REUSE_ALV_LIST_DISPLAY.....	FAGL_LINE_ITEM_BROWSER_F27	27	80
REUSE_ALV_VARIANT_DEFAULT_GET.	FAGL_LINE_ITEM_BROWSER_P01	51	112
RF_WORKLISTS_VALUES_GET.....	FAGL_LINE_ITEM_BROWSER_F08	44	58
	FAGL_LINE_ITEM_BROWSER_F08	90	59
RGRE_ERGSL_TO_RACCT_CONVERT...	FAGL_LINE_ITEM_BROWSER_F27	334	85
RH_APPLICATION_SYSTEM_CHECK...	FAGL_HR_ONLY_CHECK	12	7
RKE_FIELD_SELECTION_POPUP.....	RKESS_FORMS	2008	197
RSTI_APPL_STACK_INITIALIZE....	FAGL_LINE_ITEM_BROWSER_F27	140	82
RSTI_APPL_STACK_POP.....	FAGL_LINE_ITEM_BROWSER_F27	93	81
RSTI_REPORT_ADD.....	FAGL_LINE_ITEM_BROWSER_F13	14	72
RSTI_SELECTION_IMPORT.....	FAGL_LINE_ITEM_BROWSER_F27	132	82
RS_GET_SCREENS_4_1_VARIANT....	RKESS_FORMS	3375	220
RS_READ_SEL_OPTIONS.....	FAGL_LINE_ITEM_BROWSER_F06	184	47
	FAGL_LINE_ITEM_BROWSER_F28	137	92
	FAGL_LINE_ITEM_BROWSER_P02	260	120
RS_REFRESH_FROM_SELECTOPTIONS.	FAGL_LINE_ITEM_BROWSER_F20	52	73
RS_REPORTSELECTIONS_INFO.....	FAGL_LINE_ITEM_BROWSER_F27	162	82
RS_SUPPORT_SELECTIONS.....	RKESS_EVENTS	113	157
RS_VARIANT_CATALOG.....	RKESS_FORMS	3615	224
RS_VARIANT_CONTENTS.....	RKESS_FORMS	3412	221
RS_VARIANT_EXISTS.....	RKESS_FORMS	421	170
RS_VARIANT_INFO.....	RKESS_FORMS	3325	219
SAPGUI_SET_FUNCTIONCODE.....	HIT_FOR_SCREEN_UPDATE	0	
	HIT_FOR_SCREEN_UPDATE	0	
	HIT_FOR_SCREEN_UPDATE	0	
	HIT_FOR_SCREEN_UPDATE	0	
SE16N_UT_GET_SELECT_CRITERIA..	FAGL_LINE_ITEM_BROWSER_F09	281	68
SELECT_OPTIONS_RESTRICT.....	RKESS_FORMS	2856	211
TR_APPEND_TO_COMM_OBJS_KEYS...	RKESS_FORMS	263	167
TR_ORDER_CHOICE_CORRECTION....	RKESS_FORMS	167	165
VRM_SET_VALUES.....	FAGL_LINE_ITEM_BROWSER_F03	554	33
	RKESS_FORMS	1476	189

SET/GET Parameters		Line	Page
ACC	FAGL_LINE_ITEM_BROWSER_F02	112	13
	FAGL_LINE_ITEM_BROWSER_F02	129	14
	FAGL_LINE_ITEM_BROWSER_F02	145	14
BUK	FAGL_LINE_ITEM_BROWSER_F02	189	15
CAC	FAGL_LINE_ITEM_BROWSER_PCL4	14	133
FIT_BRANCH	FAGL_LINE_ITEM_BROWSER_F50	33	106
FIT_X_AP	FAGL_LINE_ITEM_BROWSER_F02	108	13
FIT_X_AR	FAGL_LINE_ITEM_BROWSER_F02	125	14
FIT_X_GL	FAGL_LINE_ITEM_BROWSER_F02	117	14
FI_WORKLISTS_FLAG	FAGL_LINE_ITEM_BROWSER_F02	257	16
GLN	FAGL_LINE_ITEM_BROWSER_F02	154	14
	FAGL_LINE_ITEM_BROWSER_P02	96	117
	FAGL_LINE_ITEM_BROWSER_P02	131	118
	FAGL_LINE_ITEM_BROWSER_PCL3	46	128
	FAGL_LINE_ITEM_BROWSER_PCL3	87	129
KUN	FAGL_LINE_ITEM_BROWSER_F02	120	14
LIF	FAGL_LINE_ITEM_BROWSER_F02	103	13
PIVB_LAST_TAB	FAGL_LINE_ITEM_BROWSER_F02	545	21
	FAGL_LINE_ITEM_BROWSER_F02	548	21

Reports:		Line	Page
?	FAGL_LINE_ITEM_BROWSER_F20	83	74

External subroutines		Line	Page
GET_TABLE_FIELD_FROM_CLASS	FAGL_LINE_ITEM_BROWSER_F36	21	96

DATABASE OPERATIONS

SELECT:

		Line	Page
FAGL_ORG_INFC_CT	FAGL_LINE_ITEM_BROWSER_F34	32	94
FAGL_ORG_INFG_CT	FAGL_LINE_ITEM_BROWSER_F34	37	94
FAGL_ORG_INFO_CT	FAGL_LINE_ITEM_BROWSER_F34	44	94
FINSC_LEDGER	FAGL_LINE_ITEM_BROWSER_F03	396	30
KNA1	FAGL_LINE_ITEM_BROWSER_F13	45	72
	FAGL_LINE_ITEM_BROWSER_F50	141	108
	FAGL_LINE_ITEM_BROWSER_F50	159	108
KNB1	FAGL_LINE_ITEM_BROWSER_F50	121	107
LFA1	FAGL_LINE_ITEM_BROWSER_F13	50	72
	FAGL_LINE_ITEM_BROWSER_F50	64	107
	FAGL_LINE_ITEM_BROWSER_F50	82	107
LFB1	FAGL_LINE_ITEM_BROWSER_F50	43	106
LTDX	FAGL_LINE_ITEM_BROWSER_F02	586	21
	FAGL_LINE_ITEM_BROWSER_F02	601	22
LTDXD	FAGL_LINE_ITEM_BROWSER_F02	636	22
LTDXT	FAGL_LINE_ITEM_BROWSER_F02	668	23
SKA1	FAGL_LINE_ITEM_BROWSER_F27	517	88
T001	FAGL_LINE_ITEM_BROWSER_F08	255	62
TKA01	FAGL_LINE_ITEM_BROWSER_F37	60	98
	FAGL_LINE_ITEM_BROWSER_GPC	54	110
	FAGL_LINE_ITEM_BROWSER_PCL6	31	134
TKA02	FAGL_LINE_ITEM_BROWSER_GPC	61	111
TKESS_SCR	RKESS_FORMS	1154	183
	RKESS_FORMS	1163	184
	RKESS_FORMS	1450	188
	RKESS_FORMS	1458	188
	RKESS_FORMS	1499	189
TKESS_SCR_DESCR	RKESS_FORMS	1217	184
	RKESS_FORMS	1535	190
TKESS_SCR_FIELD	RKESS_FORMS	1515	189
TKESS_SCR_INIT	FAGL_LINE_ITEM_BROWSER_PCL3	215	131
	RKESS_FORMS	239	167
	RKESS_FORMS	514	171
	RKESS_FORMS	525	171
	RKESS_FORMS	1177	184
	RKESS_FORMS	1196	184
	RKESS_FORMS	1593	191
VARID	RKESS_FORMS	3344	219

MODIFY:

		Line	Page
LT_PARAMS	FAGL_LINE_ITEM_BROWSER_F20	77	74
SS_GD-T_SCR_MANAGE	RKESS_FORMS	347	168
	RKESS_FORMS	366	169
	RKESS_FORMS	378	169
	RKESS_FORMS	1190	184
	RKESS_FORMS	1209	184
	RKESS_FORMS	1225	185
SS_GR_INT->T_TRANGE	RKESS_FORMS	1033	181
TKESS_SCR_INIT	RKESS_FORMS	1327	186
	RKESS_FORMS	1346	187
	RKESS_FORMS	1359	187
	RKESS_FORMS	1609	191

DELETE:

		Line	Page
LTDX	FAGL_LINE_ITEM_BROWSER_F02	624	22
LTDXD	FAGL_LINE_ITEM_BROWSER_F02	658	22
LTDXT	FAGL_LINE_ITEM_BROWSER_F02	690	23
RFDT	FAGL_LINE_ITEM_BROWSER_F20	42	73
TKESS_SCR	RKESS_FORMS	1621	191
TKESS_SCR_DESCR	RKESS_FORMS	1578	190
	RKESS_FORMS	1585	190
TKESS_SCR_FIELD	RKESS_FORMS	1615	191
TKESS_SCR_INIT	RKESS_FORMS	1331	186
	RKESS_FORMS	1352	187
	RKESS_FORMS	1601	191

INTERNAL TABLE OPERATIONS

READ TABLE:		Line	Page
<LSX_TABLE_FIELD_RANGES>-FRANG	FAGL_LINE_ITEM_BROWSER_F09	246	68
<LSX_TRANGE>-FRANGE_T.....	FAGL_LINE_ITEM_BROWSER_F27	420	86
	FAGL_LINE_ITEM_BROWSER_F27	427	87
	FAGL_LINE_ITEM_BROWSER_F27	492	88
	FAGL_LINE_ITEM_BROWSER_F27	500	88
<RANGE_ITEM>-FRANGE_T.....	FAGL_LINE_ITEM_BROWSER_F03	652	35
<TRANGE>-FRANGE_T.....	FAGL_LINE_ITEM_BROWSER_F03	737	36
CT_FIELDCAT.....	FAGL_LINE_ITEM_BROWSER_F06	486	52
	FAGL_LINE_ITEM_BROWSER_F06	591	53
	FAGL_LINE_ITEM_BROWSER_F06	624	54
	FAGL_LINE_ITEM_BROWSER_F06	721	55
CT_FIELDLIST.....	FAGL_LINE_ITEM_BROWSER_F06	761	56
GTS_CURTP.....	FAGL_LINE_ITEM_BROWSER_F06	358	49
	FAGL_LINE_ITEM_BROWSER_F09	152	66
	FAGL_LINE_ITEM_BROWSER_F44	174	103
	FAGL_LINE_ITEM_BROWSER_P02	224	119
	FAGL_LINE_ITEM_BROWSER_PCL3	178	130
LTS_DFIES.....	FAGL_LINE_ITEM_BROWSER_F06	219	47
	FAGL_LINE_ITEM_BROWSER_F06	303	48
	FAGL_LINE_ITEM_BROWSER_F06	665	54
	FAGL_LINE_ITEM_BROWSER_F06	671	55
	FAGL_LINE_ITEM_BROWSER_F06	677	55
LT_AVAILABLE_FIELDS.....	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	ADD_FIELD	0	
	FAGL_LINE_ITEM_BROWSER_PCL3	232	131
	FAGL_LINE_ITEM_BROWSER_PCL3	241	131
LT_COAREA.....	FAGL_LINE_ITEM_BROWSER_F37	72	99
LT_DD26V.....	FAGL_LINE_ITEM_BROWSER_F06	115	45
	FAGL_LINE_ITEM_BROWSER_F28	68	91
LT_DEFAULT_FIELDS.....	FAGL_LINE_ITEM_BROWSER_P01	127	114
LT_DFIES.....	FAGL_LINE_ITEM_BROWSER_F27	454	87
LT_FIELDCAT_REFTAB.....	FAGL_LINE_ITEM_BROWSER_F06	401	50
LT_FIELDS.....	FAGL_LINE_ITEM_BROWSER_F28	148	92
	FAGL_LINE_ITEM_BROWSER_F45	24	105
LT_FIELD_NAMES.....	FAGL_LINE_ITEM_BROWSER_F06	386	50
LT_FIELD_R.....	FAGL_LINE_ITEM_BROWSER_F27	374	86
LT_FIELD_S.....	FAGL_LINE_ITEM_BROWSER_F27	358	85
LT_FRANGE.....	RKESS_FORMS	3687	225
LT_MULTI_OR_ALL.....	FAGL_LINE_ITEM_BROWSER_F09	215	67
LT_OR_MUL_ALL.....	FAGL_LINE_ITEM_BROWSER_F09	221	67
LT_PARAMS.....	FAGL_LINE_ITEM_BROWSER_F20	64	74
LT_RETURN.....	FAGL_CHOOSE_LEDGER	132	6
LT_SEL.....	FAGL_LINE_ITEM_BROWSER_F27	467	87
LT_TEXTPOOL.....	FAGL_LINE_ITEM_BROWSER_F02	267	16
	FAGL_LINE_ITEM_BROWSER_F02	274	16
	FAGL_LINE_ITEM_BROWSER_F02	281	16
	FAGL_LINE_ITEM_BROWSER_F02	288	16

PSX_ITEM-TRANGE.....	FAGL_LINE_ITEM_BROWSER_F03	632	34
	FAGL_LINE_ITEM_BROWSER_F03	705	35
	FAGL_LINE_ITEM_BROWSER_F27	413	86
	FAGL_LINE_ITEM_BROWSER_F27	486	88
PSX_KESS-TRANGE.....	FAGL_LINE_ITEM_BROWSER_F03	631	34
SS_GD-T_SCREEN.....	RKESS_FORMS	183	166
SS_GD-T_SCR_MANAGE.....	RKESS_FORMS	76	164
	RKESS_FORMS	90	164
	RKESS_FORMS	97	164
	RKESS_FORMS	150	165
	RKESS_FORMS	181	166
	RKESS_FORMS	306	168
	RKESS_FORMS	341	168
	RKESS_FORMS	361	169
	RKESS_FORMS	1184	184
	RKESS_FORMS	1203	184
	RKESS_FORMS	1319	186
	RKESS_FORMS	1338	186
SS_GD-T_VARIANT.....	RKESS_FORMS	35	163
	RKESS_FORMS	3585	223
SS_GR_INT->T_FCAT.....	RKESS_FORMS	707	174
	RKESS_FORMS	910	179
	RKESS_FORMS	1523	189
	RKESS_FORMS	2019	198
	RKESS_FORMS	2458	205
	RKESS_FORMS	3241	218
SS_GR_INT->T_SS_EF.....	RKESS_EVENTS	151	158
SS_GR_INT->T_SS_SF.....	RKESS_FORMS	2084	199
SS_GR_INT->T_TRANGE.....	RKESS_FORMS	1014	181
	RKESS_FORMS	3683	225
STH_TEXT.....	FAGL_LINE_ITEM_BROWSER_F13	34	72
ST_FRANGE.....	FAGL_LINE_ITEM_BROWSER_F37	47	98
S_CUST[].....	FAGL_LINE_ITEM_BROWSER_F50	130	108
S_VEND[].....	FAGL_LINE_ITEM_BROWSER_F50	52	106
T_F.....	RKESS_FORMS	2039	198
T_FIELDS.....	RKESS_FORMS	1995	197
T_ROWS.....	RKESS_FORMS	3583	223
T_SCREENS.....	RKESS_FORMS	3391	220
	RKESS_FORMS	3397	220
T_VALUE.....	RKESS_FORMS	3428	221

MODIFY:

		Line	Page
S_PERIOD.....	FAGL_LINE_ITEM_BROWSER_F27	588	89
S_RYEAR.....	FAGL_LINE_ITEM_BROWSER_F27	580	89

DELETE:

		Line	Page
<LT_FIELDS>.....	FAGL_LINE_ITEM_BROWSER_F09	395	70
<RANGE_ITEM>-FRANGE_T.....	FAGL_LINE_ITEM_BROWSER_F03	646	34
GT_PIVB_PARAM.....	FAGL_LINE_ITEM_BROWSER_P03	101	124
LT_FIELD_R.....	FAGL_LINE_ITEM_BROWSER_F27	231	83
	FAGL_LINE_ITEM_BROWSER_F27	234	83
	FAGL_LINE_ITEM_BROWSER_F27	237	83
LT_LTDX.....	FAGL_LINE_ITEM_BROWSER_F02	615	22
LT_LTDXD.....	FAGL_LINE_ITEM_BROWSER_F02	649	22
LT_LTDXT.....	FAGL_LINE_ITEM_BROWSER_F02	681	23

LT_PARAMS.....	FAGL_LINE_ITEM_BROWSER_F20	80	74
LT_SEL.....	FAGL_LINE_ITEM_BROWSER_F27	151	82
	FAGL_LINE_ITEM_BROWSER_F27	159	82
	FAGL_LINE_ITEM_BROWSER_F27	532	88
SS_GD-T_SCR_MANAGE.....	RKESS_FORMS	129	165
SS_GD-T_VARIANT.....	RKESS_FORMS	3401	220
	RKESS_FORMS	3435	221
SS_GR_INT->T_SS_SF.....	RKESS_FORMS	699	174
ST_SELVIEW_INFO.....	FAGL_LINE_ITEM_BROWSER_F09	133	66
	FAGL_LINE_ITEM_BROWSER_F09	209	67
T_FIELDS.....	RKESS_FORMS	1999	197
T_SS_SF.....	RKESS_FORMS	702	174