

RAM CHARAN VANGA

RA2511027010164

Sub ject : DSA

Unit 2, S13, SLO2 - Circular Doubly Linked Lists - Insertion

Algorithm to insert a new node VAL at the beginning

Step 1: IF AVAIL = NULL

Write OVERFLOW

Go to Step 13

[END OF IF]

Step 2: SET NEW_NODE = AVAIL

Step 3: SET AVAIL = AVAIL -> NEXT

Step 4: SET _____ = VAL

Step 5: SET PTR = _____

Step 6: Repeat Step 7 while PTR -> NEXT != _____

Step 7: SET PTR = PTR -> NEXT

[END OF LOOP]

Step 8: SET _____ = NEW_NODE

Step 9: SET _____ = PTR

Step 10: SET _____ = START

Step 11: SET _____ = NEW_NODE

Step 12: SET START = _____

Step 13: EXIT

Answer: Step 4: SET NEW_NODE -> DATA = VAL

Step 5: SET PTR = START

Step 6: while PTR -> NEXT != START

Step 7: SET PTR = PTR -> NEXT

Step 8: SET PTR -> NEXT = NEW_NODE

Step 9: SET NEW_NODE -> PREV = PTR

Step 10: SET NEW_NODE -> NEXT = START

Step 11: SET START -> PREV = NEW_NODE

Step 12: SET START = NEW_NODE

Step 13: EXIT

Algorithm to insert a new node VAL at the end

Step 1: IF AVAIL = NULL

Write OVERFLOW

Go to Step 12

[END OF IF]

Step 2: SET NEW_NODE = AVAIL

Step 3: SET AVAIL = AVAIL -> NEXT

Step 4: SET NEW_NODE -> DATA = _____

Step 5: SET NEW_NODE -> NEXT = _____

Step 6: SET PTR = START

Step 7: Repeat Step 8 while _____ != START

Step 8: SET PTR = PTR -> NEXT

[END OF LOOP]

Step 9: SET PTR -> NEXT = _____

Step 10: SET NEW_NODE -> PREV = _____

Step 11: SET START -> PREV = _____

Step 12: EXIT

Answer: Step 4: SET NEW_NODE -> DATA = VAL

Step 5: SET NEW_NODE -> NEXT = START

Step 6: SET PTR = START

Step 7: while PTR -> NEXT != START

Step 8: SET PTR = PTR -> NEXT

Step 9: SET PTR -> NEXT = NEW_NODE

Step 10: SET NEW_NODE -> PREV = PTR

Step 11: SET START -> PREV = NEW_NODE

Step 12: EXIT