NETWORK DATA STREAMING VASU NEGI

UFID: 8495-3933

PROJECT-3

In order to run these programs on *nix based/MAC system, follow the instructions below:

- * Go to project directory in terminal
- * Type the command in the following way:

python3 file_name

Run: python3 CountMin.py

Functions:

1. def query(self,key):

Returns the minimum size of the flow in all the counters

2. def recording(self,key):

This function records the size of each flow in counters

3. def generate_random_numbers(self):

generate random numbers

4. def get_hash_functions(self, number):

generate hashfunctions with the following function - > (number XOR i) where i is any random number in the self.random nums

5. def execute(self):

Record the sizes of all flows in the counter, query to evaluate estimated sizes of all flows, query for all flows, and calculate the average error of all flows.

Also, Print the (flowid, estimated size, true size) of the 100 largest estimated size

Output: Output/CountMin_output.txt
The output files are in the Output folder.

- 1. 1st line of the output: the average error among all flows
- 2. Next 100 lines: (flowid, estimated size, true size) of the largest estimated size

Run: python3 CounterSketch.py

Functions:

def query(self,key):

Returns the median size of the flow in all the counters

2. def recording(self,key):

This function will record the size of the flow (flowid) in the counter, depending on the MSB of the hash value. If the MSB is 1, we add, else we subtract the packet.

- 3. def generate_random_numbers(self): generate random numbers
- 4. def get_hash_functions(self, number): generate hashfunctions with the following function - > (number XOR i) where i is any random number in the self.random nums
- 5. def execute(self):

Record the sizes of all flows in the counter, query to evaluate estimated sizes of all flows, query for all flows, and calculate the average error of all flows.

Also, Print the (flowid, estimated size, true size) of the 100 largest estimated size

Output: Output/CounterSketch_output.txt The output files are in the Output folder.

- 1. 1st line of the output: the average error among all flows
- 2. Next 100 lines: (flowid, estimated size, true size) of the largest estimated size

Run: python3 ActiveCounter.py

Functions:

1. def increment(self):

This function will increment the counter. The counter is only incremented based on the probability calculated based on the exp part.

If the number n overflows, then right shift n and increment e

2. def probability(self):

This function implements the probability of incrementing the counter, as (1 / 2^c.e)

Output: Output/ActiveCounter_output.txt The output files are in the Output folder.

1. The final value of the active counter in decimal