DMP中报表所用到的SFTP目前采用的是用户密码方式,但是客户现场经常出现主机动态更换密码的情况,所以SFTP需要支持互信的方式,以下三步为配置互信的步骤:

一、应用服务器生成公私钥

在dmp应用服务器上生成公私钥对,如图:

```
[root@localhost ~]# sh-keygen -t rsa
Generating public/private rsa key pain.
Enter file in which to save the key (/root/.ssh/id_rsa):
Enter file in which to save the key (/root/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:

Your identification has been saved in /root/.ssh/id_rsa.

Your public key has been saved in /root/.ssh/id_rsa.pub.

The key fingerprint is:

SHA256:SkSNcAytha2xc25GncSuNIZ/pwAZR9btm+etqeBL47QQ root@localhost.localdomain

The key's randomart inage is:
+---[RSA 2048]----+
| +*Coo |
| .+o+o.o |
| . = EB+.S |
| o to o.o |
| .+ = |
| . 0 + to 0.o |
| .+ = |
| . 0 - soo |
+--- [SHA256]----+
[root@localhost ~]# cd ~/.ssh/
[root@localhost s.sh]# is
id_rsa_id_rsa_pub_known_hosts
```

二、公钥文件拷贝到sftp目标主机

将第一步生成的公钥文件(即id_rsa.pub)内容复制,将内容追加到**目标主机**sftp用户目录下 ~/.ssh/authorized_keys文件中(如无该文件则新建,如果dmp服务器和sftp服务器在一台机器上,也是追加到本机的该文件中)

三、更改基础服务配置文件, 重启基础服务

如图,更改基础服务的配置文件(baisic-service.yml),然后重启基础服务

```
basedir: ../tmp/basic-service-tomcat/
 base-package: cn.newdt.basic.web
sftp:
 ip: 192.168.12.35
 port: 22
 username: root
 privateKey: ~/.ssh/id_rsa 新增这个配置,指定本机私钥的文件路径
mybatis:
 mapper-locations: classpath*:/mybatis/**/**.xml
 type-aliases-package: cn.newdt.basic.domain,cn.newdt.commons.bean
 configuration:
   call-setters-on-nulls: false
   jdbc-type-for-null: null
 savepath: /word
 frontaddress: 192.168.12.35:8960
"basic-service.yml" 72L, 1608C
```