Create a virtual machine

Changing Basic options may reset selections you have made. Review all options prior to creating the virtual machine.

Basics | Disks | Networking | Management | Monitoring | Advanced | Tags | Review + create

Create a virtual machine that runs Linux or Windows. Select an image from Azure marketplace or use your own customized image. Complete the Basics tab then Review + create to provision a virtual machine with default parameters or review each tab for full customization. Learn more

Project details

Select the subscription to manage deployed resources and costs. Use resource groups like folders to organize and manage all your resources.

Subscription * : Simplilearn HOL 100492

Resource group * : (New) RG-1

Create new

Instance details

Virtual machine name * : VM-1

Region * : (US) East US

Deploy to an Azure Extended Zone

Availability options : Availability zone

Zone options :

- (selected) Self-selected zone
  Choose up to 3 availability zones, one VM per zone
- Azure-selected zone (Preview)
  Let Azure assign the best zone for your needs

Using an Azure-selected zone is not supported in region 'East US'.

Availability zone * : Zone 1

You can now select multiple zones. Selecting multiple zones will create one VM per zone. Learn more

Security type : Trusted launch virtual machines

Configure security features

Image * : Windows Server 2025 Datacenter - x64 Gen2

See all images | Configure VM generation

VM architecture : Arm64

x64

Arm64 is not supported with the selected image.

Run with Azure Spot discount ☐

Size * Standard_D2s_v3 - 2 vcpus, 8 GiB memory (Price unavailable)

See all sizes

Item(s) availability based on policy assignment(s) for the selected scope.
az13049-PolicyDefinition (Policy details)

Enable Hibernation ☐

Hibernate is not supported by the size that you have selected. Choose a size that is compatible with Hibernate to enable this feature. Learn more

Administrator account

Username * azureuser

Password * ••••••••••••••

Confirm password * ••••••••••••••

Inbound port rules

Select which virtual machine network ports are accessible from the public internet. You can specify more limited or granular network access on the Networking tab.

Public inbound ports *
- ○ None
- ◉ Allow selected ports

Select inbound ports * HTTP (80), RDP (3389)

This will allow all IP addresses to access your virtual machine. This is only recommended for testing. Use the Advanced controls in the Networking tab to create rules to limit inbound traffic to known IP addresses.

Licensing

Save up to 49% with a license you already own using Azure Hybrid Benefit. Learn more

Would you like to use an existing Windows Server license? ☐

Review Azure hybrid benefit compliance

< Previous | Next : Disks > | Review + create | Give feedback