Stock Transfer

Right now if we have stock in **Chennai Warehouse** and want to move some of it to **Hyderabad Logistics Hub**, there's no way to do that in our system.

Or even within the same warehouse — moving items from **Zone B (Storage)** to **Zone C (Picking)** for faster access — no module for this.

Where to Place It in Navigation

Add it in **two places:**

Place 1 — Inventory module, new tab: Overview | SKU Master | Stock Levels | Batch & Expiry | Movements | Damaged | Adjustments | Cycle Count | **Transfers**

Place 2 — Operations section in sidebar:

- Returns
- Operations (Tasks)
- **Stock Transfer** ← add here
- Invoices

The reason for two places is: Inventory tab shows the transfer record and stock impact, Operations sidebar gives workers quick access to initiate a transfer task.

What the Stock Transfer Page Looks Like

Header stats (3 cards):

- Pending Transfers
- In Progress
- Completed Today

Main table columns:

- Transfer # (TRF-001)
- From Warehouse / Zone / Bin
- To Warehouse / Zone / Bin
- SKU
- Quantity
- Requested By
- Assigned To
- Status
- Created Date
- Actions

Create Transfer form fields:

- Transfer Type — Inter-Warehouse (warehouse to warehouse) OR Intra-Warehouse (zone to zone within same warehouse)
- Source Warehouse (dropdown)
- Source Zone →Source aisle→ Source Rack → Source Bin (cascading dropdowns)
- Destination Warehouse (dropdown — if inter-warehouse)
- Destination Zone → Destination Rack → Destination Bin
- SKU (dropdown)
- Available Quantity (auto-shown after SKU selected)
- Transfer Quantity
- Reason (Rebalancing / Replenishment / Damaged Relocation / Customer Order / Other)
- Priority
- Assign To (worker)
- Notes

Status flow: Requested → Approved → In Transit → Completed

When completed — system deducts stock from source bin and adds to destination bin automatically.

Admin Vs Manager for Stock Transfer

Admin — can initiate both inter-warehouse and intra-warehouse transfers across all locations. **Manager** — can only initiate intra-warehouse transfers within their own warehouse. For inter-warehouse transfers, they can request but Admin must approve.