

# **Programming examples on POSIX Threads**

**Chandravva Hebbi** 

Department of Computer Science

#### Slides Credits for all PPTs of this course



- The slides/diagrams in this course are an adaptation,
   combination, and enhancement of material from the following resources and persons:
- Slides of Operating System Concepts, Abraham Silberschatz, Peter Baer Galvin, Greg Gagne - 9<sup>th</sup> edition 2013 and some slides from 10<sup>th</sup> edition 2018
- 2. Some conceptual text and diagram from Operating Systems Internals and Design Principles, William Stallings, 9<sup>th</sup> edition 2018
- 3. Some presentation transcripts from A. Frank P. Weisberg
- 4. Some conceptual text from Operating Systems: Three Easy Pieces, Remzi Arpaci-Dusseau, Andrea Arpaci Dusseau



Programming examples on POSIX Threads

#### **Chandravva Hebbi**

**Department of Computer Science** 

#### **Thread functions**

## PES UNIVERSITY ONLINE

#### **Thread creation**

```
#include<pthread.h>
int pthread_create(pthread_t *thread, const pthread_attr_t *attr, void
*(*start_routine)(void*), void *arg);
```

#### **Thread Completion**

```
int pthread_join(pthread_t thread, void **value_ptr);
```

#### Locks

```
int pthread_mutex_lock(pthread_mutex_t *mutex);
int pthread_mutex_unlock(pthread_mutex_t *mutex);
```

#### **Thread functions**



When you have a region of code that is a critical section, and thus needs to be protected to ensure correct operation, locks are quite useful.

#### Example:

```
pthread_mutex_t lock;
pthread_mutex_lock(&lock);
x = x + 1; // or whatever your critical section is
pthread_mutex_unlock(&lock);
```

#### **Thread functions**



#### **Condition Variables**

- The other major component of any threads library, and certainly the case with POSIX threads, is the presence of a condition variable.
- Condition variables are useful when some kind of signaling must take place between threads, if one thread is waiting for another to do something before it can continue.

Two primary routines are used by programs wishing to interact in this way: int pthread\_cond\_wait(pthread\_cond\_t \*cond, pthread\_mutex\_t \*mutex); int pthread\_cond\_signal(pthread\_cond\_t \*cond);

#### **Programming examples on POSIX Threads**

#### Demonstration of,

1. Write program to find sum of N natural numbers. Thread1 computes sum of even numbers(evensum) and thread 2 computes the sum of odd numbers (oddsum) and main thread computes the total sum.

Examample: N=10

Even numbers=2,4,6,8,10

Odd numbers=1,3,5,7,9

Thread 1 result, Evensum=30

Thread 2 result, Oddsum=25

Main thread result=oddsum + evensum=30+25=55.



#### **Programming examples on POSIX Threads**

- 2. Write a program to demonstrate producer consumer problem.
- 3. Write a program to demonstrate the dining philosopher's problem
- 4. Write a program create 2 threads, thread 1 prints lower case characters and thread 2 prints upper case character alternatively.

Note: synchronize the two threads using wait and signal

Expected output: aAbBcCdD.....zZ





#### **THANK YOU**

Chandravva Hebbi
Department of Computer Science Engineering
chandravvahebbi@pes.edu