

**This version of GitHub Enterprise was discontinued on 2023-03-15.** No patch releases will be made, even for critical security issues. For better performance, improved security, and new features, <u>upgrade to the latest version of GitHub Enterprise</u>. For help with the upgrade, <u>contact GitHub Enterprise support</u>.

# Updating your GitHub access credentials

#### In this article

Requesting a new password

Changing an existing password

Updating your access tokens

Updating your SSH keys

Resetting API tokens

Preventing unauthorized access

GitHub Enterprise Server credentials include not only your password, but also the access tokens, SSH keys, and application API tokens you use to communicate with GitHub Enterprise Server. Should you have the need, you can reset all of these access credentials yourself.


# Requesting a new password &

- 1 To request a new password, visit https://HOSTNAME/password\_reset .
- 2 Enter the email address associated with your account on your GitHub Enterprise Server instance, then click **Send password reset email.** The email will be sent to the backup email address if you have one configured.
- 3 We'll email you a link that will allow you to reset your password. You must click on this link within 3 hours of receiving the email. If you didn't receive an email from us, make sure to check your spam folder.
- 4 If you have enabled two-factor authentication, you will be prompted for your 2FA credentials:
  - Type your authentication code or one of your recovery codes and click **Verify**.
    - If you have added a security key to your account, click Use security key instead of typing an authentication code.
- 5 In the text field under **Password**, type a new password. Then, in the text field under **Confirm password**, type the password again.
- 6 Click Change password. For help creating a strong password, see "<u>Creating a strong password</u>."

To avoid losing your password in the future, we suggest using a secure password manager, like <u>LastPass</u> or <u>1Password</u>.

# Changing an existing password @

- 1 Sign in (https://HOSTNAME/login) to GitHub Enterprise Server.
- 2 In the upper-right corner of any page, click your profile photo, then click **Settings**.



- 3 In the left sidebar, click **Account security**.
- 4 Under "Change password", type your old password, a strong new password, and confirm your new password. For help creating a strong password, see "Creating a strong password"
- 5 Click **Update password**.

For greater security, enable two-factor authentication in addition to changing your password. See <u>About two-factor authentication</u> for more details.

# Updating your access tokens &

See "Reviewing and revoking authorization of GitHub Apps" for instructions on reviewing and deleting access tokens. To generate new access tokens, see "Managing your personal access tokens."

If you have reset your account password and would also like to trigger a sign-out from the GitHub Mobile app, you can revoke your authorization of the "GitHub iOS" or "GitHub Android" OAuth app. This will sign out all instances of the GitHub Mobile app associated with your account. For additional information, see "Reviewing and revoking authorization of GitHub Apps."

## Updating your SSH keys ∂

See "Reviewing your SSH keys" for instructions on reviewing and deleting SSH keys. To generate and add new SSH keys, see "Connecting to GitHub with SSH."

## Resetting API tokens &

If you have any applications registered with GitHub Enterprise Server, you'll want to reset their OAuth tokens. For more information, see the "Apps" endpoint.

## Preventing unauthorized access &

For more tips on securing your account and preventing unauthorized access, see "Preventing unauthorized access."

#### Legal

© 2023 GitHub, Inc. <u>Terms</u> <u>Privacy</u> <u>Status</u> <u>Pricing</u> <u>Expert services</u> <u>Blog</u>