



# **Enabling unified contributions for your enterprise**

In this article

About unified contributions

Enabling unified contributions

You can allow users to include anonymized contribution counts for their work on your GitHub Enterprise Server instance in their contribution graphs on GitHub.com.

#### Who can use this feature

Enterprise owners can enable unified contributions between your GitHub Enterprise Server instance and GitHub.com.

## About unified contributions &

As an enterprise owner, you can allow end users to send anonymized contribution counts for their work from your GitHub Enterprise Server instance to their GitHub.com contribution graph.

After you enable unified contributions, before individual users can send contribution counts from your GitHub Enterprise Server instance to GitHub.com, each user must also connect their user account on GitHub Enterprise Server with a personal account on GitHub.com. For more information, see "Sending enterprise contributions to your GitHub.com profile."

GitHub Enterprise Server sends updates hourly.

If the enterprise owner disables the functionality or individual users opt out of the connection, the contribution counts from GitHub Enterprise Server will be deleted on GitHub.com. If the user reconnects their profiles after disabling them, the contribution counts for the past 90 days are restored.

GitHub Enterprise Server **only** sends the contribution count and source (GitHub Enterprise Server) for connected users. It does not send any information about the contribution or how it was made.

## **Enabling unified contributions** &

Before enabling unified contributions on your GitHub Enterprise Server instance, you must enable GitHub Connect. For more information, see "Managing GitHub Connect."

- 1 Sign in to GitHub Enterprise Server and GitHub.com.
- 2 From an administrative account on GitHub Enterprise Server, in the upper-right corner of any page, click  $\mathcal{Q}$ .
- 3 If you're not already on the "Site admin" page, in the upper-left corner, click **Site**

## admin.

- 4 In the left sidebar, click **Enterprise overview**.
- 5 In the enterprise account sidebar, click ct GitHub Connect.
- 6 To the right of "Unified contributions", click **Enable**.



Sign in to the GitHub Enterprise Server site to receive further instructions.

When you request access, we may redirect you to the GitHub Enterprise Server site to check your current terms of service.

## Legal

© 2023 GitHub, Inc. <u>Terms</u> <u>Privacy</u> <u>Status</u> <u>Pricing</u> <u>Expert services</u> <u>Blog</u>