

# Roles in an enterprise

In this article

About roles in an enterprise

Enterprise owners

Enterprise members

Everyone in an enterprise is a member of the enterprise. To control access to your enterprise's settings and data, you can assign different roles to members of your enterprise.

#### About roles in an enterprise &

Everyone in an enterprise is a member of the enterprise. You can also assign administrative roles to members of your enterprise. Each administrator role maps to business functions and provides permissions to do specific tasks within the enterprise.

Enterprise owners can see all of the members and outside collaborators for every organization owned by the enterprise.

For more information about adding people to your enterprise, see "<u>Identity and access</u> management".

## **Enterprise owners** $\mathscr P$

Enterprise owners have complete control over the enterprise and can take every action, including:

- Managing administrators
- Managing organizations in the enterprise
- · Managing enterprise settings
- Enforcing policy across organizations

Enterprise owners do not have access to organization settings or content by default. To gain access, enterprise owners can join any organization owned by their enterprise. For more information, see "Managing your role in an organization owned by your enterprise."

Owners of organizations in your enterprise do not have access to the enterprise itself unless you make them enterprise owners.

Even if an enterprise owner has a role in multiple organizations, they will consume a single license. As a best practice, we recommend making only a few people in your company enterprise owners, to reduce the risk to your business. For more information about accounts that consume a license for your GitHub Enterprise Server instance, see "About per-user pricing."

## Enterprise members &

Members of organizations owned by your enterprise are also automatically members of the enterprise. Members can collaborate in organizations and may be organization owners, but members cannot access or configure enterprise settings.

People in your enterprise may have different levels of access to the various organizations owned by your enterprise and to repositories within those organizations. You can view the resources that each person has access to. For more information, see "Viewing people in your enterprise."

For more information about organization-level permissions, see "Roles in an organization."

People with outside collaborator access to repositories owned by your organization are also listed in your enterprise's People tab, but are not enterprise members and do not have any access to the enterprise. For more information about outside collaborators, see "Roles in an organization."

#### Legal

© 2023 GitHub, Inc. <u>Terms Privacy</u> <u>Status Pricing Expert services Blog</u>