



This version of GitHub Enterprise was discontinued on 2023-03-15. No patch releases will be made, even for critical security issues. For better performance, improved security, and new features, <u>upgrade to the latest version of GitHub Enterprise</u>. For help with the upgrade, <u>contact GitHub Enterprise support</u>.

Viewing people's roles in an organization

In this article

View organization roles

View enterprise owners and their roles in an organization


You can view a list of the people in your organization and filter by their role. For more information on organization roles, see "Roles in an organization."

Who can use this feature

Organization members can see people's roles in the organization.

View organization roles ∂


1 In the top right corner of GitHub Enterprise Server, click your profile photo, then click **Your organizations**.



- 2 Click the name of your organization.
- 3 Under your organization name, click ∧ People.



4 To filter the list by role, select the **Role** dropdown menu and click a role.



View enterprise owners and their roles in an organization *∂*

If your organization is managed by an enterprise account, then you can view the enterprise owners who manage billing settings and policies for all of your enterprise's organizations. For more information about enterprise accounts, see "Types of GitHub accounts."

You can also view whether an enterprise owner has a specific role in the organization. Enterprise owners can also be an organization member, any other organization role, or be un-affiliated with the organization.

Note: If you're an organization owner, you can also invite an enterprise owner to have a role in the organization. If an enterprise owner accepts the invitation, a seat or license in the organization is used from the available licenses for your enterprise. For more information about how licensing works, see "Roles in an enterprise."


Enterprise role	Organization role	Organization access or impact	
Enterprise owner	Un-affiliated or no official organization role	Cannot access organization content or repositories but manages enterprise settings and policies that impact your organization.	
Enterprise owner	Organization owner	Able to configure organization settings and manage access to the organization's resources through teams, etc.	
Enterprise owner	Organization member	Able to access	

and content, such as repositories, without access to the organization's settings.

To review all roles in an organization, see "Roles in an organization."

For more information about the enterprise owner role, see "Roles in an enterprise."

1 In the top right corner of GitHub Enterprise Server, click your profile photo, then click **Your organizations**.



- 2 Click the name of your organization.
- 3 Under your organization name, click ∧ People.



4 In the left sidebar, under "Enterprise permissions", click Enterprise owners.

Legal

© 2023 GitHub, Inc. Terms Privacy Status Pricing Expert services Blog