



This version of GitHub Enterprise was discontinued on 2023-03-15. No patch releases will be made, even for critical security issues. For better performance, improved security, and new features, <u>upgrade to the latest version of GitHub Enterprise</u>. For help with the upgrade, <u>contact GitHub Enterprise support</u>.

Inviting people to manage your enterprise

In this article

About users who can manage your enterprise account

Adding an enterprise administrator to your enterprise account

Removing an enterprise administrator from your enterprise account

You can add and remove enterprise owners for your enterprise account.

Who can use this feature

Enterprise owners can add additional enterprise administrators.

About users who can manage your enterprise account ${\mathscr O}$


Enterprise owners can see all of the members and outside collaborators for every organization owned by the enterprise. For more information, see "Roles in an enterprise."

If you want to manage owners and billing managers for an enterprise account on GitHub.com, see "<u>Inviting people to manage your enterprise</u>" in the GitHub Enterprise Cloud documentation.

Tip: For more information on managing users within an organization owned by your enterprise account, see "<u>Managing membership in your organization</u>" and "<u>Managing people's access to your organization</u> with roles."

Adding an enterprise administrator to your enterprise account $\mathscr O$

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.




- 2 In the enterprise account sidebar, click A **People**.
- 3 Under "A People", click **Administrators**.
- 4 Above the list of administrators, click **Add owner**.
- 5 Type the username, full name, or email address of the person you want to invite to become an enterprise administrator, then select the appropriate person from the results.
- 6 Click Add.

Removing an enterprise administrator from your enterprise account ${\mathscr O}$

Only enterprise owners can remove other enterprise administrators from the enterprise account.

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.



- 2 In the enterprise account sidebar, click A **People**.
- 3 Under "A People", click **Administrators**.
- 4 Next to the username of the person you'd like to remove, select the & dropdown menu, then click **Remove owner**.
- **5** Read the confirmation, then click **Remove owner**.

Legal

© 2023 GitHub, Inc. <u>Terms Privacy Status Pricing Expert services Blog</u>