



# Using labels with self-hosted runners

#### **Host your own runners**

5 of 8 in learning path

Next: Using self-hosted runners in a workflow

#### In this article

Creating a custom label

Assigning a label to a self-hosted runner

Removing a custom label from a self-hosted runner

Programmatically assign labels

You can use labels to organize your self-hosted runners based on their characteristics.

**Note:** GitHub-hosted runners are not currently supported on GitHub Enterprise Server. You can see more information about planned future support on the <u>GitHub public roadmap</u>.

For information on how to use labels to route jobs to specific types of self-hosted runners, see "<u>Using self-hosted runners in a workflow</u>." You can also route jobs to runners in a specific group. For more information, see "<u>Choosing the runner for a job</u>."

A self-hosted runner can be located in either your repository, organization, or enterprise settings on your GitHub Enterprise Server instance. To manage a self-hosted runner, you must have the following permissions, depending on where the self-hosted runner was added:

- **User repository**: You must be the repository owner.
- Organization: You must be an organization owner.
- **Organization repository**: You must be an organization owner, or have admin access to the repository.
- **Enterprise**: You must be a GitHub Enterprise site administrator.

### Creating a custom label @

You can create custom labels for runners at the repository, organization, and enterprise levels.

- Creating a custom label for a repository runner
- Creating a custom label for an organization runner
- Creating a custom label for an enterprise runner

Note: Labels are case-insensitive.

### Creating a custom label for a repository runner &

- 1 Navigate to the main page of the repository where your self-hosted runner group is registered.
- 2 Click 龄 Settings.
- 3 In the left sidebar, click (•) Actions, then click Runners.
- 4 In the list of runners, click on the name of the runner you'd like to configure.
- 5 In the "Labels" section, click 袋.
- 6 In the "Find or create a label" field, type the name of your new label and click

  Create new label. The custom label is created and assigned to the self-hosted runner. Custom labels can be removed from self-hosted runners, but they currently can't be manually deleted. Any unused labels that are not assigned to a runner will be automatically deleted within 24 hours.


#### Creating a custom label for an organization runner @

- 1 Navigate to the main page of the organization where your self-hosted runner group is registered.
- 2 Click 龄 Settings.
- 3 In the left sidebar, click Actions, then click Runners.
- 4 In the list of runners, click on the name of the runner you'd like to configure.
- 5 In the "Labels" section, click 袋.
- 6 In the "Find or create a label" field, type the name of your new label and click

  Create new label. The custom label is created and assigned to the self-hosted runner. Custom labels can be removed from self-hosted runners, but they currently can't be manually deleted. Any unused labels that are not assigned to a runner will be automatically deleted within 24 hours.

#### Creating a custom label for an enterprise runner &

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.



- 2 In the enterprise account sidebar, click 4 Policies.
- 3 Under "কু Policies", click Actions.
- 4 Click the Runners tab.
- 5 In the list of runners, click on the name of the runner you'd like to configure.
- 6 In the "Labels" section, click සු.
- In the "Find or create a label" field, type the name of your new label and click

  Create new label. The custom label is created and assigned to the self-hosted runner. Custom labels can be removed from self-hosted runners, but they currently can't be manually deleted. Any unused labels that are not assigned to a runner will be automatically deleted within 24 hours.

## Assigning a label to a self-hosted runner @

You can assign labels to self-hosted runners at the repository, organization, and enterprise levels.

- Assigning a label to a repository runner
- Assigning a label to an organization runner
- Assigning a label to an enterprise runner

### Assigning a label to a repository runner $\mathscr P$

- 1 Navigate to the main page of the repository where your self-hosted runner group is registered.
- 2 Click 袋 Settings.
- 3 In the left sidebar, click ⊙ Actions, then click Runners.


- 4 In the "Labels" section, click 錄.
- 5 To assign a label to your self-hosted runner, in the "Find or create a label" field, click the label.

### Assigning a label to an organization runner &

- 1 Navigate to the main page of the organization where your self-hosted runner group is registered.
- 2 Click 龄 Settings.
- 3 In the left sidebar, click Actions, then click Runners.
- 4 In the "Labels" section, click 袋.
- 5 To assign a label to your self-hosted runner, in the "Find or create a label" field, click the label.

#### Assigning a label to an enterprise runner &

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.



- 2 In the enterprise account sidebar, click **policies**.
- 3 Under "本 Policies", click **Actions**.
- 4 Click the **Runners** tab.
- **5** In the list of runners, click on the name of the runner you'd like to configure.
- 6 In the "Labels" section, click සු.

7 To assign a label to your self-hosted runner, in the "Find or create a label" field, click the label.

## Removing a custom label from a self-hosted runner



You can remove custom labels from self-hosted runners at the repository, organization, and enterprise levels.

- Removing a custom label from a repository runner
- Removing a custom label from an organization runner
- Removing a custom label from an enterprise runner

### Removing a custom label from a repository runner &


- 1 Navigate to the main page of the repository where your self-hosted runner group is registered.
- 2 Click 龄 Settings.
- 3 In the left sidebar, click Actions, then click Runners.
- 4 In the "Labels" section, click 袋.
- 5 In the "Find or create a label" field, assigned labels are marked with the ✓ icon. Click on a marked label to unassign it from your self-hosted runner.

### Removing a custom label from an organization runner &

- 1 Navigate to the main page of the organization where your self-hosted runner group is registered.
- 2 Click & Settings.
- 3 In the left sidebar, click Actions, then click Runners.
- 4 In the "Labels" section, click සු.
- 5 In the "Find or create a label" field, assigned labels are marked with the ✓ icon. Click on a marked label to unassign it from your self-hosted runner.

#### Removing a custom label from an enterprise runner &

1 In the top-right corner of GitHub Enterprise Server, click your profile photo, then click **Enterprise settings**.



- 2 In the enterprise account sidebar, click & Policies.
- 3 Under "কু Policies", click **Actions**.
- 4 Click the Runners tab.
- 5 In the list of runners, click on the name of the runner you'd like to configure.
- 6 In the "Labels" section, click සු.
- In the "Find or create a label" field, assigned labels are marked with the ✓ icon. Click on a marked label to unassign it from your self-hosted runner.

### Programmatically assign labels &

You can programmatically assign labels to a self-hosted runner after the runner is created, or during its initial configuration.

- To programmatically assign labels to an existing self-hosted runner, you must use the REST API. For more information, see the "Self-hosted runners" REST API.
- To programmatically assign labels to a self-hosted runner during the initial runner configuration, you can pass label names to the config script using the labels parameter.

**Note:** You cannot use the config script to assign labels to an existing self-hosted runner.

For example, this command assigns a label named gpu when configuring a new self-hosted runner:

```
./config.sh \ --url \ < REPOSITORY\_URL > \ --token \ < REGISTRATION\_TOKEN > \ --labels \ gpu
```

The label is created if it does not already exist. You can also use this approach to assign the default labels to runners, such as x64 or linux. When default labels are

assigned using the configuration script, GitHub Actions accepts them as given and does not validate that the runner is actually using that operating system or architecture.

You can use comma separation to assign multiple labels. For example:

./config.sh --url <REPOSITORY\_URL> --token <REGISTRATION\_TOKEN> --labels gpu,x64,linux

**Note:** If you replace an existing runner, then you must reassign any custom labels.

Previous

Next

Using a proxy server with self-hosted runners

Using self-hosted runners in a workflow

#### Legal

© 2023 GitHub, Inc. <u>Terms</u> <u>Privacy</u> <u>Status</u> <u>Pricing</u> <u>Expert services</u> <u>Blog</u>