



## Removing an outside collaborator from an organization repository

### In this article

Removing outside collaborators from all repositories in an organization

Removing an outside collaborator from a particular repository in an organization

Owners and repository admins can remove an outside collaborator's access to a repository.


#### Warning:

- When removing an outside collaborator from a private repository, the paid license count does not automatically downgrade. To pay for fewer licenses after removing users from your organization, follow the steps in "Downgrading your account's plan."
- · You are responsible for ensuring that people who have lost access to a repository delete any confidential information or intellectual property.

While forks of private repositories are deleted when a collaborator is removed, the person will still retain any local clones of your repository.

## Removing outside collaborators from all repositories in an organization @


1 In the top right corner of GitHub.com, click your profile photo, then click [] Your organizations.



- 2 Click the name of your organization.
- 3 Under your organization name, click ∧ People.



- 4 In the "Organization permissions" sidebar, click **Outside collaborators**.
- **5** Select the outside collaborator or outside collaborators you'd like to remove from the organization.



6 Above the list of outside collaborators, select the **X collaborators selected...** dropdown menu, and click **Remove from all repositories**.




Review the outside collaborator or outside collaborators who will be removed from the organization, then click Remove outside collaborators.

# Removing an outside collaborator from a particular repository in an organization $\mathscr{D}$

If you only want to remove an outside collaborator from certain repositories in your organization, you can remove this person's access to one specific repository at a time.

1 In the top right corner of GitHub.com, click your profile photo, then click Your organizations.



- 2 Click the name of your organization.
- 3 Under your organization name, click ∧ People.



- 4 In the "Organization permissions" sidebar, click **Outside collaborators**.
- 5 To the right of the username of the person you want to remove, select the & dropdown menu, and click **Manage**.



- **6** To the right of the repository that you want to remove the outside collaborator from, click **Manage access**.
- **7** To completely remove the outside collaborator's access to the repository, in the upper right corner, click **Remove access to this repository**.
- 8 To confirm, click Remove access.

You can also remove an outside collaborator from a repository in the access overview in your repository settings. For more information, see "Managing teams and people with access to your repository."

## Legal

© 2023 GitHub, Inc. <u>Terms Privacy</u> <u>Status Pricing Expert services Blog</u>