



Managing custom repository roles for an organization

In this article

About custom repository roles

Creating a repository role

Editing a repository role

Deleting a repository role

You can create, edit, or delete custom repository roles for your organization.

Who can use this feature

Organization owners can manage custom repository roles.

Note: Only organizations that use GitHub Enterprise Cloud can create custom repository roles. For more information about how you can try GitHub Enterprise Cloud for free, see "Setting up a trial of GitHub Enterprise Cloud."


About custom repository roles *₽*

A custom repository role is a configurable set of permissions with a custom name you choose. For more information, see "About custom repository roles."

Creating a repository role ₽

To create a new repository role, you add permissions to an inherited role and give the custom role a name.


1 In the top right corner of GitHub.com, click your profile photo, then click Your organizations.




- 2 Under "Organizations", next to the name of your organization, click **Settings**.
- 3 In the "Access" section of the sidebar, click 🖹 Repository roles.
- 4 Scroll to the "Custom roles" section, then click Create a Role.
- 5 Under "Name", type the name of your repository role.
- **6** Under "Description", type a description of your repository role.
- 1 Under "Choose a role to inherit", select the role you want to inherit.
- 8 Under "Add Permissions", select the dropdown menu and click the permissions you want your custom role to include.
- 9 Click Create role.

Editing a repository role &

1 In the top right corner of GitHub.com, click your profile photo, then click **Your profile**.




2 In the top right corner of GitHub.com, click your profile photo, then click **Your organizations**.



3 Under your organization name, click & **Settings**. If you cannot see the "Settings" tab, select the ··· dropdown menu, then click **Settings**.



- 4 Under "Organizations", next to the name of your organization, click **Settings**.
- 5 In the "Access" section of the sidebar, click 🖺 Repository roles.
- 6 To the right of the role you want to edit, click ..., then click **Edit**.




7 Edit, then click **Update role**.


Deleting a repository role *∂*

If you delete an existing repository role, all pending invitations, teams, and users with the custom role will be reassigned to the organization's base permissions.

1 In the top right corner of GitHub.com, click your profile photo, then click **Your profile**.




2 In the top right corner of GitHub.com, click your profile photo, then click **Your organizations**.



3 Under your organization name, click & **Settings**. If you cannot see the "Settings" tab, select the ··· dropdown menu, then click **Settings**.



- 4 Under "Organizations", next to the name of your organization, click **Settings**.
- 5 In the "Access" section of the sidebar, click 🖹 Repository roles.
- 6 To the right of the role you want to delete, click ..., then click **Delete**.



7 Review changes for the role you want to remove, then click **Delete role**.

Legal