Core_SW1:

interface range fa0/1, fa0/2
channel-group 1 mode active
exit
interface port-channel 1
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98
exit

interface range fa0/3, fa0/4
channel-group 2 mode active
exit
interface port-channel 2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98
exit

interface range fa0/5, fa0/6
channel-group 3 mode active
exit
interface port-channel 3
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98
exit

SW2:

interface range fa0/1, fa0/2

```
channel-group 1 mode active
```

exit

interface port-channel 1

switchport trunk encapsulation dot1q

switchport mode trunk

switchport trunk allowed vlan 10,20,30,40,98

exit

interface range fa0/3, fa0/4

channel-group 4 mode active

exit

interface port-channel 4

switchport trunk encapsulation dot1q

switchport mode trunk

switchport trunk allowed vlan 10,20,30,40,98

exit

Core_SW2:

interface range fa0/1, fa0/2

channel-group 5 mode active

exit

interface port-channel 5

switchport trunk encapsulation dot1q

switchport mode trunk

switchport trunk allowed vlan 10,20,30,40,98

exit

interface range fa0/3, fa0/4

channel-group 4 mode active

exit

interface port-channel 4

switchport trunk encapsulation dot1q switchport mode trunk switchport trunk allowed vlan 10,20,30,40,98 exit

interface range fa0/5, fa0/6
channel-group 3 mode active
exit
interface port-channel 3
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98
exit

SW3:

interface range fa0/1, fa0/2
channel-group 5 mode active
exit
interface port-channel 5
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98
exit

channel-group 2 mode active
exit
interface port-channel 2
switchport trunk encapsulation dot1q
switchport mode trunk
switchport trunk allowed vlan 10,20,30,40,98

interface range fa0/3, fa0/4