

Launch an EC2 instance (Linux and Windows) along with a web server. Then, create an EBS volume of 5 GB, attach it to an EC2 machine (Linux and Windows), and take a snapshot

EC2 instance created & EBS volume attached.

The screenshot shows the AWS Management Console. At the top, there's a list of EC2 instances: 'webservers-linux' (i-0207751be04951756) and 'Webserver-win' (i-0b38327f20e869f7b), both in 'Running' state. Below this, the details for instance 'i-0207751be04951756 (webservers-linux)' are shown. The 'Root device details' section indicates the root device is '/dev/sda1' of type 'EBS'. The 'Block devices' section shows a table of attached EBS volumes:

Volume ID	Device name	Volume size (GiB)	Volume State
vol-08d1b7f54a654e2be	/dev/sda1	8	In-use
vol-0613abd47a13baf01	/dev/sdd	6	In-use
vol-0dc13dbbe70e63304	/dev/sdn	6	In-use

EBS volume mounted:

```
ubuntu@ip-172-31-13-221:~$ lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0        7:0      0   27.6M 1 loop /snap/amazon-ssm-agent/11797
loop1        7:1      0   50.8M 1 loop /snap/snapd/25202
loop2        7:2      0   73.9M 1 loop /snap/core22/2133
loop3        7:3      0   27.9M 1 loop /snap/amazon-ssm-agent/12497
nvme0n1      259:0    0     8G  0 disk 
├─nvme0n1p1  259:1    0     7G  0 part /
├─nvme0n1p14 259:2    0     4M  0 part 
├─nvme0n1p15 259:3    0   106M  0 part /boot/efi
└─nvme0n1p16 259:4    0   913M  0 part /boot
ubuntu@ip-172-31-13-221:~$ lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0        7:0      0   27.6M 1 loop /snap/amazon-ssm-agent/11797
loop1        7:1      0   50.8M 1 loop /snap/snapd/25202
loop2        7:2      0   73.9M 1 loop /snap/core22/2133
loop3        7:3      0   27.9M 1 loop /snap/amazon-ssm-agent/12497
nvme0n1      259:0    0     8G  0 disk 
├─nvme0n1p1  259:1    0     7G  0 part /
├─nvme0n1p14 259:2    0     4M  0 part 
├─nvme0n1p15 259:3    0   106M  0 part /boot/efi
└─nvme0n1p16 259:4    0   913M  0 part /boot
nvme1n1      259:5    0     6G  0 disk 
ubuntu@ip-172-31-13-221:~$ sudo fdisk /dev/xvdb
```

```

ubuntu@ip-172-31-13-221:~$ sudo mkdir /mnt/data
ubuntu@ip-172-31-13-221:~$ sudo mount /dev/nvme1n1p3 /mnt/data
ubuntu@ip-172-31-13-221:~$ lsblk

```

NAME	MAJ:MIN	RM	SIZE	RO	TYPE	MOUNTPOINTS
loop0	7:0	0	27.6M	1	loop	/snap/amazon-ssm-agent/11797
loop1	7:1	0	50.8M	1	loop	/snap/snapd/25202
loop2	7:2	0	73.9M	1	loop	/snap/core22/2133
loop3	7:3	0	27.9M	1	loop	/snap/amazon-ssm-agent/12497
nvme0n1	259:0	0	8G	0	disk	
└─nvme0n1p1	259:1	0	7G	0	part	/
└─nvme0n1p14	259:2	0	4M	0	part	
└─nvme0n1p15	259:3	0	106M	0	part	/boot/efi
└─nvme0n1p16	259:4	0	913M	0	part	/boot
nvme1n1	259:5	0	6G	0	disk	
└─nvme1n1p3	259:6	0	6G	0	part	/mnt/data

```

ubuntu@ip-172-31-13-221:~$

```

Snapshot created and attached new volume:

snap-0bbc5354a6589ad93

Details

Snapshot ID

snap-0bbc5354a6589ad93

Owner

460783431859

Description

Test-Linux

▼ Source volume

Volume ID

vol-0dc13dbbe70e63304

Volume size

6 GiB

▼ Encryption

Encryption

Not encrypted

KMS key ID

-

Snapshot settings

Storage tier

Tags

▼ Snapshot Lock - new

```

ubuntu@ip-172-31-13-221:~$ lsblk

```

NAME	MAJ:MIN	RM	SIZE	RO	TYPE	MOUNTPOINTS
loop0	7:0	0	27.6M	1	loop	/snap/amazon-ssm-agent/11797
loop1	7:1	0	50.8M	1	loop	/snap/snapd/25202
loop2	7:2	0	73.9M	1	loop	/snap/core22/2133
loop3	7:3	0	27.9M	1	loop	/snap/amazon-ssm-agent/12497
nvme0n1	259:0	0	8G	0	disk	
└─nvme0n1p1	259:1	0	7G	0	part	/
└─nvme0n1p14	259:2	0	4M	0	part	
└─nvme0n1p15	259:3	0	106M	0	part	/boot/efi
└─nvme0n1p16	259:4	0	913M	0	part	/boot
nvme1n1	259:5	0	6G	0	disk	
└─nvme1n1p3	259:6	0	6G	0	part	/mnt/data
nvme2n1	259:7	0	6G	0	disk	
└─nvme2n1p3	259:8	0	6G	0	part	



```

ubuntu@ip-172-31-13-221:~$

```

Window server volume attach

EC2 launched with unallocated disk:



Disk allocated with D drive:

Attached with new drive:

i-0b38327f20e869f7b (Webserver-win)

Root device name  /dev/sda1	Root device type EBS
--	--------------------------------

▼ **Block devices**

	Volume ID	Device name	Volume size (GiB)	Volume State
☐	vol-0babfe32c1bb4bd40	/dev/sda1	30	 In-use
☐	vol-08eb8793441f0cf26	xvdd	5	 In-use
☒	vol-0890f67b5a01e251c	xvdf	5	 In-use

Snapshot disk allocated:

65.2.129.226 - Remote Desktop Connection

File Action View Help

Disk ###	St	Volume	Layout	Type	File System	Status	Capacity	Free Sp...	% Free
Disk 0	On	(C:)	Simple	Basic	NTFS	Healthy (S...	30.00 GB	9.60 GB	32 %
Disk 1	Of	New Volume (...)	Simple	Basic	NTFS	Healthy (P...	5.00 GB	4.97 GB	99 %
		New Volume (E:)	Simple	Basic	NTFS	Healthy (A...	5.00 GB	4.97 GB	99 %

DISKPART> list

Volume ###

* Volume 0

DISKPART> list

Volume ###

* Volume 0

DISKPART> list

Disk 1

Basic

5.00 GB

Online

New Volume (D:)

5.00 GB NTFS

Healthy (Primary Partition)