eXosip2 SUBSCRIBE and outgoing subscriptions

SIP messages and call control API

Enumerations

```
enum eXosip ss {
       EXOSIP SUBCRSTATE UNKNOWN,
       EXOSIP SUBCRSTATE PENDING.
       EXOSIP SUBCRSTATE ACTIVE,
       EXOSIP SUBCRSTATE TERMINATED
enum eXosip ss reason {
       DEACTIVATED,
       PROBATION.
       REJECTED,
       TIMEOUT,
       GIVEUP,
       NORESOURCE
enum
      eXosip ss status {
       EXOSIP NOTIFY UNKNOWN,
       EXOSIP NOTIFY PENDING,
       EXOSIP NOTIFY ONLINE,
       EXOSIP NOTIFY BUSY,
       EXOSIP NOTIFY BERIGHTBACK,
       EXOSIP NOTIFY AWAY,
       EXOSIP NOTIFY ONTHEPHONE,
       EXOSIP NOTIFY OUTTOLUNCH,
       EXOSIP_NOTIFY CLOSED
```

Functions

```
int eXosip_subscribe_build_initial_request (struct eXosip_t *excontext, osip_message_t **subscribe, const char *to, const char *from, const char *route, const char *event, int expires)
int eXosip_subscribe_send_initial_request (struct eXosip_t *excontext, osip_message_t *subscribe)
int eXosip_subscribe_build_refresh_request (struct eXosip_t *excontext, int did, osip_message_t **sub)
int eXosip_subscribe_send_refresh_request (struct eXosip_t *excontext, int did, osip_message_t *sub)
int eXosip_subscribe_remove (struct eXosip_t *excontext, int did)
```

Detailed Description

Enumeration Type Documentation

enum eXosip ss

Structure for subscription status

Enumerator:

EXOSIP_SUBCRSTATE_UNKNOWN

unknown subscription-state

EXOSIP_SUBCRSTATE_PENDING

pending subscription-state

EXOSIP_SUBCRSTATE_ACTIVE

active subscription-state

EXOSIP_SUBCRSTATE_TERMINATED

terminated subscription-state

enum eXosip_ss_reason

Structure for subscription reason

Enumerator:

DEACTIVATED

deactivated for subscription-state

PROBATION

probation for subscription-state

REJECTED

rejected for subscription-state

TIMEOUT

timeout for subscription-state

GIVEUP

giveup for subscription-state

NORESOURCE

noresource for subscription-state

enum eXosip ss status

Structure for notification status

Enumerator:

EXOSIP_NOTIFY_UNKNOWN

unknown state for subscription

EXOSIP_NOTIFY_PENDING

subscription not yet accepted

EXOSIP_NOTIFY_ONLINE

online status

EXOSIP_NOTIFY_BUSY

busy status

EXOSIP NOTIFY BERIGHTBACK

be right back status

EXOSIP_NOTIFY_AWAY

away status

EXOSIP_NOTIFY_ONTHEPHONE

on the phone status

EXOSIP_NOTIFY_OUTTOLUNCH

out to lunch status

EXOSIP_NOTIFY_CLOSED

closed status

Function Documentation

Build a default initial SUBSCRIBE request.

Parameters

excontext eXosip t instance.

subscribe Pointer for the SIP request to build.

to SIP url for callee. from SIP url for caller.

route Route header for SUBSCRIBE. (optional)

event Event header for SUBSCRIBE.expires Expires header for SUBSCRIBE.

Send an initial SUBSCRIBE request.

Parameters

excontext eXosip_t instance.

subscribe SIP SUBSCRIBE message to send.

Build a default new SUBSCRIBE message.

Parameters

excontext eXosip t instance.

did identifier of the subscription.

sub Pointer for the SIP request to build.

```
int eXosip_subscribe_send_refresh_request ( struct eXosip_t *
                                                              excontext,
                                                              did,
                                            osip_message_t * sub
                                          )
```

Send a new SUBSCRIBE request.

Parameters

excontext eXosip_t instance.

identifier of the subscription.

SIP SUBSCRIBE message to send. sub

```
int eXosip subscribe remove ( struct eXosip t * excontext,
                                                did
                               int
                             )
```

Remove outgoing subscription context.

Parameters

excontext eXosip_t instance.

identifier of the subscription. did