


Agenda

- General Program Structure
- Packages
- Interfaces, Classes
- Everyday Credit & Tally

General Program Structure



Packages

The following packages are created to support this functionality:

- com.sap.hallmark.views
- com.sap.hallmark.views.callbacks
- com.sap.hallmark.views.presenters
- com.sap.hallmark.adapters

Interfaces, Classes

Object Type	Object	Short Text/Comment
Class	CreditTallyActivity	Common Activity for Everyday and Seasonal Credit and Tallies; it displays the list of credit and tally entries, and expects EXTRA_IS_SEASONAL
Class	CreditTallyListAdapter	Adapter for the forms list
Class	CreditTallyTestABO	Credit Tally ABO class that integrates with the MBOs; the data can be saved locally in the device
Class	CreditAndTallyProductsListAc tivity	Common Activity for Everyday and Season credit, tally, and SBT Discard. It shows the list of products; and expects EXTRA_LIST_TYPE. Defaults to TYPE_EVERYDAY_CREDIT. EXTRA_IS_EDITABLE can be passes to set editable or non editable modes.
Class	CreditAndTallyAdapter	Adapter to display product list, it receives the list of products to display. On selecting the quantity text, it displays a list dialog box to edit the quantity.
Class	CreditTallyPresenter	Presenter class to connect the ABO layer to the Credit/tally UI
Class	ListViewWithOverlay	Listview with an overlay at the implemented position in {@link #dispatchDraw(Canvas)}
Class	AddCreditActivity	Activity to add credit and convert tally to credit
Class	CreditCategoryFragment	Category Fragment in the Credit/Tally summary screen
Class	CreditTallySummaryItemsFra gment	Summary Fragment for the Everyday/Seasonal Credit/Tally Summary screen
Class	CreditTallySummaryItemsAda pter	Adapter for items summary list
Class	SeasonalVerifyAddProductAc tivity	Activity to add unknown product details
Class	CreditNTallyProductModel	Credit tally product model

© 2011 SAP AG. All rights reserved.

Customer


Interfaces, Classes

Object Type	Object	Short Text/Comment
Class	EverydaySeasonalSummaryA ctivity	Activity to display the Credit and Tally Summary; it is commonly used for Per Visit Summary and Store Visit Summary. It expects EXTRA_IS_SEASONAL, EXTRA_CREDIT_TALLY_MODEL, EXTRA_MODE, and IS_PER_STORE.
Class	EverydaySeasonalSummaryA ctivity	Activity to display the Credit and Tally Summary; it is commonly used for Per Visit Summary and Store Visit Summary. It expects EXTRA_IS_SEASONAL, EXTRA_CREDIT_TALLY_MODEL, EXTRA_MODE, and IS_PER_STORE.
Class	CreditTallySummaryFragmen t	Summary Fragment in the Everyday Credit and Tally Summary screen
Class	CreditCategoryFragment	Category Fragment in the Credit/Tally summary screen
Class	CreditTallyPriceFragment	Price Fragment in the CreditTally summary screen.
Class	CreditTallySummaryItemsFra gment	Summary Fragment for the Everyday/Seasonal Credit/Tally Summary screen.
Class	CreditCategoryListAdapter	List adapter for the Category tab page on the CreditTally summary screen
Class	CreditTallySummaryItemsAda pter	Adapter for the items list on the Summary screen
Class	CreditTallySummaryPriceAda pter	Price Points tab page on the Summary screen
Class	CreditTallyPresenter	Presenter class to connect the ABO layer to the Credit/tally UI
Class	CreditTallyABO	Credit Tally ABO class that integrates with the MBOs. The data can be saved locally in the device.

© 2011 SAP AG. All rights reserved.

Customer


Scanning a form barcode will automatically bring up the Add Credit screen with the form number already entered.




Forms are separated out in a container each, with varying treatments depending on their status.

Tallies or credits display their status:

- Active: Editable, open credit/tally.
- Completed: Completed and ready to send.
- Transmitted: Sent to the back-end.
- Confirmation #: Received confirmation number from the back-end.




If a credit/tally is active for a long period of time, it is tagged as such.



Unlike the Lookup function, the user must enter a complete valid pocket ID or stock number to return a single result. They cannot perform searches for partial information.




Users are able to select forms to delete.



When the user opts to delete a form, we ask them to Confirm.

Terminology differs between whether a tally or credit form is selected.



Select the form, for numeric entry. If the user does not need to review the form details, the field could be automatically selected as the default state.


The user is able to scan a form and have this automatically entered. This also applies to Season Credit & Tally.

Toggling the credit limit on reveals the Limit Amount row, which the user can use to enter the dollar amount.


The user is able to track a credit against an installation event.

This list is populated with event Ids the user has for the scanned in store.


If the user has an installation they have begun, the default choice would be that installation's event ID



This screen works the same as the Add credit screen, except is editing a form's details.




Add Tally functionally works the same as Add Credit.




Scanning multiple items will increase the quantity for that product. The user can also tap on the quantity number to manually change it.

The subtitle is the user's entered note for this form. If the user has entered no form, the form number is shown instead. If there is no note or form number, the form's creation date is shown




When the user creates a tally, they are sent directly to this screen to begin scanning. If the user wishes to then make it a credit, assign a form number and so On, they are able to Convert to Credit and then enter those details.




When the user scans a product, an overlay appears allowing them to increase/decrease the quantity amount quickly.

This overlay appears in the same place, as it is anchored to the most recently scanned product, which is at the top.




If the user scans a seasonal product, an audible tone is played and a short term notification appears telling the user it is unable to add that type of product.

This notification is automatically dismissed after a short duration (~5 seconds).




If the user scans a product that is not from Hallmark, an audible tone is played and a short term notification appears telling the user it is unable to add that type of product.




This prompt is displayed when the user has scanned a product that is out of date and no longer listed, or not from Hallmark.


Out of date products are given the description "Unknown Product" and have a \$0 wholesale credit amount.




When the user scans a product that brings them within a certain dollar range of their store credit (\$5 for example), the device plays an audible tone and displays a short term notification.



If the user reaches the credit limit with an addition, they are given a prompt. The system accepts the addition that put the user on or over the limit but won't accept further additions.



After a user continues, a persistent notice is shown that they are over their credit limit set. This does not stop them from adding additional products.




Summary screen shows the form details, including retail and wholesale totals, for review.


Summary is broken down into multiple tabs for easier reading.

Date Created refers to the date the form is created on the device.


If the user is returning to a credit that has already been confirmed, the action-bar will instead only have a "Close" button.




The categories Cards, Gift Wrap and Other are used, displaying the quantity of products in each along with retail and wholesale totals.



Products are shown in a compact summary and organised by category. Categories are then sorted by price point then individual stock number.



Each price point is shown, with the quantity of products in each and totals.



Thank You

