Package 'PerMat'

June 14, 2024

Type Package

Title Perfo	ormance Metrics in Predictive Modeling
Version 0.	1.0
Maintaine	r Pankaj Das <pankaj.das2@icar.gov.in></pankaj.das2@icar.gov.in>
ror, r ted n mand	Performance metric provides different performance measures like mean squared error tmean square error, mean absolute deviation, mean absolute percentage error etc. of a fitnodel. These can provide a way for forecasters to quantitatively compare the perforce of competing models. For method details see (i) Pankaj Das (2020) http://doi.org/10.2007/j.goui/handle/123456789/44138 .
License M	IIT + file LICENSE
Encoding	UTF-8
RoxygenN	ote 7.2.3
Suggests 1	cnitr, rmarkdown, testthat (>= 3.0.0)
Config/test	tthat/edition 3
VignetteBu	uilder knitr
NeedsCom	ppilation no
Author Pa	ankaj Das [aut, cre] (<https: 0000-0003-1672-2502="" orcid.org="">)</https:>
Repository	CRAN
Date/Publi	ication 2024-06-14 15:20:11 UTC
Conten	ts
C M M M N R R	CCUITACY
Index	7
	1

2 CVRMSE

accuracy

Accuracy of Model

Description

Accuracy of Model

Usage

```
accuracy(actual, predicted)
```

Arguments

actual Actual value of the target variable

predicted Predicted/forecasted value of the target variable

Value

Accuracy of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550) predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540) accuracy(actual, predicted)
```

CVRMSE

Coefficient of Variation of Root Mean Squared Error

Description

Coefficient of Variation of Root Mean Squared Error

Usage

```
CVRMSE(actual, predicted)
```

Arguments

actual Actual value of the target variable

predicted Predicted/forecasted value of the target variable

Value

CVRMSE of the fitted model

MAE 3

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
CVRMSE(actual, predicted)
```

MAE

Mean Absolute Error

Description

Mean Absolute Error

Usage

```
MAE(actual, predicted)
```

Arguments

actual Actual value of the target variable

predicted Predicted/forecasted value of the target variable

Value

MAE of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
MAE(actual, predicted)
```

MAPE

Mean Absolute Percentage Error

Description

Mean Absolute Percentage Error

Usage

```
MAPE(actual, predicted)
```

Arguments

actual Actual value of the target variable
predicted Predicted value of the target variable

4 ME

Value

MAPE of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
MAPE(actual, predicted)
```

ME

Maximum Error

Description

Maximum Error

Usage

```
ME(actual, predicted)
```

Arguments

actual Actual value of the target variable
predicted Predicted value of the target variable

Value

ME of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
ME(actual, predicted)
```

NRMSE 5

NRMSE

Normalised Root Mean Squared Error

Description

Normalised Root Mean Squared Error

Usage

```
NRMSE(actual, predicted)
```

Arguments

actual Actual value of the target variable
predicted Predicted value of the target variable

Value

NRMSE of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
NRMSE(actual, predicted)
```

R2

Coefficient of Determination (R-Square)

Description

Coefficient of Determination (R-Square)

Usage

```
R2(actual, predicted)
```

Arguments

actual Actual value of the target variable predicted Predicted value of the target variable

Value

Coefficient of Determination (R-Square) of the fitted model

6 RMSE

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
R2(actual, predicted)
```

RMSE

Root Mean Squared Error

Description

Root Mean Squared Error

Usage

```
RMSE(actual, predicted)
```

Arguments

actual Actual value of the target variable predicted Predicted value of the target variable

Value

RMSE and MSE of the fitted model

Examples

```
actual <- c(100, 150, 200, 250, 300, 350, 400, 450, 500, 550)
predicted <- c(95, 148, 210, 245, 290, 360, 395, 440, 510, 540)
RMSE(actual, predicted)
```

Index

```
accuracy, 2
CVRMSE, 2
MAE, 3
MAPE, 3
ME, 4
NRMSE, 5
R2, 5
RMSE, 6
```