
1,

mdmvazquez@server:/\$ __

EX1-Mdmvazquez-Server [Corriendo] - Oracle VM VirtualBox Archivo Máquina Ver Entrada Dispositivos Ayuda mdmvazquez@server:/\$ cat /etc/netplan/50–cloud–init.yaml # This file is generated from information provided by ¥ the datasource. Changes to it will not persist across an instance. ¥ To disable cloud–init's network configuration capabilities, write a file # /etc/cloud/cloud.cfg.d/99–disable–network–config.cfg with the following: network: {config: disabled} network: ethernets: enp0s3: dhcp4: true enp0s8: addresses: [172.30.92.1/23] gateway4: 172.30.92.254 nameservers: addresses: [1.1.1.1 , 1.0.0.1] enpOs9: addresses: [172.30.93.1/23] gateway4: 172.30.93.253 nameservers: addresses: [1.1.1.1 , 1.0.0.1] version: 2

EX1-Mdmvazquez-Server [Corriendo] - Oracle VM VirtualBox Archivo Máguina Ver Entrada Dispositivos Ayuda mdmvazquez@server:/\$ ip –cc a Option "-cc" is unknown, try "ip -help". mdmvazquez@server:/\$ ip -c a 1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00 inet 127.0.0.1/8 scope host lo valid_lft forever preferred_lft forever inet6 ::1/128 scope host valid_lft forever preferred_lft forever 2: enpOs3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:a4:a7:6c brd ff:ff:ff:ff:ff inet6 fe80::a00:27ff:fea4:a76c/64 scope link valid_lft forever preferred_lft forever 3: enpOs8: <BROADCAST.MULTICAST.UP.LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:82:7b:28 brd ff:ff:ff:ff:ff inet 172.30.92.1/23 brd 172.30.93.255 scope global enp0s8 valid_lft forever preferred_lft forever inet6 fe80::a00:27ff:fe82:7b28/64 scope link valid_lft forever preferred_lft forever 4: enpOs9: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:b2:e2:49 brd ff:ff:ff:ff:ff inet 172.30.93.1/23 brd 172.30.93.255 scope global enp0s9 valid_lft forever preferred_lft forever inet6 fe80::a00:27ff:feb2:e249/64 scope link valid_lft forever preferred_lft forever mdmvazquez@server:/\$ _

4,



EX1-Mdmvazquez-Client [Corriendo] - Oracle VM VirtualBox

Archivo Máquina Ver Entrada Dispositivos Ayuda

```
mdmvazquez@client:~$ cat /etc/netplan/50-cloud-init.yaml
# This file is generated from information provided by
# the datasource. Changes to it will not persist across an instance.
# To disable cloud-init's network configuration capabilities, write a file
# /etc/cloud/cloud.cfg.d/99-disable-network-config.cfg with the following:
# network: {config: disabled}
network:
    ethernets:
        enp0s3:
            dhcp4: true
        enp0s8:
            dhcp4: true
        enp0s9:
            dhcp4: true
        version: 2
mdmwvazquez@client:~$ __
```

5,

EX1-Mdmvazquez-Client [Corriendo] - Oracle VM VirtualBox Archivo Máquina Ver Entrada Dispositivos Ayuda mdmvazquez@client:~\$ ip –c a 1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 inet 127.0.0.1/8 scope host lo valid_lft forever preferred_lft forever inet6 ::1/128 scope host valid_lft forever preferred_lft forever 2: enpOs3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:84:c0:b7 brd ff:ff:ff:ff:ff inet 172.16.128.154/20 brd 172.16.143.255 scope global dynamic enp0s3 valid_lft 3992sec preferred_lft 3992sec inet 172.16.128.192/20 brd 172.16.143.255 scope global secondary enpOs3 valid_lft forever preferred_lft forever inet6 fe80::a00:27ff:fe84:c0b7/64 scope link valid_lft forever preferred_lft forever 3: enpOs8: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:af:32:73 brd ff:ff:ff:ff:ff inet6 fe80::a00:27ff:feaf:3273/64 scope link valid_lft forever preferred_lft forever 4: enpOs9: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP gro link/ether 08:00:27:bd:7e:4b brd ff:ff:ff:ff:ff inet6 fe80::a00:27ff:febd:7e4b/64 scope link valid_lft forever preferred_lft forever mdmvazquez@client:~\$

6,

EX1-Mdmvazquez-Client [Corriendo] - Oracle VM VirtualBox Archivo Máquina Ver Entrada Dispositivos Ayuda mdmvazquez@client:~\$ sudo dhclient -v -r enp0s9 [sudo] password for mdmvazquez: Internet Systems Consortium DHCP Client 4.3.5 Copyright 2004-2016 Internet Systems Consortium. All rights reserved. For info, please visit https://www.isc.org/software/dhcp/ Listening on LPF/enp0s9/08:00:27:bd:7e:4b Sending on LPF/enp0s9/08:00:27:bd:7e:4b Sending on Socket/fallback mdmvazquez@client:~\$ __