

# Guide: Getting Started with Huawei Cloud ECS



Huawei Technologies CO., LTD

**v3.6.0** — September 14, 2026 12:43

# Contents

---

|                                                  |          |
|--------------------------------------------------|----------|
| <b>1 Provision an Elastic Cloud Server .....</b> | <b>2</b> |
| 1.1 Launch the instance .....                    | 2        |
| 1.2 Connect over SSH .....                       | 3        |
| 1.2.1 Retrieve the public IP .....               | 3        |
| 1.3 Verify the instance .....                    | 3        |
| 1.3.1 Recommended flavors .....                  | 4        |
| <b>2 Configure the Terraform Provider .....</b>  | <b>5</b> |
| 2.1 Create an AK/SK .....                        | 5        |
| 2.2 Declare the provider .....                   | 5        |
| 2.3 Next steps .....                             | 6        |
| <b>3 Clean Up .....</b>                          | <b>7</b> |
| <b>4 Brand Color Palette .....</b>               | <b>8</b> |
| <b>5 Changelog .....</b>                         | <b>9</b> |



### Info

This document demonstrates the `guide.cls` template for Huawei Cloud guides. It exercises all available commands and environments: cover page, table of contents, objectives, code blocks, images, callouts, badge, changelog, and the `\menu` command for menu paths.

# 1

## Provision an Elastic Cloud Server

**General Objective:** This lab walks you through provisioning an Elastic Cloud Server (ECS) on Huawei Cloud via the Console. By the end you will be able to launch a virtual machine, connect to it over SSH, and verify that it is running.

**Prerequisites:**

- Active IAM account on Huawei Cloud (valid username and password).
- A web browser (Google Chrome, Mozilla Firefox, or Microsoft Edge).
- An SSH client installed locally (OpenSSH, PuTTY, etc.).
- A key pair created in the Console, or permission to create one.

### Info

This guide covers the basic ECS provisioning flow. For advanced operations, consult the official Huawei Cloud documentation.

## 1.1 Launch the instance

**Objective:** Create a single ECS instance in the `sa-brazil-1` region using the Console wizard.

**Step by step:**

1. In the Console, open the service catalog and navigate to **Console** → **Elastic Cloud Server**.




**Figure 1:** Service catalog in the Console.

2. Click **Create ECS** and fill in the basic configuration:

|                 |                                |
|-----------------|--------------------------------|
| Name:           | web-server-01                  |
| Flavor:         | s6.small.1 (1 vCPU, 1 GB RAM)  |
| Image:          | Ubuntu 22.04 Server 64bit      |
| Disk:           | 40 GB General Purpose SSD      |
| VPC:            | vpc-default                    |
| Subnet:         | subnet-default                 |
| Security Group: | sg-ssh (allows inbound TCP 22) |

- Under **Login Configuration**, select the key pair you created earlier. Click **Create Now** and wait for the status to change to **Running**.



*The instance is assigned a public IP (EIP). If you need a fixed IP, allocate a dedicated EIP and bind it after creation.*

### Important

The EIP assigned during creation is released when the instance is deleted. Allocate a dedicated EIP if you need to keep the address.

## 1.2 Connect over SSH

### 1.2.1 Retrieve the public IP

On the ECS details page, copy the **EIP** (Elastic IP) field. This is the address you will use to connect.

#### 1.2.1.1 Using OpenSSH

From a terminal, connect with the private key that matches the key pair selected during creation:

```
chmod 400 ~/.ssh/huawei_key.pem
ssh -i ~/.ssh/huawei_key.pem ubuntu@<EIP>
```

#### 1.2.1.2 Using PuTTY

Convert the key to PPK format with PuTTYgen, then open a session to the EIP with the converted key.

## 1.3 Verify the instance

Once connected, run a few checks:

```
uname -a          # confirm OS version
df -h             # check disk space
systemctl status  # verify services are running
```

Alternatively, save the checks to a script and run it with

```
#!/bin/bash
# Example: verify an ECS instance is reachable and running
# Usage: ./check-ecs.sh <EIP>

EIP="${1:?Usage: check-ecs.sh <EIP>}"

echo "Checking instance at $EIP ..."
ssh -i ~/.ssh/huawei_key.pem "ubuntu@$EIP" << 'EOF'
    uname -a
    df -h
    systemctl is-active nginx
EOF

echo "Done."
```

### 1.3.1 Recommended flavors

The table below lists recommended ECS flavors for development workloads:

| Flavor        | vCPU / RAM     | Use case                          |
|---------------|----------------|-----------------------------------|
| ac8.large.2   | 2 vCPU / 4 GB  | Light development                 |
| ac8.xlarge.2  | 4 vCPU / 8 GB  | Recommended — full coding stack   |
| ac8.2xlarge.2 | 8 vCPU / 16 GB | Heavy workloads + multiple agents |

**Table 1:** Recommended ECS flavors for development.

[ Image placeholder ]

File: assets/ecs-flavors.png

**Description:** Screenshot of the ECS flavor selection page in the Console

Place the image file at the path above, then replace this command with `\image{assets/ecs-flavors.png}` or `\imagecap{assets/ecs-flavors.png}{caption}`.

*This is an English sample that exercises every command and environment provided by the guide class. Use it as a reference when writing your own guides.*

# 2

## Configure the Terraform Provider

---

**General Objective:** This chapter shows how to obtain an AK/SK pair from the Console and declare the Huawei Cloud provider in a Terraform configuration file, preparing the environment for Infrastructure as Code.

**Prerequisites:**

- Chapter 1 completed (Console access working).
  - IAM permission to create access credentials.
  - terraform installed locally (version 1.0 or later).
- 

### 2.1 Create an AK/SK

**Objective:** Generate an Access Key ID / Secret Access Key pair to authenticate external tools with Huawei Cloud.

In the Console, click your username in the top-right corner and open **My Credentials**. In the **Access Keys** section, click **Create Access Key** and download the generated file. Store it in a safe location: the Secret Access Key is shown only once.

### 2.2 Declare the provider

**Step by step:**

1. Create a file named *provider.tf* in your project directory with the following content:

```
terraform {
  required_providers {
    huaweicloud = {
      source  = "huaweicloud/huaweicloud"
      version = ">= 1.60.0"
    }
  }
}

provider "huaweicloud" {
  region      = "sa-brazil-1"
  access_key  = "YOUR_ACCESS_KEY_HERE"
  secret_key  = "YOUR_SECRET_KEY_HERE"
```

```
}
```

Replace the `access_key` and `secret_key` values with the credentials obtained in the previous section.

2. In a terminal, in the project folder, initialize the Terraform working directory:

```
terraform init
terraform plan
```

*Never commit the `provider.tf` file with real credentials. Use environment variables or a state file ignored by version control.*

## 2.3 Next steps

With the provider declared, you can start defining resources in `terraform`. For the full list of available resources, see the official documentation at [Huawei Cloud Provider](#).

### Tip

Use `terraform validate` to check syntax before applying changes.

### Example

# 3

## Clean Up

---

**General Objective:** Remove the resources created in this lab to avoid ongoing charges.

---

### Step by step:

1. In the Console, navigate to **Elastic Cloud Server**.
2. Select the instance `web-server-01`, click **More** and choose **Delete**.
3. Confirm deletion. Optionally release the EIP if it was dedicated.

*If you used Terraform, run `terraform destroy` instead to remove all resources declared in the configuration.*

# 4

## Brand Color Palette

---

The template defines auxiliary brand colors aligned to the Huawei Cloud Brand Guidelines:

| Color    | HEX     | Pantone | Sample                                                                             |
|----------|---------|---------|------------------------------------------------------------------------------------|
| Rose Red | #C40054 | 7636    |  |
| Dark Red | #7F0001 | 483C    |  |
| Orange   | #ED6D00 | 165C    |  |
| Yellow   | #FCC800 | 7406C   |  |
| Green    | #62B230 | 3501C   |  |
| Blue     | #30B5C5 | 2227C   |  |

# 5

## Changelog

---

- 
- 3.6.0** *September 14, 2026*
- Added `\setdocauthors` to demonstrate the authors feature on the cover page.
- 1.9.0** *September 14, 2026*
- Updated to base template v3.0.1 — minor fixes (test auto-discovery, help text, comments, CI).
- 1.8.0** *September 14, 2026*
- Updated to base template v3.0.0 — modular pipeline refactoring (shared Lua filter factory, shared DOCX fix logic, build system auto-discovery).
- 1.7.0** *September 14, 2026*
- Updated to base template v2.16.0 — Lua filter fixes and build system improvements.
- 1.6.0** *2026-08-12*
- The `changelog` environment now emits its own section heading; `[nochangelog]` suppresses the heading and entries in one switch.
- 1.5.1** *2026-08-12*
- Fix `hutable` centering and row-color fill: use `\hline` so `colortbl` row colors fill cleanly up to the rules.
- 1.5.0** *2026-08-12*
- New `hutable` environment: full-grid tables with Huawei-red header and alternating body rows.
  - Floats now default to `[H]` placement so tables and figures appear in source order.
- 1.4.1** *2026-08-10*
- H1 section title size reduced from 27pt to 20pt.
- 1.4.0** *2026-08-10*
- Default image size increased: width 65% → 90% of text width, height 40% → 50% of text height.
- 1.3.0** *2026-08-10*
- Enlarged H1 section title (18pt → 27pt, 50% bigger).
  - `nochangelog` option now hides version, date, and time on the cover page.
  - Document date defaults to `\today` (compilation date).
- 1.2.1** *2026-08-09*



- Rolled back `/ActualText` markers — broke code block rendering.

### 1.2.0

2026-08-09

- Added key-value sizing options to `\image` and `\imagecap` — width and height can now be set independently.

### 1.1.3

2026-08-09

- Fixed PDF copy-paste of URLs in code blocks — disabled Cascadia Code programming ligatures (`ca1t`) that corrupted `//` into `)` on copy.

### 1.1.2

2026-08-09

- Fixed italic font rendering — HarmonyOS Sans and Cascadia Code have no italic variants; enabled synthetic slant (`AutoFakeSlant`).

### 1.1.1

2026-08-08

- Changed table and figure caption labels to black (was Huawei red).

### 1.1.0

2026-08-08

- Added Huawei-branded table styling: red header bar, alternating row colors, and bordered cells.

### 1.0.0

2026-08-05

- Initial version.
  - Added callout boxes, badge, and changelog support.
-