Manager and owner guide

You decide who may do what, approve what is above your staff's limits, and read the business. Everything is in the back office (web browser).

Who may do what

- **People & access** → **Users**: one account per person, never shared. Give each person a **role** for the right branch (a cashier for their till's branch, a supervisor for the shop).
- Limits (discounts, purchase approvals, credit) come with the role; change them on the person's access.
- The **IT Admin** sets up devices and users but sees no sales or money unless you also give them a business role.
- Owners and managers must use **two-step sign-in** (an authenticator app or a passkey).

Stock requests between industries

When one of your branches asks a branch of another industry for stock (or the other way round), **Stock** → **Stock requests** shows it as *Awaiting approval*. Open it and click **Approve** or **Reject**. You cannot approve a request you made yourself. The goods move at cost once both sides approve.

Daily (ten minutes)

1. **Dashboard**: sales today against last week, stock alerts, anything waiting for your approval.
2. **Insights** → **Alerts**: unusual voids or refunds, items about to run out, margins that fell.
3. Approve purchase orders, stock adjustments and expense claims that wait for you.
4. **Sales** → **Till shifts**: cash and MoMo / card / voucher differences, and the *Drawer* column (paid out, dropped, no-sale opens). **Insights** → **Loss prevention** now also compares how often each cashier opens the drawer without a sale.
5. **Cash** → **Close the day** before leaving: fix any red ✗ (or write why), enter the cash taken to the bank with the slip number and what stays in the safe, and press **Close the day**.

Settings for the drawer (System → Settings → Tills and cash): *Expenses paid from the till: a supervisor approves above* (default GHS 100) and *Cash limit in a till drawer* (default off; e.g. 200000 = GHS 2,000). Who approves pay-outs and takes cash drops: the permission *Approve till pay-outs above the limit and take cash drops* (supervisors and managers have it).

Going live

System → **Go-live** leads you through it:

1. **Plan** — where the data comes from, how you switch over (*parallel run* is safest), how the pilot runs.
2. **Checklist** — each step in order; most turn green by themselves when done.
3. **Practice company** — create it, give your staff practice logins, let them practise for a few days.
4. **Check the figures** — with your accountant, against the old system.
5. **Parallel run** — every evening, type in the old system's day totals; explain any difference.

6. **Take the go-live backup**, then **Go live**. If things go badly wrong, **Go back to the old system** and follow the rollback plan (installation guide, chapter 17.8).

When staff report a problem

Staff tap **Report a problem**. Support gets an e-mail with a picture of the screen; you and IT see the list under **System → Problem reports**. To let SyncLytics support connect to a till or computer, use **System → Support access** (free, for a few hours or until the problem is closed; a banner shows while it is open, and you can withdraw it). During the pilot, a **pilot report** is e-mailed every evening: sales per branch, cash over/short, tills that were offline, the parallel-run difference and open problems.

Practise first

In the **practice company**: give a new cashier access to one till only, approve a large discount, read the insights for last week.