


How to Enable Microsoft Authenticator via Azure Portal

docs.wetransact.io/how-to-enable-microsoft-authenticator-via-azure-portal

Step 1 – Go to Security

1. Sign in to <https://portal.azure.com>
2. On the home page, under **Azure Services**, click on **Security**



Step 2 – Open Authentication Methods

1. In the Security left-hand menu, expand **Manage**
2. Click on **Authentication Methods**

Home

Security | Getting started

What are the key components of

Search

Getting started

- Diagnose and solve problems
- Protect
- Manage**
 - Identity Secure Score
 - Named locations
 - Authentication methods**
 - Multifactor authentication
 - Certificate authorities (classic)
 - Public key infrastructure
- Report
- Troubleshooting + Support

Documentation

Microsoft Entra ID offers a range of security fea

- Microsoft Entra Conditional Access
- Microsoft Entra ID Protection
- Azure Security Center
- Identity Secure Score
- Named locations
- Authentication methods
- Multifactor authentication

Security guidance

For a strong security posture, we recommend th

- 5 steps to secure your identity infrastructure
- Microsoft Entra Password Guidance

Step 3 – Go to Policies

1. Under Authentication Methods, click on **Policies** from the left-hand menu
2. You will see a list of available authentication methods under **Authentication Method Policies**

Home > Security | Authentication methods

Authentication methods | Policies

cc399a02-f38a-4820-a991-894e8c59d676 - Microsoft Entra ID Security

Search

Manage

- Policies**
- Password protection
- Registration campaign
- Authentication strengths
- Settings
- Monitoring

Migration status

In progress (change)
Begin automated guide

Authentication method policies

Use authentication methods policies to configure the authentication methods your users may register and use. If a user is in scope for a method, they may use it to authenticate and for password reset (some methods aren't supported for some scenarios). [Learn more](#)

Method	Target	Enabled
Built-in		
Passkey (FIDO2)		No
Microsoft Authenticator	All users	Yes
SMS		No
Temporary Access Pass		No

Step 4 – Enable Microsoft Authenticator

1. In the list, locate **Microsoft Authenticator**
2. Click on it to open the settings
3. Set **Enable** to **Yes**
4. Set **Target** to **All Users** (or select specific users/groups as needed)
5. Click **Save**

 Microsoft Authenticator is now enabled for your tenant.

Need Help?

Contact: *support@wetransact.io*

Always-current version of this guide: docs.wetransact.io/how-to-enable-microsoft-authenticator-via-azure-portal · Questions? Reply to this email and your CSM will pick it up.