


**Document History** 

Date	Author	Summary of Change	Note
7/04/06	Augmentum	Initial version.	

# **Documentum Adapter Installation Guide**

### **Precondition:**

- 1. Make sure the Documentum Server is available.
- 2. Install the DFC API environment(DFC\_5.3\_SP2\_windows.exe) with correct configuration, including host name of Doucumentum Server, Documentum repository, user name and password for accessing Doucmentum server.
- 3. Enable the Webservice in Ambassador with correct install key.



#### CONFIDENTIAL

This document contains confidential information, trade secrets, and copyrighted expressions that are the property of Augmentum, Inc., 1065 E. Hillsdale Blvd. Suite 400, Foster City, CA 94404. Any disclosure, reproduction, sale or license of all or any part of the information or expression contained in this document is prohibited by California law and the United States copyright law, and may be subject to criminal penalties. If you are not an employee of Augmentum, Inc. or otherwise authorized in writing by Augmentum, Inc. to possess this document, please contact Augmentum, Inc. immediately at the address listed above.



## **Documentum Adapter Installation:**

1. Extract the ZIP file DocumentumAdapter.zip file over the <a href="mailto:Ambassador\_Home">Ambassador\_Home</a> directory where you installed Ambassador.

For example, if Ambassador is installed to C:\apps\Ambassador\_6.7.2 then unzip the zip file to the C:\apps directory.

- 2. Edit the file "dfc.properties" which locates in
  - <Ambassador\_Home>\deployment\ambassador.ear\lib \classes. Edit "dfc.data.dir" property and
    set its value with the path where the DFC API is installed. (Note: Refer to
    <DFC Home>\config\dfc.properties).
- 3. In the file "envoy.properties", edit "remote.ipAddressFilterWSvc" property to add IP address of webtop plug-in machine so that webtop plug-in can access the web service provided by Ambassador. For example, "remote.ipAddressFilterWSvc=192.168.0.174" (192.168.0.174 is the IP address of webtop plug-in machine).
- 4. If the default DQL script provided by us is used without any modification, just skip this step. If you define your own Documentum custom attributes or table names in DQL script, you need to edit the file "DocumentumAdapter.properties" to match those attributes or table names.
- 5. Restart Ambassador.

Note: This demo version for Documentum Adapter just only supports one webtop client. The final version will support more than one client concurrently.

#### CONFIDENTIAL