

Getting started

Everything from opening it the first time to running a tournament. No knowledge assumed — if you can send a text message, you can use this.

1 What this is


A golf handicap tracker your group shares. Somebody posts the scores after a round, and everyone's handicap keeps itself up to date.

It is a **website that behaves like an app**. There is nothing to buy and nothing to install from an app store. You open a web address once, add it to your home screen, and after that it opens like any other app — including when you have no signal.

IT DOES	IT DOES NOT
Work out handicaps the official way (World Handicap System)	Need an app store account
Keep working with no signal, and catch up later	Cost anything
Share results to WhatsApp, email or text	Show adverts
Handle several groups, and tournaments over more than one day	Need a password, for most people

2 Opening it the first time

Everything starts with a web address — the same sort of thing you type to reach any website. It will look like this:



Whoever runs your group will send you the exact address, usually as a link you can just tap.

If you were sent an invitation link, simply tap it. It opens the app, knows which group you belong to, and greets you by name. Skip to section 4.

3 Putting it on your device

You only do this once. Afterwards it sits with your other apps and opens with one tap.

Why bother? Because it opens full screen without the browser's bars around it, it starts faster, and it keeps working when you have no signal out on the course.


iPhone and iPad

1 Open it in Safari

It must be **Safari**. Chrome on an iPhone cannot add apps to the home screen.

2 Tap the Share button

A square with an arrow pointing up out of it. On an iPhone it is at the bottom of the screen; on an iPad it is at the top right.



Tap Share, then scroll down the list until you see Add to Home Screen.

3 Scroll down and tap Add to Home Screen

The list is long. Keep scrolling — it is well down, past Add Bookmark and Add to Favourites.

4 Tap Add

Top right corner. The icon appears on your home screen with your other apps.

The one thing to know about iPhones and iPads. Safari and the home-screen icon are treated as two separate places. If you use both, sign in on each — otherwise the app thinks you are two different people. Guests who joined by an invitation link need do nothing.

Android


1 Open it in Chrome

Chrome is the one that comes with most Android phones.

2 Look for the prompt, or use the menu

Chrome often offers **Install app** or **Add to Home screen** along the bottom by itself. Tap it and you are finished.

If it does not appear, tap the **three dots** at the top right, then **Add to Home screen** or **Install app**.



Either the prompt or the menu works. Both do exactly the same thing.

Mac

1 Open it in Safari

On macOS Sonoma or newer.

2 Menu bar, File, then Add to Dock

It then lives in your Dock and opens in its own window, without tabs or an address bar.

On an older Mac there is no Add to Dock. Use Chrome or Edge instead: the three dots at the top right, then **Cast, save and share**, then **Install page as app**.

Windows


1 Open it in Edge or Chrome

Edge comes with Windows.

2 Click the install icon in the address bar

A small screen-with-an-arrow icon appears at the right-hand end of the address bar. Click it, then click **Install**.

If you cannot see it: three dots at the top right, then **Apps**, then **Install this site as an app**.



The install icon only appears on sites that can be installed. This is one of them.

4 Joining your group

Almost everybody joins by tapping a link. There is nothing to type and no password.



The link knows who you are. One tap and you are in, with your rounds and handicap already attached.

If you were given a code instead

Type your name exactly as it appears on your group's list, then the six-character code. Spelling matters — "Bob" and "Robert Tan" become two different people with two different handicaps.

Using more than one device

Tap the same invitation link on each of them. Your link keeps working for you.

5 Posting a round

What you fill in

DATE

Aug 15, 2026

GOLFER

Willy Rosales

COURSE

Royal Ontario

TEES

White 68.8/133

Blue 70.5/138

GROSS SCORE

97

What you see while it saves



Posting your round...

This can take a moment

Your own name is fixed in place, so you cannot post against somebody else by mistake.

Whenever the app is working it dims the screen and says so. Wait for it to clear rather than tapping again.

Two ways to enter a round

At the foot of the Enter tab there is a link that switches between them, and the app remembers which you chose.

- **Every field at once** — the original. Best for typing in a whole fourball's cards after a game.
- **One step at a time** — golfer, then course and tees, then the score, each on its own with much larger type. Best for posting your own round on a phone.

The fields, the order and the checks are identical. Only the layout differs, so a round posted either way is exactly the same round.

Adjusted score

Leave it blank almost always. It exists for the official rule that caps each hole at net double bogey. If you do not already know you need it, you do not need it.

If you have no signal

Post anyway. The round is kept on your phone and uploads by itself when signal returns. The badge at the top right turns red while anything is waiting.


6 Your handicap

Open **Summary**. After **three rounds** your Handicap Index appears. Before that it tells you how many more you need.

TERM	WHAT IT MEANS
Handicap Index	Your ability as one number, the same at every course. This is the one people mean by "my handicap".
Course Handicap	How many strokes you get at <i>this</i> course from <i>these</i> tees. Worked out from your index.
Gross	Your actual score.
Net	Your score minus your course handicap. This is what makes a game between different abilities fair.
Differential	How well you played that day, adjusted for how hard the course was. Your index comes from your best eight of the last twenty.

The trend chart

Open **My rounds** and it appears at the top.



The line is your index after each round. Filled dots are the eight rounds currently counting. Hollow ones are still in the window but are not affecting your number today. Tap any dot for the details.

7 For whoever runs the group

Everything above, plus three tabs guests never see: **Manage**, **Admin**, and the full **History**.

Before the first outing

1 Add every golfer

Manage, type the name, **Add golfer**. Include people without phones — they can be scored without ever opening the app.


Setting up a second group? **Add from my other groups** brings people across with their rounds and handicap. Never retype a name — that creates a second person with half their history.

2 Add your courses

Manage, **Add a course**. Search by name, or type the rating and slope from the scorecard.

3 Invite everybody

Manage, then **Invite** beside each name. The link names them, so they tap once and are in. Choose guest or admin, then WhatsApp, email or text.



Each golfer has Invite, Rename and Index. Buttons grey out when they no longer apply.

Somebody who already has a handicap

Manage, **Index** beside their name, and type it in. It stands in until they have three rounds with you, then their own rounds take over completely.

Guest, admin, owner

ROLE	CAN DO	PASSWORD?
Guest	Posts their own rounds; sees results, rankings and their own history.	None
Admin	Also adds courses and golfers, creates games, posts for anybody, edits any round.	Yes
Owner	Everything, plus invitations, roles, backup and settings. Cannot be demoted.	Yes

Admins are asked for a password as they join. The form appears straight after tapping the invitation — nothing to go and find. Not the password for their email — a new one, for this app only. They can choose Not now, but until they set it their role works in that one browser only: it cannot follow them to another device, and it is lost if the browser's data is cleared. Guests are never asked for one.

An admin link is a different link. A guest cannot turn theirs into an admin one. A guest link keeps working for that same person on another device; an admin link works once.

Running a game

1. **Games, Add a game.** Set the date and course. For a tournament, tap **Runs over more than one day** and set the last day.
2. Everyone posts their round as normal. They do not have to pick the game.
3. Open the game afterwards. Every round played on those dates is offered — tick and add in one tap.
4. **Share** the result. Tick net, gross, or both.

A whole field to enter at once? Create the game first, open it, then tap **Enter scores for everyone**. You get one row per golfer — their index and a box for the score. Type the scores you have and leave the rest blank; only the ones you filled in are posted, and they all go straight into the game. Anybody with no handicap yet gets a small box to type one.

Set somebody's handicap after the game already existed? Open the game and tap **Recalculate this game's handicaps**. A round remembers the handicap that applied when it was posted — that is what stops old results shifting — so an index set afterwards does not reach back into it. Recalculating shows you every change before making it.

Things worth doing

WHAT	WHERE	HOW OFTEN
Back up	Admin , Back up now, then save it somewhere	Monthly, and before anything risky
Course search key	Admin , Course lookup	Once
Check the data	Add /tidy.html to the web address	If a number looks wrong
Start another group	Tap the group name at the top	As needed

8

When something looks wrong

WHAT YOU SEE	WHAT TO DO
The old version after an update	Add /reset.html to the web address
A red bar under the header	It names the problem and the fix. The app keeps working; only syncing is affected.
"This screen couldn't be drawn"	Tap Technical detail and send that text to whoever maintains the app. It says exactly what went wrong.
Status badge red, rounds waiting	You are offline. Rounds are safe and upload when signal returns.
Somebody's name twice	Add /tidy.html to the web address. It reports duplicates and can clear unused ones.
Golfers missing after a change	Add /rebuild.html to the web address. It puts everyone back with their rounds.
Not sure which version is running	Foot of Summary , or add /reset.html to the address

Nothing you can tap in the app deletes a golfer or their rounds. Remove only takes somebody off a roster. Their record, rounds and handicap stay where they are.

Before you hand it to the group

- The app opens and shows no red bar.
- Your courses and roster are in, under Manage.
- You have taken a backup and saved it somewhere you will find it.
- You have joined on a second device and it shows the same rounds.
- One friend has joined and can post a round — and cannot see Manage or Admin.
- Airplane mode: post a round, the badge goes red, turn it off, it uploads.

Then send the invitations.