@root.dns

vim /etc/bind/named.conf

```
9 include "/etc/bind/named.conf.options";
10 include "/etc/bind/named.conf.local";
11 include "/etc/bind/named.conf.default-zones";
13
14 zone "." {
                type master;
16
                file "root.zone";
17 };
18
19 zone "dns" {
20
                type master;
21
                file "dns.zone";
22 };
23
24 zone "46.204.114.in-addr.arpa" {
25
26
                type master;
                file "dns.rev";
27 };
```

vim /etc/bind/named.conf.options

//forward 설정이 되어있으면 안됨.

vim /var/cache/bind/root.zone

```
; BIND reverse data file for broadcast zone
  4
5
6
7
8
9
              604800
                                 root.dns. root.root.dns. (
                                                    ; Serial
                                  604800
                                                     ; Refresh
                                   86400
                                                    ; Retry
                                                    ; Expire
                                  604800 )
                                                    ; Negative Cache TTL
  11
 12 @
13 dns
                                                    root.dns.
                                                    root.dns.
ns.dreaminfo.biz.
 14 dreaminfo.biz
  15 worldsign.org
                                                    ca.worldsign.org.
                                                    114.204.56.1
108.96.58.1
95.201.100.1
114.204.56.1
 16
 17 ns.dreaminfo.biz
    ca.worldsign.org
  19 root.dns
```

```
2;
  ; BIND reverse data file for broadcast zone
4 $TTL
5 @
6
           604800
                    SOA
                             root.dns. root.root.dns. (
                                              ; Serial
7
8
9
                              604800
                                                Refresh
                               86400
                                              ; Retry
                             2419200
                                              ; Expire
10
                              604800 )
                                              ; Negative Cache TTL
11;
12
                    NS
                             root.dns.
13 @
                             114.204.56.1
                             114.204.56.1
14 root
```

vim /var/cache/bind/dns.rev

```
2; BIN
3;
4 $TTL
5@
   ; BIND reverse data file for broadcast zone
            604800
                     SOA
                              root.dns. root.root.dns. (
                                                ; Serial
7
8
9
                               604800
                                                ; Refresh
                                86400
                                                ; Retry
                              2419200
                                                ; Expire
10
                               604800 )
                                                ; Negative Cache TTL
11;
12
                     NS
                              root.dns.
13
  1
                     PTR
                              root.dns.
```

vim /etc/bind/named.

@ca.worldsign.org DNS

vim /etc/bind/named.conf.default-zones // 주석처리

```
1 // prime the server with knowledge of the root servers
2 //zone "." {
3 // type hint;
4 // file "/etc/bind/db.root";
5 //};
6
```

```
9 include "/etc/bind/named.conf.options";
10 include "/etc/bind/named.conf.local";
11 include "/etc/bind/named.conf.default-zones";
13 zone "worldsign.org" {
14
             type master;
15
16
             file "worldsign.zone";
             3;
17
18 zone "100.201.95.in-addr.arpa" {
19
             type master;
20
             file "worldsign.rev";
21
             3;
```

vim /etc/bind/named.conf.options

```
// forwarders {
13
14
               0.0.0.0;
15
16
17
        allow-transfer { none; };
18
        19
        _// If BIND logs error messages about the root k
20
        // you will need to update your keys. See http
21
        22
        dnssec-validation no;
23
24
        auth-nxdomain no;
                         # conform to RFC1035
25
        listen-on-v6 { any; };
26 };
27
```

vim /var/cache/bind/worldsign.zone

```
; BIND reverse data file for broadcast zone
 3;
 4 $TTL
            604800
4 @ 5 6 7 8 9 10 .
                    SOA
                             ca.worldsign.org. root.ca.worldsign.org. (
                                               ; Serial
                              604800
                                               ; Refresh
                               86400
                                              ; Retry
                             2419200
                                              ; Expire
                              604800 )
                                              ; Negative Cache TTL
11;
12 @
                             ca.worldsign.org.
                    NS
13 @
                    MX 10
                             mail.worldsign.org.
14 @
                             95.201.100.1
15 mail
                             95.201.100.1
16 ca
                             95.201.100.1
                    Α
17 cml
                    CNAME
                             ca.worldsign.org.
```

```
i; BIND reverse data file for broadcast zone
 23
            604800
4 9 6 7 8 9 10
                     SOA
                              ca.worldsign.org. root.ca.worldsign.org. (
                                                ; Serial
                               604800
                                                ; Refresh
                                86400
                                                ; Retry
                              2419200
                                                ; Expire
                               604800 )
                                                ; Negative Cache TTL
11 ;
12 @
12 @
13 1
                              ca.worldsign.org.
                     PTR
                              ca.worldsign.org.
14 1
                     PTR
                              crl.worldsign.org.
```

vim /etc/bind/db.root

```
17 . 3600000 IN NS root.dns
18 root.dns. 3600000 IN A 114.204.56.1
```

@ns.dreaminfo.biz

vim /etc/bind/named.conf

```
9 include "/etc/bind/named.conf.options";
10 include "/etc/bind/named.conf.local";
11 //include "/etc/bind/named.conf.default-zones";
12
13
14 view in {
               match-clients { 192.168.0.0/16; 172.16.0.0/24; 10.0.0.0/30; 10.8.0.0/24; };
    zone "dreaminfo.biz" {
17
18
               type master;
file "dreaminfo.int.zone";
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
    zone "0.16.172.in-addr.arpa" {
               type master;
file "dreaminfo.int.rev1";
    zone "0.168.192.in-addr.arpa" {
                type master;
                file "dreaminfo.int.rev2";
    zone "." {
               type hint;
                file "/etc/bind/db.root";
34
35
36
```

vim /etc/bind/named.conf.options

// 10.8.0.0/24 는 Openvpn 대역

vim /etc/bind/db.root

```
      17 .
      3600000 IN NS root.dns

      18 root.dns.
      3600000 IN A 114.204.56.1
```

vim /var/cache/bind/dreaminfo.int.rev1

```
1;
2; BIND reverse data file for broadcast zone
3;
4 $TTL 604800
5 @ IN SOA ns.dreaminfo.biz.rd
6 1; Se
7 604800; Re
8 86400; Re
9 2419200; Ex
10 604800); Ne
                                         ns.dreaminfo.biz. root.ns.dreaminfo.biz. (
                                                                   Serial
                                                                   Refresh
                                                                 ; Retry
                                                                ; Expire
                                                                ; Negative Cache TTL
11;
12 @
13 1
                                        ns.dreaminfo.biz.
                             PTR
                                        ns.dreaminfo.biz.
14 2
15 254
                             PTR
                                         file.dreaminfo.biz.
                             PTR
                                        hq.dreaminfo.biz.
16 2
                             PTR
                                         mail.dreaminfo.biz.
```

```
ns.dreaminfo.biz. root.ns.dreaminfo.biz. (
                                      ; Serial
                                      ; Refresh
                                      ; Retry
                                      ; Expire
                                      ; Negative Cache TTL
                         ns.dreaminfo.biz.
branch.dreaminfo.biz.
                  PTR
```

vim /var/cache/bind/dreaminfo.int.zone

```
1;
2; BIND reverse data file for broadcast zone
3;
4 $TTL 604800
5 © IN SOA ns.dreaminfo.biz.rd
6 _ 1 ; Se
7 604800 ; Re
                                   ns.dreaminfo.biz. root.ns.dreaminfo.biz. (
                                                        ; Serial
                                                         ; Refresh
8
9
10
                                      86400
                                                         ; Retry
                                   2419200
                                                         ; Expire
                                    604800 )
                                                        ; Negative Cache TTL
11;
12 @
13 @
                                   ns.dreaminfo.biz.
                                   172.16.0.1 mail.dreaminfo.biz.
14 @
                         MX 10
15 ns
                                   172.16.0.1
16 file
                                   172.16.0.2
17 hq
                                   192.168.0.254
                                   192.168.1.254
172.16.0.2
18 branch
19 mail
20 WWW
21 crl
                         CNAME
                                   ns.dreaminfo.biz.
                         CNAME
                                   ns.dreaminfo.biz.
                                   hq.dreaminfo.biz.
22 vpn
                         CNAME
```