ALGORITHM:
1. Initialize Counter to 1
2. Set Counter limit to 9
3. Read a number
4. Initialize Maximum to that value
5. Read a number
6. If number <= Maximum, go to (8)
7. Set Maximum to number
8. Increment Counter
9. If Counter <= Limit, go to (5)
10. Print Maximum
11. Stop

 # CODE:

```
# Maximum: $t0, Counter: $t1, Counter Limit: $t2
.text
main:   li $t1, 1                   # Initialize Cntr
        li $t2, 9                   # Initialize Cntr-Lmt
        li $v0, 5                   # load code for "read integer"
        syscall                     # read next number (into $v0)
        move $t0, $v0               # set Max to that value
next:   li $v0, 5                   # load code for "read integer"
        syscall                     # read next number (into $v0)
        ble $v0, $t0, cont          # check if < or  = Max
        move $t0, $v0               # if not, update Max
cont:   addi $t1, $t1, 1            # increment counter
        ble $t1, $t2, next          # if < limit, do again
        move $a0, $t0               # prepare argument for print
        li $v0, 1                   # load code for "print integer"
        syscall                     # will print integer in $a0
        li $v0, 10                  # load code for "stop
        syscall                     # end execution
```

 # ALGORITHM MODIFIED TO INCLUDE PROMPTS AND OUTPUT MESSAGE

```
#  1.    Initialize Counter to 1
#  2.    Set Counter limit to 9
#  3a.  Print prompt
#  3b.  Read a number
#  4.    Initialize Maximum to that value
#  5a.   Print prompt
#  5b.   Read a number
#  6.     If number <= Maximum, go to (8)
#  7.     Set Maximum to number
#  8.     Increment Counter
#  9.     If Counter <=  Limit, go to (5a)
#  10a: Print output message
#  10b. Print Maximum
#  11.   Stop
```

 # CODE:

```
# Maximum: $t0, Counter: $t1, Counter Limit: $t2
#
.data
        Prompt: .asciiz "Enter a number: "
        OutMssg: .asciiz "\n The maximum is: "
.text
main:  li $t1, 1                    # Initialize Cntr
        li $t2, 9                   # Initialize Cntr-Lmt
        la $a0, Prompt              # load prompt address
         li $v0, 4                  # load syscode for "print string"
        syscall                     # print prompt
         li $v0, 5                  # load syscode for "read integer"
        syscall                     # read next number (into $v0)
         move $t0, $v0              # set Max to that value
next:   la $a0, Prompt              # load prompt address
        li $v0, 4                   # load syscode for "print string"
        syscall                     # print prompt
        li $v0, 5                   # load syscode for "read integer"
        syscall                     # read next number (into $v0)
        ble $v0, $t0, cont          # check if < or  = Max
        move $t0, $v0               # if not, update Max
cont:   addi $t1, $t1, 1            # increment counter
         ble $t1, $t2, next         # if < limit, do again
        la $a0, OutMssg             # load output-message address
        li $v0, 4                   # load syscode for "print string"
         syscall                    # print output message
         move $a0, $t0              # prepare argument for print
```

```
li $v0, 1                    # load syscode for "print integer"
 syscall                     # will print integer in $a0
li $v0, 10                   # load code for "stop
syscall                      # end execution
```