

Trade one account. **The rest follow.**

STRATUH Copier mirrors trades from your **master** account to your **follower** accounts, live, inside the Vest page. It runs in your own logged-in browser, acts only on your trades, and only while **armed**.

#### ■ You trade the master

Place, manage and close trades on Vest exactly as you normally do.



#### ■ The copier sees the order

It watches your master's order requests in the page, then fires matching orders.



#### ■ Followers mirror it

Open

Add

Reduce

Stop / TP

Close

Cancel

## 01 INSTALL

- 1 Add **Tampermonkey** from your browser's store (Chrome Web Store, Edge Add-ons or Firefox Add-ons). In Chrome, Edge or Brave: `chrome://extensions` > Tampermonkey > Details > turn on **Allow User Scripts**.
- 2 Install from `github.com/xAmped/Vest-Copier` (it then auto-updates), or paste `vest-copier.user.js` into a new Tampermonkey script.
- 3 Open or refresh **next.vestmarkets.com** — the panel appears top-right.  
New versions show as a bar in the panel: click Install. Settings are kept.

## 02 SET UP & ARM

- 1 Your accounts load automatically (click `u` to reload). A green dot means the account can trade.
- 2 Click `M` on your master, then `FLW` on each follower.  
Strict 1:1 needs matching size & type. For mixed sizes, turn on Cap-to-fit first.
- 3 Set the leverage you'll use on Vest for the session.
- 4 Click `ARM`. The first time, accept the one-time agreement.  
Everyone flat, or already in the same trade (it's adopted).
- 5 Trade the master normally. Every copy is logged.
- 6 Click `DISARM` when you're done. It stops copying; it doesn't close positions.

**Trade tab:** follows Vest's market. Margin and risk bars, a price ladder in points, risk or max sizing, limits from a chart click, and in a trade Breakeven, Close and add chips. Changed leverage or market? **Disarm and arm again.**

## 03 SIZING

### DEFAULT Strict 1:1

Followers copy the master's exact size. Same size & type only.

### SETTINGS > CAP-TO-FIT Sized to each account

Sized to its own equity. Same stop, same % risk.

```
follower size =
  master size × follower equity ÷ master equity
// e.g. 25k master 10.00 · 5k follower 1.90
```

## 04 OPTIONS & SAFETY

|                     |                                                                                                           |
|---------------------|-----------------------------------------------------------------------------------------------------------|
| <b>Fast mode</b>    | Fires follower entries the instant you send yours, before the master confirms.                            |
| <b>Auto-flatten</b> | Closes followers left in a trade without the master.                                                      |
| <b>Flatten All</b>  | Closes all positions and orders on every loaded account. Instant, no confirmation. Stays armed.           |
| <b>Fill check</b>   | Names any account that didn't fill, master included.                                                      |
| <b>Not copied</b>   | Refused orders; closes Vest forces (breach, liquidation).                                                 |
| <b>Records</b>      | <code>P&amp;L</code> totals · <code>CSV</code> log · <code>Diag</code> report (token-free, safe to send). |
| <b>Status</b>       | Bottom right. Amber after a Vest update: click it to run the site check, then accept.                     |

## 05 GOOD HABITS

- ✓ **Start tiny.** Test one small trade across all accounts first.
- ✓ **Stay flat** between sessions and disarm when not trading.
- ✓ **Leave headroom.** Don't run the master at 100% margin in strict 1:1.
- ✓ **Size for the worst case:** a loss on every account at once.
- ✓ **Disarm** before any manual trade you don't want copied.
- ✓ **Something off?** Click `Diag` and send the file.

## 06 TROUBLESHOOTING

**No panel?** Turn on **Allow User Scripts**, then refresh Vest.

**Can't pick a follower?** It's a different size or type. Turn on Cap-to-fit, or match accounts.

**Won't arm?** The log names the account and the reason.