

+ Many Skies the canvas above one dashboard · pages, tending, Pro, the wall · card-agnostic

A person can keep several skies and swipe between them. Direction B, committed: two altitudes inside one Tend. The dial still flips between looking and tending, exactly as shipped — and in Tend, the page dots grow into a pressable capsule: press them and the view rises to page altitude, where whole dashboards are the tiles. Every card here is a generic placeholder — the frame is the design; the faces come later.

Glance · a sky → swipe · the next sky → dial · Tend this sky's cards → press the dots · the skies → tap a sky · descend → dial · Glance

The dots are the door

In Tend the page dots grow a capsule and become pressable — the control that shows the set is the control that opens it. Press: the skies. Tap a sky: back down — to.

Nameless until named

Skies are dots, not names. An optional label lives only at page altitude (and in the wall's hold chrome). Glance never grows text — to.

Swipe never edits

Swiping means the next sky — in Glance and in Tend alike. Edit entry is only the deliberate dial flip (or holding a card). Nothing structural rides on a gesture a sleeve can brush — to.

The wall hangs one sky


Hanging chooses one dashboard. Cycle is opt-in, slow, off by default, set from the phone. The wall stays glance-only; its hold shows where you are, never an edit surface — to, to.

Scope: every tile is the standard card with a neutral value block — no card interiors (a later chat). The Pro payroll screen is a later chat too; only its trigger lives here. Pro has exactly two doors: both "more places to look", a second sky (to) and the wall. Single-sky Tend is unchanged from The Sky Fills In; the guided front door is Raising the Sail. Web render stands in for React Native.

1a The paged canvas — Glance


swiping is a page turn; dots wake with a touch and sink like the dial

IDLE — NO CHROME, NO DOTS




One sky and nothing else. No dots on an idle surface — a second dashboard adds zero pixels to the thing you stare at all day.

MID-SWIPE — THE NEXT SKY SLIDES IN



The touch that swipes also wakes the chrome — dial and dots appear together, for five seconds. A page turn can never edit: in Glance nothing under the finger can move.

SETTLED — DOTS LINGER, THEN SINK




Five seconds after the finger lifts, dots and dial sink together and the sky is bare again. Each sky keeps its own arrangement and its own worst news — a stale dot travels with its card.

Why dots and not names on the glance surface: a label is a thing to read; a dot is a thing to know. Two to three skies is the honest case — at that count, position is identity. Names exist, optionally, one altitude up (to).

1b The seam — one dial, two altitudes


Tend opens on this sky's cards, exactly as shipped; the dots are the door up

CARD ALTITUDE — TEND, SKY 2 OF 2



Everything from the shipped single-sky Tend, unchanged — plus one new feat: the dots have grown a capsule. Information became a button. Swiping here still turns the page.

PAGE ALTITUDE — THE SKIES



Whole dashboards become the tiles — the dots, grown. The current sky arrives ringed (the same selection language as a card). Actions belong to the ringed sky; the + silver waits at the end. Tap a sky to descend into its cards; the dial exits to Glance from either altitude.


Why the two levels never blur: they show different subjects at different scales. Card altitude is full-size cards with sockets; page altitude is whole skies at thumbnail size, centered, with air around them. You cannot mistake one for the other, and the same two moves — tap to select, hold to drag — mean the same thing at both.

Entry stays accident-proof: the capsule is a small target pressed on purpose, inside a mode already entered on purpose. The pinch is the fast lane for people who think spatially (pinch in Tend rises; spread at page altitude descends). Holding a card in Glance still drops straight into card Tend — unchanged.

1c The placeholder card — states and sizes


the contract every future face must fit; flip "Worst case" in Tweaks to stress it

SIX STATES, ONE TILE



Status is a badge or a dot, never a fill. Connecting shimmers in skeleton greys with the one allowed pulse; a ghost is transparent — an invitation, not a card pretending to be fit.

FOUR SIZES ON THE PHONE GRID




S 1x1 · M 1x2 · W 2x1 · L 2x2 on a two-column, 96px-row grid (24px gutters on the wall). The rule for every future face: the value never shrinks below its step; detail truncates first, then drops.

1d Tending cards — move, add, configure


card altitude; select is shown at 1b; resize reflows neighbors live

MOVE — HOLD, LIFT, A SLOT OPENS




The held card lifts one surface step; a hairline slot opens where it will land. Carry it to the screen's edge and hold — the next sky slides in under it (the silver at right), so a card can move between skies without ever leaving your finger.

ADD — THE CATALOG, PRICED PLAINLY



Generic rows grouped by service: connected cards say Add and land as the small size where the drag began; unconnected ones state their price — a sign-in, a key — exactly the language of the ghosts. Add never leaves Tend.

CONFIGURE — A CARD'S OWN SHEET




Options opens the card's own sheet — rows are placeholders here; each face brings its own in a later chat. The frame guarantees only the header, the row anatomy, and Remove at the bottom as the second path to deletion.

1e Tending skies — reorder, label, delete


page altitude; the same two moves — tap to select, hold to drag

REORDER — HOLD A SKY, CARRY IT




The held sky lifts and its slot waits as a hairline. Order here is the swipe order — and the dots' order everywhere.

LABEL — OPTIONAL, TAP UNDER THE SKY



A label is a note to self, not chrome: it shows here and in the wall's hold capsule (to) — never on Glance, never in the dots. Clear the text to return a sky to namelessness.

DELETE — THE SKY ITSELF ASKS



No modal — the tile's face becomes the question, and tapping anywhere else is Keep. Connections survive (they belong to the account); only the arrangement dies. The last sky can't be deleted, only emptied.

1f The second sky — the Pro moment, two takes


a free person taps + an invitation, never a wall · the payroll screen is a later chat

TAKE A — THE DOOR ANSWERS



The + silver opens into this face in place — same motion as a real new sky, so the answer is spatial, not a popup. One line, one quiet door, and tapping elsewhere closes it. Zero ceremony.

TAKE B — THE SAIL BRINGS IT



The mascot returns for exactly one breath — the sail bobs once on the sheet, gold as it was at the front door. Warmer, names both Pro doors at once; costs a sheet and a little restraint.

THE CALL BETWEEN THEM


A holds the product's temperature: the invitation is architecture, not theater, and it can't interrupt anything. B spends the mascot's scarce budget to make the one revenue moment feel like the front door did.

My lean: A on the canvas, B's copy. If the sail appears at every paid door it stops being a guest.

1g A new sky — the creation moment, two takes


a Pro person taps + the view descends into the new, empty dashboard

TAKE A — DEALT DARK



Honest and silent: a dark field, one plain sentence, one door. The third dot simply exists now — the before → after is the dot row growing.

TAKE B — STARTS WITH A LIGHT



The sail deals one card — the Clock, the free light every sky can afford — with the same gust as the front door, then leaves. The sky is born lit, and the empty slot below already shows where the next card lands.

THE CALL BETWEEN THEM


B answers the coldest moment in the model — a brand-new empty surface — with the product's one belief: nothing here is over a blank form, it's a sky that fights. It also teaches removal (don't want the Clock? Remove is right there).

A is the stricter reading of "never loud." My lean: B — this is a delight moment the brief explicitly budgets for, and it echoes first-run.

1h Hang on a wall — choose a sky, set the cycle


page altitude is where skies meet places; first-time pairing reuses the code flow from Raising the Sail

HUNG — THE SKY WEARS A QUIET MARK



Hanging a different sky simply moves the mark — one wall, one chosen sky. The accent dot under the tile is the only place "on the wall" is ever stated; the Pro badge appears on this door only for free accounts.

THE WALL SHEET — CYCLE LIVES HERE




Cycle ships off — a wall that changes by itself must be asked for. Dwell is minutes, not seconds; the wall is weather, not a slideshow. All of this is set from the phone; the wall itself is never driven by touch.

1i The wall with many skies


glance-only, landscape · one hung sky · the cycle and the hold are the whole story

HUNG — THE CHOSEN SKY, NOTHING ELSE




No dots, no dial, no hint that other skies exist — a wall showing chrome about elsewhere would never stop whispering. One pulse maximum, as ever.

CYCLE ON — MID-DISSOLVE, MINUTE 15



An 800ms dissolve on the calm curve, then stillness for another quarter hour. The dots surface only during the change — three seconds to say where you landed — then sink, the sky with nothing to show are skipped.

A ONE-SECOND HOLD — WHERE AM I, AND WHO EDITS



The hold answers the only two questions a wall can be asked — which sky is this, and where do I change it — then sinks after five seconds. It supersedes the earlier wall-Tend hold from The Sky Fills In: with this brief the wall is glance-only, and the phone is the only editor.

Then sink, the sky with nothing to show are skipped. The dots surface only during the change — three seconds to say where you landed — then sink, the sky with nothing to show are skipped. The dots surface only during the change — three seconds to say where you landed — then sink, the sky with nothing to show are skipped.

Then sink, the sky with nothing to show are skipped. The dots surface only during the change — three seconds to say where you landed — then sink, the sky with nothing to show are skipped. The dots surface only during the change — three seconds to say where you landed — then sink, the sky with nothing to show are skipped.