




0 · Base (Enthium)





1 · Numbers & Symbols



2 · Navigation & Editing




3 · System & Function



# Navigation modes

The EXTEND layer cursor cluster, with Select / Delete / Tabs sub-modes layered on top.



| Key  | Navigation   | Select               | Delete               | Tabs         |
|------|--------------|----------------------|----------------------|--------------|
| ◀    | Char left    | Select char left     | Backspace            | Previous tab |
| ▶    | Char right   | Select char right    | Forward-delete       | Next tab     |
| ▲    | Line up      | Select line up       | ·                    | New tab      |
| ▼    | Line down    | Select line down     | ·                    | Close tab    |
| ◀◀   | Word back    | Select word back     | Delete word back     | Page back    |
| ▶▶   | Word forward | Select word forward  | Delete word forward  | Page forward |
| ⏮    | Line start   | Select to line start | Delete to line start | ·            |
| ⏭    | Line end     | Select to line end   | Delete to line end   | ·            |
| PgUp | Page up      | Select page up       | ·                    | ·            |
| PgDn | Page down    | Select page down     | ·                    | ·            |
| ●    | ·            | ·                    | ·                    | Reopen tab   |

· no special role in that mode — the key keeps its Navigation behaviour. Tab actions are OS-aware (Firefox & Chrome, macOS & Linux).  
Select and Delete are mutually exclusive — while Delete is held the Select key is inert.

# Compose & diacritics

Press Shift + Space on the base layer to arm Compose, then press one key.

**Arm**  
**Shift + Space** from the base layer

**Cancel**  
**Esc** any other key types as usual

| Key | Produces                                            | Example             |
|-----|-----------------------------------------------------|---------------------|
|     | <b>DEAD KEYS</b> — press, then type the base letter |                     |
| e   | ´ acute                                             | Shift+Space e e → é |
| a   | ` grave                                             | Shift+Space a e → è |
| u   | ¨ diaeresis                                         | Shift+Space u e → ë |
| o   | ^ circumflex                                        | Shift+Space o e → ê |
|     | <b>DIRECT</b> — prints the character immediately    |                     |
| c   | ç                                                   | Shift+Space c → ç   |
| n   | ñ                                                   | Shift+Space n → ñ   |
| w   | € euro                                              | Shift+Space w → €   |

Dead keys wait for a base letter, so the same accent works on any vowel (é á í ó ú · è à ì ò ù ...). Accents are OS-aware (macOS & Linux).