






0 · Base (Enthium)





1 · Numbers & Symbols



2 · Navigation & Editing



3 · System & Function



Navigation modes

The EXTEND layer cursor cluster, with Select / Delete / Tabs sub-modes layered on top.

Navigation Engage Hold the EXTEND key Exit Release (or Layer Lock)	<i>base</i>	Select Engage Tap — toggle Exit Tap again / Esc	<i>SI</i>	Delete Engage Hold Exit Release (hold-only)	<i>DI</i>	Tabs Engage Hold Exit Release (hold-only)	<i>hold</i>
---	-------------	--	-----------	--	-----------	--	-------------

Key	Navigation	Select	Delete	Tabs
	Char left	Select char left	Backspace	Previous tab
	Char right	Select char right	Forward-delete	Next tab
	Line up	Select line up	.	New tab
	Line down	Select line down	.	Close tab
	Word back	Select word back	Delete word back	Page back
	Word forward	Select word forward	Delete word forward	Page forward
	Line start	Select to line start	Delete to line start	.
	Line end	Select to line end	Delete to line end	.
PgUp	Page up	Select page up	.	.
PgDn	Page down	Select page down	.	.
	.	.	.	Reopen tab

· no special role in that mode — the key keeps its Navigation behaviour. Tab actions are OS-aware (Firefox & Chrome, macOS & Linux).
Select and Delete are mutually exclusive — starting a deletion clears an active selection latch.

Compose & diacritics

Press Shift + Space on the base layer to arm Compose, then press one key.

Arm

Shift + Space from the base layer

Cancel

Esc any other key types as usual

Key	Produces	Example
	DEAD KEYS — press, then type the base letter	
e	´ acute	Shift+Space e e → é
a	` grave	Shift+Space a e → è
u	¨ diaeresis	Shift+Space u e → ë
o	^ circumflex	Shift+Space o e → ê
	DIRECT — prints the character immediately	
c	ç	Shift+Space c → ç
n	ñ	Shift+Space n → ñ
w	€ euro	Shift+Space w → €

Dead keys wait for a base letter, so the same accent works on any vowel (é á í ó ú · è à ì ò ù ...). Accents are OS-aware (macOS & Linux).