

EasySave v3.0

User Manual — Quick Start Guide

What is EasySave?

EasySave is a backup tool that copies files from one location to another. Version 3.0 introduces parallel job execution, real-time job control, priority file management, large file bandwidth limiting, and centralized log management via Docker. The graphical interface and console application from v2.0 remain available.

What's New in v3.0?

- Parallel backup execution — all jobs run simultaneously.
- Pause, Resume, and Stop controls per job and for all jobs.
- Real-time progress percentage per job.
- Priority file extensions — copied before all other files.
- Large file limit — only one large file transfers at a time (configurable threshold).
- Business software detection now pauses jobs and auto-resumes when software closes.
- Docker log centralization — logs sent to a central server in real time.
- Full GUI language switching — labels update immediately when language is changed.

System Requirements

Component	Requirement
.NET Runtime	.NET 8.0
Operating System	Windows 10 / Windows Server 2016 or later
Docker (optional)	Docker Desktop with WSL2 (for log centralization)
Permissions	Read on source directory, write on target directory

Starting the Application

- Launch EasySave.GUI.exe to open the graphical interface.
- The main window shows your backup jobs, status, and quick action buttons.
- Use + Add to create your first backup job.
- Click Settings to configure all preferences.
- The console app (EasySave.exe) is still available for command-line use.
- To enable Docker log centralization, start Docker Desktop and run docker-compose up in the docker-server folder before launching EasySave.

Managing Backup Jobs

Button	Action
+ Add	Create a new backup job (name, source, target, type)
Edit	Modify the selected job

Delete	Remove the selected job
Run	Execute the selected job in parallel with others
Run All	Execute all jobs in parallel
Pause	Pause selected job after current file completes
Resume	Resume a paused job
Stop	Immediately stop the selected job

Backup Types

Type	Behaviour
Full	Copies every file from source to target on every run, overwriting existing files.
Differential	Copies only new or modified files since the last backup.

Settings

Setting	Description
Log Format	Choose JSON or XML for the daily log file.
Language	Application language (English / French / Spanish). Updates GUI immediately.
CryptoSoft Path	Full path to CryptoSoft.exe for file encryption.
Business Software	Process names that pause all backups when detected.
Extensions to Encrypt	File extensions to encrypt after backup (e.g. .txt, .docx).
Priority Extensions	Extensions copied before all other files (e.g. .pdf).
Large File Limit (KB)	Files above this size cannot transfer simultaneously. Default: 1024 KB.
Log Centralization	Local only, Remote only (Docker), or Both.
Docker Server URL	URL of the Docker log server. Default: http://localhost:5050/log

Command-Line Mode (console app)

- EasySave.exe 1-3 — runs jobs 1, 2 and 3 in parallel
- EasySave.exe 1;3 — runs jobs 1 and 3

Log File Locations

- Daily log (local): %APPDATA%\EasySave\Logs\YYYY-MM-DD.json (or .xml)
- Daily log (Docker): docker-server/logs/YYYY-MM-DD.json
- Live state: %APPDATA%\EasySave\State\state.json
- Job config: %APPDATA%\EasySave\config.json
- Settings: %APPDATA%\EasySave\settings.json

Support Contract

5/7, 8h – 17h. Updates included. Annual renewal with SYNTEC index revaluation. For assistance contact the ProSoft support team and provide your log file.