

Main example, download as py file and execute via command box / prompt calling PYTPRA_02_04_MLPdeploy.py RETURN Note that this is only a sketch, u may improve it to a sensible solution to be deployed and integrated in batch

```
In [1]: #torch
import torch
import os

global_var = 2.0
```

```
In [2]: def set_target_directory():
    targetDirectory = "C:\\\\CASES\\\\PYTPRA"
    os.chdir(targetDirectory)
    return True #returning an explicit true helps you in checking successful execution
#otherwise None is returned, i.e. we make the function fruitful
```

```
In [3]: def get_model_weight():
    #then we can load and maybe write a main-style program for batch exe
    loaded_model = torch.load("car_mlp_pt.pt", map_location = 'cpu')#avoid default access to GPU
    ret_val = loaded_model.get('0.weight')[0,1].detach().numpy()
    return ret_val
```

```
In [4]: def show_model():
    #then we can load and maybe write a main-style program for batch exe
    loaded_model = torch.load("car_mlp_pt.pt", map_location = 'cpu')#avoid default access to GPU
    #diags of learning process
    print("\nParams of Pytorch Net car_mlp_pt")
    print(loaded_model)
    #if u want to adress specific elements might make a List of it - but not useful
    #loaded_model_list = list(loaded_model)
    #print("\nVia List:", loaded_model_list[3])
    print("\nWhat is available:", dir(loaded_model))
    print("\nDirect Access to 2nd weight:", loaded_model.get('0.weight')[0,1].detach().numpy())
    return
```

```
In [5]: def make_forecast(gv_arg):
    user_input = float(input('\nGib zuletzt gefahrene KM ein! '))

    if user_input <= 0:
        print('Invalid Input! Nur pos Zahlen!!')
    else:
```

```
    print("Wertverlust in EUR", gv_arg * user_input)  
    return (max (0, gv_arg * user_input))
```

```
In [6]: def main():  
        print("\nMAIN STARTS")  
        set_target_directory()  
        global_var = get_model_weight()  
        make_forecast(global_var)  
        print("\nMAIN DONE")
```

```
In [7]: main() #this is the main program
```

MAIN STARTS

Gib zuletzt gefahrene KM ein! 10

Wertverlust in EUR -4.822861552238464

MAIN DONE