Ubuntu开发环境搭建

```
1 编译FFmpeg
```

2 安装qt-5.12.10

安装QT

如果报错

ubuntu安装qt5 Could not load the Qt platform plugin "xcb" in "" even though it was found.

Ubuntu16.04打开Qt显示/home/user/.config/QtProject/qtcreator/qtversion.xml: Permission denied

3 QT使用FFmpeg

linux_1-ffmpeg

linux_2-sdl

linux_3-ffmpeg-extract-aac

腾讯课堂 零声学院

FFmpeg/WebRTC/RTMP音视频流媒体高级开发 https://ke.qq.com/course/468797?tuin=137bb271

Darren QQ 326873713

虚拟机版本: VMware 14 Linux版本: Ubuntu 16.04

QT版本: QT-5.12

1 编译FFmpeg

FFmpeg版本: 4.2.1

参考《零声学院 音视频高级教程 ubuntu ffmpeg开发环境搭建0.2》

2 安装qt-5.12.10

安装QT

https://blog.csdn.net/lzp_k2/article/details/82662112

下载地址: https://download.qt.io/archive/qt/

下载地址: https://download.qt.io/archive/qt/5.12/5.12.10/

qt-opensource-windows-x86-5.12.10.ex		09-Nov-2020 08:13	3.7G	Details
t-opensource-mac-x64-5.12.10.dmg	苹果	09-Nov-2020 08:10	2.7G	Details
gt-opensource-linux-x64-5.12.10.run	Ubuntu	09-Nov-2020 08:07	1.3G	Details
■ md5sums.txt		09-Nov-2020 08:16	210	Details

如果报错

ubuntu安装qt5 Could not load the Qt platform plugin "xcb" in "" even though it was found.

https://blog.csdn.net/u012768805/article/details/98756925

需要安装:

sudo apt install --reinstall libxcb-xinerama0

Ubuntu16.04打开Qt显

示/home/user/.config/QtProject/qtcreator/qtversion.xml: Permission denied

权限不够所导致, 执行命令 sudo chown -R user:user ~/.config/即可解决。

默认需要使用sudo权限启动

不是sudo权限也能启动则需要修改权限

语法: sudo chown -R username:username ~/.config/比如我的ubuntu:

```
1 sudo chown -R lqf:lqf ~/.config/
```

3 QT使用FFmpeg

linux_1-ffmpeg

pro文件写法

```
1 \text{ TEMPLATE} = app
 2 CONFIG += console
 3 CONFIG -= app bundle
 4 CONFIG -= qt
 6 SOURCES += \
           main.c
 8 INCLUDEPATH += /home/lqf/ffmpeg_build/include
10 LIBS += /home/lqf/ffmpeg_build/lib/libavcodec.a \
           /home/lqf/ffmpeg_build/lib/libavdevice.a \
11
12
           /home/lqf/ffmpeg_build/lib/libavfilter.a \
           /home/lqf/ffmpeg_build/lib/libavformat.a \
13
           /home/lqf/ffmpeg_build/lib/libavutil.a \
14
           /home/lqf/ffmpeg_build/lib/libswresample.a \
15
           /home/lqf/ffmpeg_build/lib/libswscale.a
16
17
```

main.c

```
1 #include <stdio.h>
```

```
3 // 包含ffmpeg头文件
4 #include "libavutil/avutil.h"
5
6 int main()
7 {
8     printf("Hello FFMPEG, version is %s\n", av_version_info());
9
10     return 0;
11 }
```

linux_2-sdl

```
下载地址: https://www.libsdl.org/download-2.0.php
1. 下载SDL源码库,SDL2-2.0.10.tar.gz
2. 解压,然后依次执行命令
./autogen.sh
./configure --prefix=/home/lqf/ffmpeg_build --bindir=/home/lqf/binmake
sudo make install
linux_2-sdl-basic项目
```

linux_3-ffmpeg-extract-aac

重点看

工程的pro文件